Maxwell Bloch Solver

User Guide

Version 8.4

Vahid Anari

vahid.anari8@gmail.com

This document describes the interactive desktop application for solving the Maxwell–Bloch equations, exploring driven coherent radiative regimes, and comparing model results with astronomical light curves.

Contents

1 Overview **3**

2 Physical Model **3**
2.1 Numerical Method 4
2.2 Drive Profiles 4

3 Getting Started **4**
3.1 Launching the Application 4
3.2 Operating Modes 5
3.3 Main Window Layout 5

4 Parameter Tabs **5**
4.1 Sample Tab 5
4.2 Grid Tab 5
4.3 Slice Tab 6
4.4 Dynamics Tab 6
4.5 ICs Tab 6
4.6 BCs Tab 6
4.7 Pump 1 and Pump 2 Tabs 6
4.8 Fit Mode Tab 7
4.9 Range Tab 7

5 The Plot Area **7**
5.1 Top Panel 7
5.2 Bottom Panel 7
5.3 Cosh-Peak Marker 8

6 Fit Mode **8**
6.1 Loading a Data Folder 8
6.2 Velocity Navigation 9
6.3 Save and Unsave Behaviour 9
6.4 Mismatch Readout 9
6.5 Closing Data 9

7 File Menu Reference **10**

8 View Menu Reference **10**

9 Info and Help Menus **10**

10 Exporting Plots **11**

11 Saving and Loading Parameters **11**
11.1 Saved JSON Structure 11
11.2 App Defaults 11

12 Typical Workflows **11**
12.1 Standalone Simulation Workflow 11

12.2 Observational Fitting Workflow 12

13 Troubleshooting **12**

1 Overview

Maxwell Bloch Solver is a desktop GUI application for numerically solving the Maxwell–Bloch equations and visualizing the resulting intensity, inversion, pump, and boundary-field profiles. The app is intended for coherent-radiation problems in which a driven resonant medium is modeled with a one-dimensional Maxwell–Bloch system.

In astrophysical work, the same framework can be used to study several regimes, including:

- steady or slowly varying **maser** amplification,
- transient **superradiant** bursts,
- weakly radiative or suppressed-response regimes that may be interpreted as **subradiant** behaviour depending on the chosen initial conditions and relaxation times.

The application provides:

- interactive parameter editing with sliders, line edits, and combo boxes,
- automatic re-solving when physical solver parameters change,
- two operating modes: **standalone simulation** and **fit mode**,
- overlay of simulation results with observational light curves,
- JSON-based parameter/configuration saving,
- export of the current figure to PDF, PNG, or SVG,
- a PDF export report containing metadata and the current parameter state.

Note

The app is designed around fast interactive exploration. In normal use, there is no separate "Run" button: changing a solver parameter triggers a new solve automatically.

2 Physical Model

The solver evolves a dimensionless one-dimensional Maxwell–Bloch system for a driven two-level medium. The equations solved by the application are

$$\frac{\partial w}{\partial \tau'} = A' R - \frac{w - w_0}{T_1'} + \Lambda_n', \tag{1}$$

$$\frac{\partial R}{\partial \tau'} = -A' w - \frac{R - R_0}{T_2'}, \tag{2}$$

$$\frac{\partial A'}{\partial z'} = -\eta R, \tag{3}$$

where w is the population inversion, R is the medium coherence, and A' is the dimensionless field envelope. The solver works in normalised variables, with $\tau' = \tau/T_0$ and $z' = z/L$ a propagation coordinate normalised to the sample length L.

Symbol	Meaning
$w(\tau', z')$	Population inversion $\rho_{22} - \rho_{11}$
$R(\tau', z')$	Coherence envelope ($= \rho_{21}$ slowly varying)
$A'(\tau', z')$	Dimensionless field envelope
$\tau' = \tau/T_0$	Normalised retarded time
$z' = z/L$	Normalised propagation distance
$T_1' = T_1/T_0$	Longitudinal relaxation time
$T_2' = T_2/T_0$	Transverse dephasing time
$\eta = T_0/T_R$	Dimensionless coupling parameter
$\Lambda_n' = T_0\Lambda_n$	Dimensionless pump rate
w_0, R_0	Equilibrium inversion and coherence

The physical reference time T_0 is set in the **Sample** tab. By default, $T_0 = 86400\,\mathrm{s}$ (one day), but any positive value may be used. The derivation of these equations from first principles is given in the companion Equations Reference document.

2.1 Numerical Method

The application solves the system numerically on a time–space grid. The matter variables are advanced in time with a fourth-order Runge–Kutta scheme, while the field is propagated through the spatial grid. Performance-critical loops are accelerated with Numba.

2.2 Drive Profiles

The boundary field and pump terms are entered through the GUI as sums of hyperbolic-cosine components. In the symmetric case, the profile displayed by the app corresponds to a sum of sech^2 pulses,

$$f(\tau) = \sum_{i=0}^{N-1} a_i \,\mathrm{sech}^2\left(\frac{\tau - \tau_0^i}{w^i}\right). \tag{4}$$

In asymmetric mode, each component instead uses separate left and right widths,

$$w^i = \begin{cases} w_l^i, & \tau < \tau_0^i, \\ w_r^i, & \tau > \tau_0^i. \end{cases} \tag{5}$$

An optional spacing control may also be enabled so that the centers follow

$$\tau_0^i = \tau_0^0 + i\,\tau_p. \tag{6}$$

This is useful for repeated pump or boundary components with a regular separation.

3 Getting Started

3.1 Launching the Application

From the project root directory, run

```
python main.py
```

A splash screen appears during startup, followed by the main window.

3.2 Operating Modes

The application has two main modes.

1. **Standalone simulation mode:** used when no data folder is loaded. The app solves the Maxwell–Bloch system directly from the current parameters.
2. **Fit mode:** entered after loading a light-curve folder. In this mode, the top panel overlays observational data and the model curve for one selected velocity component.

3.3 Main Window Layout

The main window is divided into three user-facing areas.

- **Top toolbar (fit mode only):** velocity navigation, save/unsave controls, an "Only saved velocities" filter, and a χ^2-style mismatch readout.
- **Central plot area:** two vertically stacked panels that share the time axis. The top panel shows intensity or flux; the bottom panel shows one selected auxiliary curve.
- **Parameter tabs:** organized controls for the sample, solver grid, initial conditions, driving terms, fit alignment, and display ranges.

A small selector labeled **Bottom Plot** appears beside the velocity controls and chooses which auxiliary quantity is shown in the lower panel.

4 Parameter Tabs

4.1 Sample Tab

The **Sample** tab defines the global physical scaling:

Parameter	Symbol	Description
Transition frequency	ν	Line frequency
Spontaneous emission rate	Γ	Einstein-A-type rate
Time scale	T_0	Physical reference time
Sample length	L	Physical propagation length
Number density	n_0	Medium number density

From these values, the app derives internal scaling quantities such as the coupling constant η. The expression used by the app can be viewed from `Info` → `Scaling Formula`.

4.2 Grid Tab

The **Grid** tab controls the numerical resolution:

Parameter	Symbol	Description
Time points	N_t	Number of time-grid samples
Spatial points	N_z	Number of propagation steps
Total time span	$T_{\max}$	Simulation duration in units of T_0

Increasing N_t or N_z generally improves resolution but also increases solve time.

4.3 Slice Tab

The **Slice** tab selects which spatial position is shown in the plots. The displayed solution is taken from one sampled z plane within the interval $[0, 1]$. Changing only the selected slice updates the displayed curve immediately. If the underlying slice array length is changed, the app performs a new solve.

4.4 Dynamics Tab

The **Dynamics** tab sets the relaxation parameters:

Parameter	Symbol	Description
Population relaxation	T_1	Longitudinal relaxation time
Dephasing	T_2	Transverse dephasing time

These are entered in units of T_0.

4.5 ICs Tab

The **ICs** tab defines the initial state of the medium. Two input styles are available:

- θ_0 **mode:** the initial state is set through a Bloch-angle parameter.
- **Direct mode:** the initial inversion and coherence are entered directly as $w|_{\tau=0}$ and $R|_{\tau=0}$.

This tab is especially important when exploring the transition between weak response, maser-like response, and superradiant burst behaviour.

4.6 BCs Tab

The **BCs** tab defines the boundary field $A|_{z=0}(\tau)$. Unlike a single-pulse editor, this widget supports a **multi-component** profile:

- N: number of components,
- i: currently edited component index,
- component amplitude A^i,
- center τ_0^i,
- either a symmetric width w^i or asymmetric widths w_l^i and w_r^i,
- optional regular spacing via τ_p.

Additional checkboxes allow the user to force all components to share the same amplitude and/or widths. The **Show values** button opens a table of all component values.

4.7 Pump 1 and Pump 2 Tabs

The **Pump 1** and **Pump 2** tabs define two independent contributions to the total pump,

$$\Lambda_n(\tau) = \Lambda_n^{(1)}(\tau) + \Lambda_n^{(2)}(\tau). \tag{7}$$

Each tab uses the same multi-component editor described above for the BCs tab. This makes it easy to build single-pulse, repeated-pulse, or multi-episode pumping scenarios.

4.8 Fit Mode Tab

The **Fit Mode** tab is enabled only when a data folder is loaded. It does not change the physical solve itself. Instead, it controls the conversion, alignment, and scaling used when the model is displayed against data.

Control	Description
Data time unit	Time unit used for the imported data axis (d, h, m, s, ms, μs, ns)
Data flux unit	Flux unit for the imported data (currently Jy)
Data time offset	Constant shift applied to the loaded data times
Results time offset	Horizontal shift applied to the model curve
Intensity scale	Vertical scale applied to the displayed model intensity

Note

In fit mode, the displayed model curve is rescaled for plotting. The time axis is converted using the chosen data unit, and the intensity is peak-normalized internally before the user-selected display scale is applied.

4.9 Range Tab

The **Range** tab controls the visible axis limits for:

- time,
- top-panel flux/intensity,
- w,
- Λ_n,
- $A|_{z=0}$.

Each quantity uses a two-handle range slider.

5 The Plot Area

5.1 Top Panel

The top panel shows:

- **standalone mode:** model intensity $I(t)$,
- **fit mode:** observational flux points together with the transformed model curve.

In fit mode, the plotted data points come from the loaded light-curve file for the currently selected velocity.

5.2 Bottom Panel

The bottom panel displays one auxiliary quantity chosen from the **Bottom Plot** selector:

Option	Displayed quantity
w	Population inversion at the selected z slice
Λ_n	Total pump profile
$A\|_{z=0}$	Boundary field $A\|_{z=0}$

5.3 Cosh-Peak Marker

When a BC or pump tab is active, the app can display a marker for the currently selected component. A vertical line marks the component center and a shaded region indicates the width. This marker is shown only when it is relevant to the currently selected bottom-panel quantity:

- BC marker with bottom plot $A|_{z=0}$,
- pump marker with bottom plot Λ_n.

6 Fit Mode

Fit mode is used to compare the model with observed light curves one velocity component at a time.

6.1 Loading a Data Folder

To enter fit mode:

1. choose `File` → `Open Data Folder...` (`Ctrl+Shift+O`),
2. select the folder containing the data files,
3. if more than one period group is present, choose the desired period,
4. review the import summary dialog.

If matching saved parameters already exist in the folder, they are loaded automatically.

Expected File Naming

The application expects filenames of the form

```
SourceName_v=12.3.txt
SourceName_p1_v=12.3.txt
```

where the optional token `p1`, `p2`, ... is a period label and `v=` denotes the velocity.

Folder Rules

A valid data folder should satisfy the following conditions:

- all valid files belong to the same source,
- files are either all period-tagged or all non-period-tagged,
- each light-curve file is plain text,
- the app reads the **first two numeric columns** as time and flux,
- blank lines and lines beginning with `#` are ignored.

Important

`File` → `Open Parameters...` is intended for standalone parameter snapshots, not for fit-mode source files. Fit-mode parameter sets are loaded automatically from the selected data folder.

6.2 Velocity Navigation

Once a data folder is open, the velocity toolbar becomes active. You can:

- move to the previous or next component,
- choose a component directly from the drop-down list,
- filter the list with **Only saved velocities**,
- save or unsave the current component.

Each velocity component has its own stored parameter state.

6.3 Save and Unsave Behaviour

In fit mode, pressing **Save** or using `Ctrl+S` saves the current velocity's parameters into a single source-level JSON file in the loaded folder:

```
SourceName_params.json
SourceName_p1_params.json
```

The file stores the saved states for all velocities in the selected source/period group.

The **Unsave** button removes the saved state of the current velocity from that file.

If a velocity has unsaved changes and you try to switch away from it, the app asks whether you want to save, discard, or cancel the change.

6.4 Mismatch Readout

The toolbar shows a quantity labeled χ^2. Within the app, this is a **reduced χ^2-like mismatch** computed over the currently visible data range. It is useful as a quick comparison metric, but it is **not** a formal statistical reduced chi-square based on measurement uncertainties.

6.5 Closing Data

Choose `File` → `Close Data` (`Ctrl+W`) to leave fit mode and return to the default standalone state. If there are unsaved changes, the app prompts before closing the folder.

7 File Menu Reference

The shortcuts below use Windows/Linux conventions. On macOS, replace `Ctrl` with `Cmd` and `Alt` with `Option`.

Menu Item	Shortcut	Description
Open Data Folder...	`Ctrl+Shift+O`	Import a data folder and enter fit mode
Recent Data Folders	—	Reopen a recently used source folder
Open Current Source Folder	`Ctrl+O`	Open the active source folder in the file browser
Open Parameters...	`Ctrl+Shift+P`	Import a standalone parameter snapshot
Close Data	`Ctrl+W`	Close the loaded data folder
Save Parameters	`Ctrl+S`	Save current parameters
Save Parameters As...	`Ctrl+Shift+S`	Save a standalone snapshot to a new file
Save Parameters as Default	`Ctrl+Alt+S`	Store the current state as the startup default
Export Plot...	`Ctrl+E`	Export the current figure
Quit	`Ctrl+Q`	Exit the application

Note

In fit mode, `Save Parameters As...` is disabled. The active save target is the source-level parameter file inside the loaded data folder.

8 View Menu Reference

Menu Item	Shortcut	Description
Time Grid → Major / Minor	—	Toggle major and minor time-axis grid lines
Flux Grid → Major / Minor	—	Toggle major and minor grid lines on the top pa
Bottom Panel Grid → Major / Minor	—	Toggle major and minor grid lines on the botto
Show Slider Range	`Ctrl+Alt+R`	Show or hide slider range labels
Line Colors	—	Change the colors of plotted curves

Line-color choices and several view preferences are persisted between sessions.

9 Info and Help Menus

Menu Item	Shortcut	Description
Data Summary	`Ctrl+Alt+D`	Show source, period, velocity, and data ranges
Scaling Formula	`Ctrl+Alt+F`	Show the scaling expression used by the app
Equations Reference	`Ctrl+Alt+E`	Open the bundled equations reference PDF
Solver Step Viewer	`Ctrl+Alt+V`	Open the interactive solver-step viewer
User Guide	`F1`	Open the user guide PDF if available
Documentation	—	Open the generated local documentation
About This App	—	Show application and author information
About Qt	—	Show the Qt about dialog

10 Exporting Plots

Use `File` → `Export Plot...` to save the current figure.

- **PDF:** exports the current plot on the first page and appends one or more text-report pages containing metadata and the current parameter values.
- **PNG / SVG:** exports the figure only.

The exported PDF also includes document metadata such as title, creator, and author name.

11 Saving and Loading Parameters

11.1 Saved JSON Structure

Saved parameter snapshots use the structure

```
{
  "metadata": { ... },
  "config":   { ... },
  "params":   { ... }
}
```

where:

- `metadata` stores version, save time, username, and mode information,
- `config` stores widget/configuration state,
- `params` stores the current parameter values.

In fit mode, the `params` section stores the saved values for all saved velocities in the source/period group.

11.2 App Defaults

The command `File` → `Save Parameters as Default` stores the current standalone state in the platform's persistent application settings using Qt's `QSettings`. On later launches, the app restores these saved defaults instead of the factory defaults.

12 Typical Workflows

12.1 Standalone Simulation Workflow

1. Launch the application.
2. Set the physical sample parameters in **Sample**.
3. Adjust the numerical resolution in **Grid** if needed.
4. Choose the initial state in **ICs**.
5. Define the boundary field in **BCs**.
6. Add one or two pump contributions in **Pump 1** and **Pump 2**.
7. Inspect different propagation slices in **Slice**.

8. Use **Range** to zoom the displayed region.
9. Export the plot or save the parameters when satisfied.

12.2 Observational Fitting Workflow

1. Open a data folder with `File` → `Open Data Folder...`.
2. Select a velocity component from the toolbar.
3. Use **Fit Mode** to choose the correct data time unit and apply any needed offsets.
4. Adjust the physical and driving parameters in **Sample**, **Dynamics**, **ICs**, **BCs**, and the pump tabs.
5. Use the fit controls to align the model in time and scale it vertically.
6. Monitor the χ^2-style mismatch as a quick diagnostic.
7. Save the current velocity.
8. Repeat for the remaining velocities.

13 Troubleshooting

The plot does not seem to change after I edit a value.
Solver parameters under `solve.*` trigger a new solve. Pure display parameters such as range settings, selected slice index, or fit offsets may update the display without re-solving.

Open Parameters refuses one of my saved JSON files.
That file is probably a fit-mode source parameter file. Load the corresponding data folder instead; the app will read that file automatically.

The imported folder is rejected.
Check the filename pattern and make sure the folder contains only one source name and is not mixing period-tagged and non-period-tagged data files.

The solver becomes slow.
Large values of N_t and N_z increase compute time. The first solve after launch may also be slower because the JIT-compiled kernels are being prepared.

The mismatch value is blank.
This happens when there is no loaded data, no visible overlap between the plotted data and model, or no valid interpolated comparison range.

The PDF export contains extra pages.
This is expected. PDF export includes a report section with metadata and parameters in addition to the figure page.