







GALAHAD

EQP

USER DOCUMENTATION

GALAHAD Optimization Library version 5.1

1 SUMMARY

This package uses an iterative method to solve the equality-constrained quadratic programming problem

minimize
$$\frac{1}{2}\mathbf{x}^T\mathbf{H}\mathbf{x} + \mathbf{g}^T\mathbf{x} + f$$
 (1.1)

subject to the linear constraints

$$\mathbf{A}\mathbf{x} + \mathbf{c} = \mathbf{0},\tag{1.2}$$

where the n by n symmetric matrix \mathbf{H} , the m by n matrix \mathbf{A} , the vectors \mathbf{g} and \mathbf{c} , and the scalar f are given. Full advantage is taken of any zero coefficients in the matrices \mathbf{H} and \mathbf{A} .

The package may alternatively be used to minimize the (shifted) squared-least-distance objective

$$\frac{1}{2} \sum_{j=1}^{n} w_j^2 (x_j - x_j^0)^2 + \mathbf{g}^T \mathbf{x} + f, \tag{1.3}$$

subject to the linear constraints (1.2), for given vectors \mathbf{w} and \mathbf{x}^0 .

ATTRIBUTES — Versions: GALAHAD_EQP_single, GALAHAD_EQP_double. Uses: GALAHAD_CLOCK, GALAHAD_SYMBOLS, GALAHAD_SPACE, GALAHAD_QPD, GALAHAD_QPT, GALAHAD_FDC, GALAHAD_SBLS, GALAHAD_GLTR, GALAHAD_SPECFILE. Date: March 2006. Origin: N. I. M. Gould, Rutherford Appleton Laboratory. Language: Fortran 95 + TR 15581 or Fortran 2003. Parallelism: Some options may use OpenMP and its runtime library.

2 HOW TO USE THE PACKAGE

The package is available with single, double and (if available) quadruple precision reals, and either 32-bit or 64-bit integers. Access to the 32-bit integer, single precision version requires the USE statement

USE GALAHAD_EQP_single

with the obvious substitution GALAHAD_EQP_double, GALAHAD_EQP_quadruple, GALAHAD_EQP_single_64, GALAHAD_EQP_double_64 and GALAHAD_EQP_quadruple_64 for the other variants.

If it is required to use more than one of the modules at the same time, the derived types QPT_problem_type, EQP_time_type, EQP_control_type, EQP_initialize, EQP_data_type (Section 2.4) and the subroutines EQP_initialize, EQP_solve, EQP_resolve, EQP_terminate, (Section 2.5) and EQP_read_specifile (Section 2.7) must be renamed on one of the USE statements.

2.1 Matrix storage formats

Both the Hessian matrix **H** and the constraint Jacobian **A** may be stored in a variety of input formats.

2.1.1 Dense storage format

The matrix **A** is stored as a compact dense matrix by rows, that is, the values of the entries of each row in turn are stored in order within an appropriate real one-dimensional array. Component n*(i-1)+j of the storage array A%val will hold the value a_{ij} for $i=1,\ldots,m,\ j=1,\ldots,n$. Since **H** is symmetric, only the lower triangular part (that is the part h_{ij} for $1 \le j \le i \le n$) need be held. In this case the lower triangle will be stored by rows, that is component i*(i-1)/2+j of the storage array H%val will hold the value h_{ij} (and, by symmetry, h_{ji}) for $1 \le j \le i \le n$.

All use is subject to the conditions of a BSD-3-Clause License.

2.1.2 Sparse co-ordinate storage format

Only the nonzero entries of the matrices are stored. For the l-th entry of \mathbf{A} , its row index i, column index j and value a_{ij} are stored in the l-th components of the integer arrays A%row, A%col and real array A%val, respectively. The order is unimportant, but the total number of entries A%ne is also required. The same scheme is applicable to \mathbf{H} (thus requiring integer arrays H%row, H%col, a real array H%val and an integer value H%ne), except that only the entries in the lower triangle need be stored.

2.1.3 Sparse row-wise storage format

Again only the nonzero entries are stored, but this time they are ordered so that those in row i appear directly before those in row i+1. For the i-th row of $\mathbf A$, the i-th component of a integer array A%ptr holds the position of the first entry in this row, while A%ptr (m+1) holds the total number of entries plus one. The column indices j and values a_{ij} of the entries in the i-th row are stored in components $l = \text{A} \text{ptr}(i), \ldots, \text{A} \text{ptr}(i+1) - 1$ of the integer array A%col, and real array A%val, respectively. The same scheme is applicable to $\mathbf H$ (thus requiring integer arrays H%ptr, H%col, and a real array H%val), except that only the entries in the lower triangle need be stored.

For sparse matrices, this scheme almost always requires less storage than its predecessor.

2.1.4 Diagonal storage format

If **H** is diagonal (i.e., $h_{ij} = 0$ for all $1 \le i \ne j \le n$) only the diagonals entries h_{ii} , $1 \le i \le n$, need be stored, and the first n components of the array H%val may be used for the purpose. There is no sensible equivalent for the non-square **A**.

2.1.5 Scaled-identity-matrix storage format

If **H** is a scalar multiple of the identity matrix (i.e., $h_{ii} = h_{11}$ and $h_{ij} = 0$ for all $1 \le i \ne j \le n$) only the first diagonal entry h_{11} needs be stored, and the first component of the array H%val may be used for the purpose. Again, there is no sensible equivalent for the non-square **A**.

2.1.6 Identity-matrix storage format

If **H** is the identity matrix (i.e., $h_{ii} = 1$ and $h_{ij} = 0$ for all $1 \le i \ne j \le n$), no explicit entries needs be stored.

2.2 Real and integer kinds

We use the terms integer and real to refer to the fortran keywords REAL(rp_) and INTEGER(ip_), where rp_ and ip_ are the relevant kind values for the real and integer types employed by the particular module in use. The former are equivalent to default REAL for the single precision versions, DOUBLE PRECISION for the double precision cases and quadruple-precision if 128-bit reals are available, and correspond to rp_ = real32, rp_ = real64 and rp_ = real128 respectively as defined by the fortran iso_fortran_env module. The latter are default (32-bit) and long (64-bit) integers, and correspond to ip_ = int32 and ip_ = int64, respectively, again from the iso_fortran_env module.

2.3 Parallel usage

OpenMP may be used by the GALAHAD_EQP package to provide parallelism for some solvers in shared memory environments. See the documentation for the GALAHAD package SLS for more details. To run in parallel, OpenMP must be enabled at compilation time by using the correct compiler flag (usually some variant of <code>-openmp</code>). The number of threads may be controlled at runtime by setting the environment variable <code>OMP_NUM_THREADS</code>.

All use is subject to the conditions of a BSD-3-Clause License.

MPI may also be used by the package to provide parallelism for some solvers in a distributed memory environment. To use this form of parallelism, MPI must be enabled at runtime by using the correct compiler flag (usually some variant of -lmpi). Although the MPI process will be started automatically when required, it should be stopped by the calling program once no further use of this form of parallelism is needed. Typically, this will be via statements of the form

```
CALL MPI_INITIALIZED( flag, ierr )
IF ( flag ) CALL MPI_FINALIZE( ierr )
```

The code may be compiled and run in serial mode.

2.4 The derived data types

Six derived data types are accessible from the package.

2.4.1 The derived data type for holding matrices

The derived data type SMT_TYPE is used to hold the matrices A and H. The components of SMT_TYPE used here are:

- is a scalar component of type INTEGER (ip_), that holds the number of rows in the matrix.
- is a scalar component of type INTEGER (ip_), that holds the number of columns in the matrix.
- is a scalar variable of type INTEGER (ip_), that holds the number of matrix entries.
- type is a rank-one allocatable array of type default CHARACTER, that is used to indicate the matrix storage scheme used. Its precise length and content depends on the type of matrix to be stored (see §2.4.2).
- val is a rank-one allocatable array of type REAL(rp_) and dimension at least ne, that holds the values of the entries. Each pair of off-diagonal entries $h_{ij} = h_{ji}$ of a symmetric matrix **H** is represented as a single entry (see §2.1.1– 2.1.3). Any duplicated entries that appear in the sparse co-ordinate or row-wise schemes will be summed.
- is a rank-one allocatable array of type INTEGER (ip_), and dimension at least ne, that may hold the row indices of the entries. (see §2.1.2).
- col is a rank-one allocatable array of type INTEGER (ip_), and dimension at least ne, that may hold the column indices of the entries (see §2.1.2–2.1.3).
- ptr is a rank-one allocatable array of type INTEGER (ip_), and dimension at least m + 1, that may hold the pointers to the first entry in each row (see §2.1.3).

2.4.2 The derived data type for holding the problem

The derived data type QPT_problem_type is used to hold the problem. The components of QPT_problem_type are:

- is a scalar variable of type INTEGER (ip_), that holds the number of optimization variables, n.
- is a scalar variable of type INTEGER (ip_), that holds the number of linear constraints, m.

Hessian_kind is a scalar variable of type INTEGER (ip_), that is used to indicate what type of Hessian the problem involves. Possible values for Hessian_kind are:

<0 In this case, a general quadratic program of the form (1.1) is given. The Hessian matrix H will be provided in the component H (see below).

All use is subject to the conditions of a BSD-3-Clause License.

- 0 In this case, a linear program, that is a problem of the form (1.3) with weights $\mathbf{w} = 0$, is given.
- 1 In this case, a least-distance problem of the form (1.3) with weights $w_i = 1$ for j = 1, ..., n is given.
- >1 In this case, a weighted least-distance problem of the form (1.3) with general weights w is given. The weights will be provided in the component WEIGHT (see below).

By default $Hessian_kind = -1$.

- is scalar variable of type SMT_TYPE that holds the Hessian matrix **H**. The following components are used:
 - H%type is an allocatable array of rank one and type default CHARACTER, that is used to indicate the storage scheme used. If the dense storage scheme (see Section 2.1.1) is used, the first five components of H%type must contain the string DENSE. For the sparse co-ordinate scheme (see Section 2.1.2), the first ten components of H%type must contain the string COORDINATE, for the sparse row-wise storage scheme (see Section 2.1.3), the first fourteen components of H%type must contain the string SPARSE_BY_ROWS, for the diagonal storage scheme (see Section 2.1.4), the first eight components of H%type must contain the string DIAGONAL, for the scaled-identity matrix storage scheme (see Section 2.1.5), the first fifteen components of H%type must contain the string SCALED_IDENTITY, for the identity matrix storage scheme (see Section 2.1.6), and the first eight components of H%type must contain the string IDENTITY.

For convenience, the procedure SMT_put may be used to allocate sufficient space and insert the required keyword into H%type. For example, if prob is of derived type EQP_problem_type and involves a Hessian we wish to store using the co-ordinate scheme, we may simply

```
CALL SMT_put( prob%H%type, 'COORDINATE', istat )
```

See the documentation for the GALAHAD package SMT for further details on the use of SMT_put.

- Hane is a scalar variable of type INTEGER (ip_), that holds the number of entries in the lower triangular part of **H** in the sparse co-ordinate storage scheme (see Section 2.1.2). It need not be set for any of the other three schemes.
- H%val is a rank-one allocatable array of type REAL (rp_), that holds the values of the entries of the lower **triangular** part of the Hessian matrix **H** in any of the storage schemes discussed in Section 2.1.
- H%row is a rank-one allocatable array of type INTEGER (ip_), that holds the row indices of the lower triangular part of **H** in the sparse co-ordinate storage scheme (see Section 2.1.2). It need not be allocated for any of the other three schemes.
- H%col is a rank-one allocatable array variable of type INTEGER(ip_), that holds the column indices of the lower triangular part of H in either the sparse co-ordinate (see Section 2.1.2), or the sparse row-wise (see Section 2.1.3) storage scheme. It need not be allocated when the dense or diagonal storage schemes are
- H%ptr is a rank-one allocatable array of dimension n+1 and type INTEGER (ip_), that holds the starting position of each row of the lower triangular part of H, as well as the total number of entries plus one, in the sparse row-wise storage scheme (see Section 2.1.3). It need not be allocated when the other schemes are used.

If $Hessian_kind \ge 0$, the components of H need not be set.

- WEIGHT is a rank-one allocatable array type REAL (rp_{-}) , that should be allocated to have length n, and its j-th component filled with the value w_j for $j=1,\ldots,n$, whenever Hessian_kind > 1. If Hessian_kind ≤ 1 , WEIGHT need not be allocated.
- target_kind is a scalar variable of type INTEGER (ip_), that is used to indicate whether the components of the targets \mathbf{x}^0 (if they are used) have special or general values. Possible values for target_kind are:
 - 0 In this case, $\mathbf{x}^0 = 0$.

All use is subject to the conditions of a BSD-3-Clause License.

- 1 In this case, $x_i^0 = 1$ for j = 1, ..., n.
- \neq 0, 1 In this case, general values of \mathbf{x}^0 will be used, and will be provided in the component X0 (see below).
- By default target_kind = -1.
- is a rank-one allocatable array type REAL (rp_), that should be allocated to have length n, and its j-th component X () $\text{filled with the value } x_i^0 \text{ for } j=1,\dots,n, \text{ whenever } \text{\tt Hessian_kind} > 0 \text{ and } \text{\tt target_kind} \neq 0,1. \text{ If } \text{\tt Hessian_kind}$ ≤ 0 or target_kind = 0, 1, X0 need not be allocated.
- gradient_kind is a scalar variable of type INTEGER (ip_), that is used to indicate whether the components of the gradient g have special or general values. Possible values for gradient_kind are:
 - 0 In this case, $\mathbf{g} = 0$.
 - 1 In this case, $g_i = 1$ for $j = 1, \dots, n$.
 - $\neq 0, 1$ In this case, general values of **g** will be used, and will be provided in the component G (see below).
 - By default $gradient_kind = -1$.
- is a rank-one allocatable array of dimension n and type REAL (rp_), that holds the gradient g of the linear term G of the quadratic objective function. The j-th component of G, $j = 1, \dots, n$, contains \mathbf{g}_j . If gradient_kind = 0, 1, G need not be allocated.
- is a scalar variable of type REAL (rp_), that holds the constant term, f, in the objective function.
- is scalar variable of type SMT_TYPE that holds the Jacobian matrix A. The following components are used: Α
 - A%type is an allocatable array of rank one and type default CHARACTER, that is used to indicate the storage scheme used. If the dense storage scheme (see Section 2.1.1) is used, the first five components of A%type must contain the string DENSE. For the sparse co-ordinate scheme (see Section 2.1.2), the first ten components of A%type must contain the string COORDINATE, while for the sparse row-wise storage scheme (see Section 2.1.3), the first fourteen components of A*type must contain the string SPARSE_BY_ROWS.

Just as for H%type above, the procedure SMT_put may be used to allocate sufficient space and insert the required keyword into A%type. Once again, if prob is of derived type EQP_problem_type and involves a Jacobian we wish to store using the sparse row-wise storage scheme, we may simply

```
CALL SMT_put( prob%A%type, 'SPARSE_BY_ROWS', istat )
```

- Agne is a scalar variable of type INTEGER (ip_), that holds the number of entries in A in the sparse co-ordinate storage scheme (see Section 2.1.2). It need not be set for either of the other two schemes.
- A%val is a rank-one allocatable array of type REAL (rp_), that holds the values of the entries of the Jacobian matrix A in any of the storage schemes discussed in Section 2.1.
- A&row is a rank-one allocatable array of type INTEGER (ip_), that holds the row indices of A in the sparse coordinate storage scheme (see Section 2.1.2). It need not be allocated for either of the other two schemes.
- A*col is a rank-one allocatable array variable of type INTEGER (ip_), that holds the column indices of A in either the sparse co-ordinate (see Section 2.1.2), or the sparse row-wise (see Section 2.1.3) storage scheme. It need not be allocated when the dense storage scheme is used.
- A%ptr is a rank-one allocatable array of dimension m+1 and type INTEGER (ip_), that holds the starting position of each row of A, as well as the total number of entries plus one, in the sparse row-wise storage scheme (see Section 2.1.3). It need not be allocated when the other schemes are used.
- is a rank-one allocatable array of dimension m and type default REAL (rp_), that holds the values of the vectorc Cof constant terms for the constraints. The *i*-th component of C, i = 1, ..., m, contains c_i .

All use is subject to the conditions of a BSD-3-Clause License.

is a rank-one allocatable array of dimension n and type REAL (rp_), that holds the values **x** of the optimization variables. The *j*-th component of X, j = 1, ..., n, contains x_i .

is a rank-one allocatable array of dimension m and type REAL (rp_), that holds the values \mathbf{y} of estimates of the Lagrange multipliers corresponding to the linear constraints (see Section 4). The *i*-th component of Y, $i = 1, \dots, m$, contains y_i .

2.4.3 The derived data type for holding control parameters

The derived data type EQP_control_type is used to hold controlling data. Default values may be obtained by calling EQP_initialize (see Section 2.5.1), while components may also be changed by calling GALAHAD_EQP_read_spec (see Section 2.7.1). The components of EQP_control_type are:

- error is a scalar variable of type INTEGER (ip_), that holds the stream number for error messages. Printing of error messages in EQP_solve and EQP_terminate is suppressed if error ≤ 0 . The default is error = 6.
- out is a scalar variable of type INTEGER(ip_), that holds the stream number for informational messages. Printing of informational messages in EQP_solve is suppressed if out < 0. The default is out = 6.
- print_level is a scalar variable of type INTEGER(ip_), that is used to control the amount of informational output which is required. No informational output will occur if print_level ≤ 0 . If print_level = 1, a single line of output will be produced for each iteration of the process. If print_level ≥ 2 , this output will be increased to provide significant detail of each iteration. The default is print_level = 0.
- new_h is a scalar variable of type INTEGER(ip_-), that is used to indicate how **H** has changed (if at all) since the previous call to EQP_solve. Possible values are:
 - 0 H is unchanged
 - 1 the values in **H** have changed, but its nonzero structure is as before.
 - 2 both the values and structure of **H** have changed.

The default is $new_h = 2$.

- new_a is a scalar variable of type INTEGER($ip_$), that is used to indicate how A has changed (if at all) since the previous call to EQP_solve. Possible values are:
 - 0 A is unchanged
 - 1 the values in A have changed, but its nonzero structure is as before.
 - 2 both the values and structure of **A** have changed.

The default is new_a = 2.

- cg_maxit is a scalar variable of type INTEGER (ip_), that is used to limit the number of conjugate-gradient iterations performed in the optimality phase. If cg_maxit is negative, no limit will be impossed. The default is cg_maxit = 200.
- radius is a scalar variable of type default REAL (rp_), that may be used to specify an upper bound on the norm of the allowed solution (a "trust-region" constraint) during the iterative solution of the optimality phase of the problem. This is particularly useful if the problem is unbounded from below. If radius is set too small, there is a possibility that this will preclude the package from finding the actual solution. If initial_radius is not positive, it will be reset to the default value, initial_radius = SQRT(0.1*HUGE(1.0)) (SQRT(0.1*HUGE(1.0D0)) in GALAHAD_EQP_double).

All use is subject to the conditions of a BSD-3-Clause License.

- inner_stop_relative and inner_stop_absolute are scalar variables of type REAL(rp_), that hold the relative and absolute convergence tolerances for the iterative solution of the optimality phase of the problem using the package GALAHAD_GLTR, and correspond to the values control%stop_relative and control%stop_absolute in that package. The defaults are inner_stop_relative = 0.01 and inner_stop_absolute = \sqrt{u} , where u is EPSILON(1.0) (EPSILON(1.0D0) in GALAHAD_EQP_double).
- max_infeasibility_relative and max_infeasibility_absolute are scalar variables of type REAL(rp_), that hold the relative and absolute tolerances for assessing infeasibility in the feasibility phase. If the constraints are believed to be rank defficient and the norm of the residual $Ax_T + c$ at a "typical" feasiblke point is larger than $\max(\max_i)$, the problem will be marked as infeasible, The defaults are max_infeasibility_relative = max_infeasibility_absolute = $u^{0.75}$ where u is EPSILON(1.0) (EPSILON(1.0D0) in GALAHAD_EQP_double).
- remove_dependencies is a scalar variable of type default LOGICAL, that must be set .TRUE. if linear dependent constraints Ax + c = 0 should be removed and .FALSE, otherwise. The default is remove_dependencies =
- space_critical is a scalar variable of type default LOGICAL, that must be set .TRUE. if space is critical when allocating arrays and .FALSE. otherwise. The package may run faster if space_critical is .FALSE. but at the possible expense of a larger storage requirement. The default is space_critical = .FALSE..
- deallocate_error_fatal is a scalar variable of type default LOGICAL, that must be set .TRUE. if the user wishes to terminate execution if a deallocation fails, and .FALSE. if an attempt to continue will be made. The default is deallocate_error_fatal = .FALSE..
- FDC_control is a scalar variable of type FDC_control_type whose components are used to control any detection of linear dependencies performed by the package GALAHAD_FDC. See the specification sheet for the package GALAHAD_FDC for details, and appropriate default values.
- GLTR_control is a scalar variable argument of type GLTR_control_type that is used to pass control options to the conjugate-gradient solver used to solve linear systems that arise. See the documentation for the GALAHAD package GLTR for further details. In particular, default values are as for GLTR.
- SBLS_control is a scalar variable argument of type SBLS_control_type that is used to pass control options to the symmetric block linear equation preconditioner used to help solve linear systems that arise. See the documentation for the GALAHAD package SBLS for further details. In particular, default values are as for SBLS.
- prefix is a scalar variable of type default CHARACTER and length 30, that may be used to provide a user-selected character string to preface every line of printed output. Specifically, each line of output will be prefaced by the string prefix (2:LEN (TRIM (prefix))-1), thus ignoreing the first and last non-null components of the supplied string. If the user does not want to preface lines by such a string, they may use the default prefix =

2.4.4 The derived data type for holding timing information

The derived data type EQP_time_type is used to hold elapsed CPU and system clock times for the various parts of the calculation. The components of EQP_time_type are:

total is a scalar variable of type REAL (rp_), that gives the total CPU time spent in the package.

find_dependent is a scalar variable of type REAL (rp_), that gives the CPU time spent detecting and removing dependent constraints prior to solution.

factorize is a scalar variable of type REAL (rp_), that gives the CPU time spent factorizing the required matrices.

All use is subject to the conditions of a BSD-3-Clause License.

solve is a scalar variable of type REAL (rp_), that gives the CPU time spent computing the solution given the factorization(s).

- clock_total is a scalar variable of type REAL(rp_), that gives the total elapsed system clock time spent in the package.
- clock_find_dependent is a scalar variable of type REAL(rp_), that gives the elapsed system clock time spent detecting and removing dependent constraints prior to solution.
- clock_factorize is a scalar variable of type REAL (rp_), that gives the elapsed system clock time spent factorizing the required matrices.
- clock_solve is a scalar variable of type REAL (rp_), that gives the elapsed system clock time spent computing the search direction.

2.4.5 The derived data type for holding informational parameters

The derived data type EQP_inform_type is used to hold parameters that give information about the progress and needs of the algorithm. The components of EQP_inform_type are:

- status is a scalar variable of type INTEGER (ip_), that gives the exit status of the algorithm. See Section 2.6 for details
- alloc_status is a scalar variable of type INTEGER(ip_{-}), that gives the status of the last attempted array allocation or deallocation. This will be 0 if status = 0.
- bad_alloc is a scalar variable of type default CHARACTER and length 80, that gives the name of the last internal array for which there were allocation or deallocation errors. This will be the null string if status = 0.
- cg_iter is a scalar variable of type INTEGER(ip_), that gives the total number of conjugate-gradient iterations required.
- factorization_integer is a scalar variable of type long INTEGER (ip_), that gives the amount of integer storage used for the matrix factorization.
- factorization_real is a scalar variable of type INTEGER (int 64), that gives the amount of real storage used for the matrix factorization.
- obj is a scalar variable of type REAL (rp_), that holds the value of the objective function at the best estimate of the solution found.
- time is a scalar variable of type EQP_time_type whose components are used to hold elapsed CPU and system clock times for the various parts of the calculation (see Section 2.4.4).
- FDC_inform is a scalar variable of type FDC_inform_type whose components are used to provide information about any detection of linear dependencies performed by the package GALAHAD_FDC. See the specification sheet for the package GALAHAD_FDC for details.
- SBLS_inform is a scalar variable of type SBLS_inform_type whose components are used to hold information relating to the formation and factorization of the preconditioner. See the documentation for the GALAHAD package SBLS for further details.
- GLTR_inform is a scalar variable of type GLTR_inform_type whose components are used to hold information relating to the computation of the solution via the conjugate-gradient method. See the documentation for the GALAHAD package GLTR for further details.

All use is subject to the conditions of a BSD-3-Clause License.

2.4.6 The derived data type for holding problem data

The derived data type EQP_data_type is used to hold all the data for a particular problem, or sequences of problems with the same structure, between calls of EQP procedures. This data should be preserved, untouched, from the initial call to EQP_initialize to the final call to EQP_terminate.

2.5 Argument lists and calling sequences

There are three procedures for user calls (see Section 2.7 for further features):

- 1. The subroutine EQP_initialize is used to set default values, and initialize private data, before solving one or more problems with the same sparsity and bound structure.
- 2. The subroutine EQP_solve is called to solve the problem.
- 3. The subroutine EQP_terminate is provided to allow the user to automatically deallocate array components of the private data, allocated by EQP_solve, at the end of the solution process.

2.5.1 The initialization subroutine

Default values are provided as follows:

```
CALL EQP_initialize( data, control, inform )
```

- data is a scalar INTENT (INOUT) argument of type EQP_data_type (see Section 2.4.6). It is used to hold data about the problem being solved.
- control is a scalar INTENT (OUT) argument of type EQP_control_type (see Section 2.4.3). On exit, control contains default values for the components as described in Section 2.4.3. These values should only be changed after calling EQP_initialize.
- inform is a scalar INTENT (INOUT) argument of type EQP_inform_type (see Section 2.4.5). A successful call to EQP_initialize is indicated when the component status has the value 0. For other return values of status, see Section 2.6.

2.5.2 The equality-constrained-quadratic programming subroutine

The equality-constrained quadratic programming algorithm is called as follows:

```
CALL EQP_solve(p, data, control, inform)
```

is a scalar INTENT (INOUT) argument of type QPT_problem_type (see Section 2.4.2). It is used to hold data about the problem being solved. The user must have allocated all array components, and set appropriate values for all components. Users are free to choose whichever of the matrix formats described in Section 2.1 is appropriate for A and H for their application—different formats may be used for the two matrices.

The components p%X and p%Y must be set to initial estimates, \mathbf{x}^0 , of the solution variables, \mathbf{x} , and Lagrange multipliers for the constraints, y. Inappropriate initial values will be altered, so the user should not be overly concerned if suitable values are not apparent, and may be content with merely setting p%X=0.0 and p%Y=0.0.

On exit, the components p%X and p%Y will contain the best estimates of the solution variables x, and Lagrange multipliers for the constraints y. Restrictions: p = 0 and, p = 0, and p = 0, and p = 0 and p = 0 and p = 0. ∈ {'DENSE', 'COORDINATE', 'SPARSE_BY_ROWS', 'DIAGONAL'}.

data is a scalar INTENT (INOUT) argument of type EQP_data_type (see Section 2.4.6). It is used to hold data about the problem being solved. It must not have been altered by the user since the last call to EQP_initialize.

All use is subject to the conditions of a BSD-3-Clause License.

control is a scalar INTENT (INOUT) argument of type EQP_control_type (see Section 2.4.3). Default values may be assigned by calling EQP_initialize prior to the first call to EQP_solve.

inform is a scalar INTENT (OUT) argument of type EQP_inform_type (see Section 2.4.5). A successful call to EQP_solve is indicated when the component status has the value 0. For other return values of status, see Section 2.6.

2.5.3 The resolve subroutine

Once EQP_solve has been called, further quadratic programs, for which the data \mathbf{g} , \mathbf{c} and f may have been altered but \mathbf{A} and \mathbf{H} are unchanged, may be solved more efficiently as follows:

```
CALL EQP_resolve( p, data, control, inform )
```

is a scalar INTENT (INOUT) argument of type QPT_problem_type as described for EQP_solve but for which only the components %G, %f and %C may have been altered since the last call to EQP_solve. As before, on exit, the components p%X and p%Y will contain the best estimates of the solution variables x, and Lagrange multipliers for the constraints y.

data , control and inform are precisely as described for EQP_solve.

2.5.4 The termination subroutine

All previously allocated arrays are deallocated as follows:

```
CALL EQP_terminate( data, control, info )
```

data is a scalar INTENT (INOUT) argument of type EQP_data_type exactly as for EQP_solve, which must not have been altered by the user since the last call to EQP_initialize. On exit, array components will have been deallocated.

control is a scalar INTENT(IN) argument of type EQP_control_type exactly as for EQP_solve.

inform is a scalar INTENT (OUT) argument of type EQP_inform_type exactly as for EQP_solve. Only the component status will be set on exit, and a successful call to EQP_terminate is indicated when this component status has the value 0. For other return values of status, see Section 2.6.

2.6 Warning and error messages

A negative value of inform%status on exit from EQP_solve or EQP_terminate indicates that an error has occurred. No further calls should be made until the error has been corrected. Possible values are:

- -1. An allocation error occurred. A message indicating the offending array is written on unit control%error, and the returned allocation status and a string containing the name of the offending array are held in inform%alloc_status and inform%bad_alloc respectively.
- -2. A deallocation error occurred. A message indicating the offending array is written on unit control%error and the returned allocation status and a string containing the name of the offending array are held in inform%alloc_status and inform%bad_alloc respectively.
- -3. One of the restrictions prob%n > 0 or prob%m ≥ 0 or requirements that prob%A_type and prob%H_type contain its relevant string 'DENSE', 'COORDINATE', 'SPARSE_BY_ROWS' or 'DIAGONAL' has been violated.
- -5. The constraints appear to be inconsistent.

All use is subject to the conditions of a BSD-3-Clause License.

- -9. An error was reported by the subroutine SILS_analyse called by SBLS. The return status from SILS_analyse is given in one of the components of inform%SBLS_inform%SLS_inform. See the documentation for the GALA-HAD package SILS for further details.
- $\hbox{-10. An error was reported by the subroutine $\tt SILS_factorize called by $\tt SBLS. The return status from {\tt SILS_factorize} is a substant of the subroutine {\tt SILS_factorize} is a substant of the substant of the subroutine {\tt SILS_factorize} is a substant o$ is given in one of the components of inform%SBLS_inform. See the documentation for the GALA-HAD package SILS for further details.
- -11. An error was reported by the subroutine SILS_solve called by SBLS. The return status from SILS_solve is given in one of the components of $inform SBLS_inform$. See the documentation for the GALAHAD package SILS for further details.
- -12. An error was reported by the subroutine ULS_analyse called by SBLS. The return status from ULS_analyse is given in one of the components of inform%SBLS_inform%ULS_inform. See the documentation for the GALA-HAD package ULS for further details.
- -14. An error was reported by the subroutine ULS_solve called by SBLS. The return status from ULS_solve is given in one of the components of inform%SBLS_inform%ULS_inform. See the documentation for the GALAHAD package ULS for further details.
- -15. The computed preconditioner has the wrong inertia and is thus unsuitable.
- -16. The residuals from the preconditioning step are large, indicating that the factorization may be unsatisfactory.
- -25. EOP_resolve has been called before EOP_solve.

2.7 Further features

In this section, we describe an alternative means of setting control parameters, that is components of the variable control of type EQP_control_type (see Section 2.4.3), by reading an appropriate data specification file using the subroutine EQP_read_specfile. This facility is useful as it allows a user to change EQP control parameters without editing and recompiling programs that call EQP.

A specification file, or specifile, is a data file containing a number of "specification commands". Each command occurs on a separate line, and comprises a "keyword", which is a string (in a close-to-natural language) used to identify a control parameter, and an (optional) "value", which defines the value to be assigned to the given control parameter. All keywords and values are case insensitive, keywords may be preceded by one or more blanks but values must not contain blanks, and each value must be separated from its keyword by at least one blank. Values must not contain more than 30 characters, and each line of the specfile is limited to 80 characters, including the blanks separating keyword and value.

The portion of the specification file used by EQP_read_specifile must start with a "BEGIN EQP" command and end with an "END" command. The syntax of the specfile is thus defined as follows:

```
( .. lines ignored by EQP_read_specfile .. )
 BEGIN EQP
    keyword
                value
     . . . . . . .
                value
    keyword
 END
( .. lines ignored by EQP_read_specfile .. )
```

where keyword and value are two strings separated by (at least) one blank. The "BEGIN EQP" and "END" delimiter command lines may contain additional (trailing) strings so long as such strings are separated by one or more blanks, so that lines such as

All use is subject to the conditions of a BSD-3-Clause License.

BEGIN EQP SPECIFICATION

and

END EQP SPECIFICATION

are acceptable. Furthermore, between the "BEGIN EQP" and "END" delimiters, specification commands may occur in any order. Blank lines and lines whose first non-blank character is ! or * are ignored. The content of a line after a ! or * character is also ignored (as is the ! or * character itself). This provides an easy manner to "comment out" some specification commands, or to comment specific values of certain control parameters.

The value of a control parameters may be of three different types, namely integer, logical or real. Integer and real values may be expressed in any relevant Fortran integer and floating-point formats (respectively). Permitted values for logical parameters are "ON", "TRUE", ".TRUE.", "T", "YES", "Y", or "OFF", "NO", "N", "FALSE", ".FALSE." and "F". Empty values are also allowed for logical control parameters, and are interpreted as "TRUE".

The specification file must be open for input when EQP_read_specfile is called, and the associated device number passed to the routine in device (see below). Note that the corresponding file is REWINDed, which makes it possible to combine the specifications for more than one program/routine. For the same reason, the file is not closed by EQP_read_specfile.

Control parameters corresponding to the components SBLS_control and GLTR_control may be changed by including additional sections enclosed by "BEGIN SBLS" and "END SBLS", and "BEGIN GLTR" and "END GLTR", respectively. See the specification sheets for the packages GALAHAD_SBLS and GALAHAD_GLTR for further details.

2.7.1 To read control parameters from a specification file

Control parameters may be read from a file as follows:

```
CALL EQP_read_specfile( control, device )
```

control is a scalar INTENT (INOUT) argument of type EQP_control_type (see Section 2.4.3). Default values should have already been set, perhaps by calling EQP_initialize. On exit, individual components of control may have been changed according to the commands found in the specifile. Specifile commands and the component (see Section 2.4.3) of control that each affects are given in Table 2.1.

command	component of control	value type
error-printout-device	%error	integer
printout-device	%out	integer
print-level	%print_level	integer
maximum-number-of-cg-iterations	%cg_maxit	integer
trust-region-radius	%radius	real
max-relative-infeasibility-allowed	%max_infeasibility_relative	real
max-absolute-infeasibility-allowed	%max_infeasibility_absolute	real
inner-iteration-relative-accuracy-required	%inner_stop_relative	real
inner-iteration-absolute-accuracy-required	%inner_stop_absolute	real
remove-linear-dependencies	%remove_dependencies	logical
space-critical	%space_critical	logical
deallocate-error-fatal	%deallocate_error_fatal	logical

Table 2.1: Specifle commands and associated components of control.

device is a scalar INTENT (IN) argument of type INTEGER (ip_), that must be set to the unit number on which the specifile has been opened. If device is not open, control will not be altered and execution will continue, but an error message will be printed on unit control%error.

All use is subject to the conditions of a BSD-3-Clause License.

2.8 Information printed

If control%print_level is positive, information about the progress of the algorithm will be printed on unit control-%out. If control%print_level = 1, the norm of the constraint violation and the value of the objective function for both the feasibility and optimality phases are reported. Additionally, if control%print_level = 2, print_level = 1 output from both SBLS and GLTR occurs, summarising the factorization and iteration phases, as well as timing statistics from the two phases. If control $print_evel \ge 3$ detailed output from SBLS and GLTR occurs which is unlikely to be useful to general users.

GENERAL INFORMATION 3

Use of common: None.

Workspace: Provided automatically by the module.

Other routines called directly: None.

Other modules used directly: EQP_solve calls the GALAHAD packages GALAHAD_CLOCK, GALAHAD_SYMBOLS, GALAHAD_SPACE, GALAHAD_QPT, GALAHAD_FDC, GALAHAD_SBPS, GALAHAD_GLTR and GALAHAD_SPECFILE.

Input/output: Output is under control of the arguments control%error, control%out and control%print_level.

Restrictions: prob%n > 0, prob%m ≥ 0 , prob%A_type and prob%H_type $\in \{$ 'DENSE', 'COORDINATE', 'SPARSE_BY_ROWS', 'DIAGONAL' }.

Portability: ISO Fortran 95 + TR 15581 or Fortran 2003. The package is thread-safe.

METHOD

Any finite solution \mathbf{x} to the problem necessarily satisfies the primal optimality conditions

$$\mathbf{A}\mathbf{x} + \mathbf{c} = \mathbf{0} \tag{4.1}$$

and the dual optimality conditions

$$\mathbf{H}\mathbf{x} + \mathbf{g} - \mathbf{A}^T \mathbf{y} = \mathbf{0},\tag{4.2}$$

where the components of the vector y are known as the Lagrange multipliers for the constraints.

A solution to the problem is found in two phases. In the first, a point \mathbf{x}_F satisfying (4.1) is found. In the second, the required solution $\mathbf{x} = \mathbf{x}_F + \mathbf{s}$ is determined by finding \mathbf{s} to minimize $q(\mathbf{s}) = \frac{1}{2}\mathbf{s}^T\mathbf{H}\mathbf{s} + \mathbf{g}_F^T\mathbf{s} + f_F$ subject to the homogeneous constraints $\mathbf{A}\mathbf{s} = \mathbf{0}$, where $\mathbf{g}_F = \mathbf{H}\mathbf{x}_F + \mathbf{g}$ and $f_F = \frac{1}{2}\mathbf{x}_F^T\mathbf{H}\mathbf{x}_F + \mathbf{g}^T\mathbf{x}_F + f$. The required constrained minimizer of $q(\mathbf{s})$ is obtained by implictly applying the preconditioned conjugate-gradient method in the null space of **A**. Any preconditioner of the form

$$\mathbf{K}_G = \left(\begin{array}{cc} \mathbf{G} & \mathbf{A}^T \\ \mathbf{A} & 0 \end{array} \right)$$

is suitable, and the GALAHAD package SBLS provides a number of possibilities. In order to ensure that the minimizer obtained is finite, an additional, precautionary trust-region constraint $||s|| \le \Delta$ for some suitable positive radius Δ is imposed, and the GALAHAD package GLTR is used to solve this additionally-constrained problem.

References:

The preconditioning aspects are described in detail in

H. S. Dollar, N. I. M. Gould and A. J. Wathen. "On implicit-factorization constraint preconditioners". In Large Scale Nonlinear Optimization (G. Di Pillo and M. Roma, eds.) Springer Series on Nonconvex Optimization and Its Applications, Vol. 83, Springer Verlag (2006) 61-82

All use is subject to the conditions of a BSD-3-Clause License.

and

H. S. Dollar, N. I. M. Gould, W. H. A. Schilders and A. J. Wathen "On iterative methods and implicit-factorization preconditioners for regularized saddle-point systems". SIAM Journal on Matrix Analysis and Applications, **28**(1) (2006) 170–189,

while the constrained conjugate-gradient method is discussed in

N. I. M. Gould, S. Lucidi, M. Roma and Ph. L. Toint, "Solving the trust-region subproblem using the Lanczos method". SIAM Journal on Optimization **9(2)** (1999), 504-525.

5 EXAMPLE OF USE

Suppose we wish to minimize $\frac{1}{2}x_1^2 + x_2^2 + \frac{3}{2}x_3^2 + 4x_1x_3 + 2x_2 + 1$ subject to the general linear constraints $2x_1 + x_2 - 2 = 0$ and $x_2 + x_3 - 2 = 0$. Then, on writing the data for this problem as

$$\mathbf{H} = \begin{pmatrix} 1 & 4 \\ 2 & 3 \end{pmatrix}, \ \mathbf{g} = \begin{pmatrix} 0 \\ 2 \\ 0 \end{pmatrix}, \ \mathbf{A} = \begin{pmatrix} 2 & 1 \\ 1 & 1 \end{pmatrix} \text{ and } \mathbf{c} = \begin{pmatrix} -2 \\ -2 \end{pmatrix}$$

in sparse co-ordinate format, we may use the following code:

```
! THIS VERSION: GALAHAD 2.1 - 22/03/2007 AT 09:00 GMT.
  PROGRAM GALAHAD_EQP_EXAMPLE
  USE GALAHAD_EQP_double
                                 ! double precision version
  IMPLICIT NONE
  INTEGER, PARAMETER :: wp = KIND( 1.0D+0 ) ! set precision
  TYPE ( QPT_problem_type ) :: p
  TYPE ( EQP_data_type ) :: data
  TYPE ( EQP_control_type ) :: control
  TYPE ( EQP_inform_type ) :: inform
  INTEGER :: s
  INTEGER, PARAMETER :: n = 3, m = 2, h_ne = 4, a_ne = 4
! start problem data
  ALLOCATE( p%G( n ), p%C( m ), p%X( n ), p%Y( m ) )
  p%new_problem_structure = .TRUE. ! new structure
  p%n = n ; p%m = m ; p%f = 1.0_wp
                                            ! dimensions & objective constant
  p%G = (/ 0.0_wp, 2.0_wp, 0.0_wp /)
                                           ! objective gradient
  p\C = (/ - 2.0 wp, - 2.0 wp /)
                                            ! constraint constants
  p%X = 0.0_wp ; p%Y = 0.0_wp
                                             ! start from zero
! sparse co-ordinate storage format
  CALL SMT_put(p%H%type, 'COORDINATE', s) ! Specify co-ordinate
  CALL SMT_put(p%A%type, 'COORDINATE', s) ! storage for H and A
  ALLOCATE( p%H%val( h_ne ), p%H%row( h_ne ), p%H%col( h_ne ) )
  ALLOCATE( p%A%val( a_ne ), p%A%row( a_ne ), p%A%col( a_ne ) )
  pH%val = (/ 1.0_wp, 2.0_wp, 3.0_wp, 4.0_wp /) ! Hessian H
  p%H%row = (/ 1, 2, 3, 3 /)
                                                 ! NB lower triangle
  p%H%col = (/ 1, 2, 3, 1 /) ; p%H%ne = h_ne
  p%A%val = (/ 2.0_wp, 1.0_wp, 1.0_wp, 1.0_wp /) ! Jacobian A
  p%A%row = (/ 1, 1, 2, 2 /)
  p%A%col = (/ 1, 2, 2, 3 /) ; p%A%ne = a_ne
! problem data complete
  CALL EQP_initialize( data, control, inform ) ! Initialize control parameters
  control%SBLS_control%symmetric_linear_solver = 'sytr'
  control%FDC_control%symmetric_linear_solver = 'sytr'
  CALL EQP_solve(p, data, control, inform) ! Solve problem
```

All use is subject to the conditions of a BSD-3-Clause License.

```
IF ( inform%status == 0 ) THEN
                                             ! Successful return
  WRITE( 6, "( ' EQP: ', IO, ' CG iteration(s). Optimal objective value =', &
         ES12.4, /, ' Optimal solution = ', ( 5ES12.4 ) )")
  inform%cg_iter, inform%obj, p%X
ELSE
                                             ! Error returns
  WRITE( 6, "( ' EQP_solve exit status = ', I6 ) " ) inform%status
END IF
CALL EQP_terminate( data, control, inform ) ! delete internal workspace
DEALLOCATE ( p%G, p%C, p%X, p%Y )
                                           ! deallocate problem arrays
DEALLOCATE ( p%H%val, p%H%row, p%H%col, p%A%val, p%A%row, p%A%col )
DEALLOCATE ( p%H%type, p%A%type )
END PROGRAM GALAHAD_EQP_EXAMPLE
```

This produces the following output:

```
EQP: 1 CG iteration(s). Optimal objective value = 7.0541E+00
Optimal solution = 3.2432E-01 1.3514E+00 6.4865E-01
```

The same problem may be solved holding the data in a sparse row-wise storage format by replacing the lines

```
! sparse co-ordinate storage format
! problem data complete
! sparse row-wise storage format
  CALL SMT_put( p%H%type, 'SPARSE_BY_ROWS', s ) ! Specify sparse-by-row
  CALL SMT_put( p%A%type, 'SPARSE_BY_ROWS', s ) ! storage for H and A
  ALLOCATE( p%H%val( h_ne ), p%H%col( h_ne ), p%H%ptr( n + 1 ) )
  ALLOCATE( p%A%val(a_ne), p%A%col(a_ne), p%A%ptr(m + 1))
  p%H%val = (/ 1.0_wp, 2.0_wp, 3.0_wp, 4.0_wp /) ! Hessian H
  p%H%col = (/ 1, 2, 3, 1 /)
                                                 ! NB lower triangular
                                                 ! Set row pointers
  p%H%ptr = (/ 1, 2, 3, 5 /)
  p%A%val = (/ 2.0_wp, 1.0_wp, 1.0_wp, 1.0_wp /) ! Jacobian A
  p%A%col = (/ 1, 2, 2, 3 /)
  p%A%ptr = (/ 1, 3, 5 /)
                                                 ! Set row pointers
! problem data complete
```

or using a dense storage format with the replacement lines

```
! dense storage format
  CALL SMT_put( p%H%type, 'DENSE', s ) ! Specify dense
  CALL SMT_put(p%A%type, 'DENSE', s) ! storage for H and A
  ALLOCATE (p%H%val(n * (n + 1) / 2))
  ALLOCATE ( p%A%val ( n * m ) )
  p%H%val = (/1.0_wp, 0.0_wp, 2.0_wp, 4.0_wp, 0.0_wp, 3.0_wp/)! Hessian
  p%A%val = (/ 2.0_wp, 1.0_wp, 0.0_wp, 0.0_wp, 1.0_wp, 1.0_wp /) ! Jacobian
! problem data complete
```

respectively.

If instead **H** had been the diagonal matrix

$$\mathbf{H} = \left(\begin{array}{cc} 1 & & \\ & 0 & \\ & & 3 \end{array}\right)$$

but the other data is as before, the diagonal storage scheme might be used for H, and in this case we would instead

All use is subject to the conditions of a BSD-3-Clause License.

EQP GALAHAD

```
CALL SMT_put( prob%H%type, 'DIAGONAL', s ) ! Specify dense storage for H ALLOCATE( p%H%val( n ) ) p%H%val = (/ 1.0_wp, 0.0_wp, 3.0_wp /) ! Hessian values
```

Notice here that zero diagonal entries are stored.