

FRESH & QUICK

MOBILE APP USER MANUAL

Covers the Customer App, the Delivery Partner App and the Admin App

(React Native + Expo — the Vendor Portal remains web-only)

Version 4.15 – Admin registrations

9 October 2026

Table of Contents

Chapter 1 — Introduction	3
Chapter 2 — Getting Started	7
Chapter 3 — Customer App	12
Chapter 4 — Delivery Partner App	36
Chapter 5 — FAQ & Troubleshooting	42
Chapter 6 — Ask Zippy	45
Chapter 7 — Admin App	49
Appendix A — Order Status Reference	51

Chapter 1 — Introduction

The Fresh & Quick mobile app is a React Native + Expo application that brings three of the platform's four portals — the Customer App, the Delivery Partner App and a small Admin App — to a phone. It is a companion to the existing Fresh & Quick web app, not a separate product: it talks to the same self-hosted Supabase backend and the same Next.js API routes as the web app, so an account created on the web works identically when signed into on mobile, and an order placed on one surface is immediately visible on the other.

The mobile app covers the three portals a real end user, gig worker or platform administrator would use on a phone:

- Customer App — browse stores, order food or goods, track delivery, and manage your account.
- Delivery Partner App — go online, accept ready orders and mark them picked up (the customer's app then completes the delivery), with a History screen for finished jobs.
- Admin App — for administrators only: a read-only Overview and the Registrations screen, where you approve or reject new customer registrations (Chapter 7).

The Vendor Portal (store/restaurant management) and the rest of the Admin Portal (orders, vendors, delivery partners, coupons, reviews and settings) are desk-oriented back-office tools and remain web-only in this release. The phone Admin App covers only the Overview and Registrations screens. Store owners and platform staff should continue to use a browser for everything else.

1.1 What's New in This Version

What's new for version 4.15 (admin registrations on the phone): the start screen now has three buttons: Customer, Delivery Partner and Admin. Admin is for administrators only. A new Chapter 7 describes the Admin App: Admin Log In, a read-only Overview with four tiles, and a Registrations screen where an administrator approves a customer registration or rejects it with a reason (the reason is emailed to the customer). Approving or rejecting sends the same emails as on the web. No new screenshots were added: the new screens are described in text.

What's new for version 4.14 (registration approval): signing up no longer signs you in. After you tap Sign Up a pop-up says “Your registration approval is in progress. We will email you once the admin has reviewed it.”; tap OK to return to Log In. Your account waits for an administrator to approve it, and you get an email when the decision is made. Until it is approved, Log In shows a message saying the registration is still awaiting approval (or was rejected). Ask Zippy now needs you to be signed in: signed out, tapping the Ask Zippy button shows a pop-up with a Register or log in button (sections 2.2 and 6.2).

What's new for version 4.13 (coupons, wallet and notifications): Checkout has a Promo code section where you can type a code or tap a suggested one, and a Use wallet credit switch when you have credit; the order summary then shows Discount and Wallet credit lines (section 3.4.1). The Wallet screen under the Account tab now shows your credit balance, your referral code with a Share button and a history of credit (section 3.7.1), and sign-up has an optional Referral code field (section 2.2). A new Notifications screen, reached from the Account tab (customers) or the dashboard header (delivery partners), lists your updates and has notification settings; the phone can also receive push notifications (sections 3.7.2 and 4.8). No new screenshots were added for this version: the new screens are described in text.

What's new for version 4.12 (ratings and reviews): after an order is Delivered, its screen has a Rate your order card where you give the store 1 to 5 stars and can add a comment, one photo, stars for the dishes and stars for the delivery partner (section 3.6.2). Afterwards the order shows Your review. A store's screen now has a Reviews section with each review, the store's reply and a Report link (section 3.2.1), dishes show their average once

customers have rated them, and a delivery partner's Dashboard has a My rating card (section 4.7). About an hour after delivery an email asks how your order was. Also corrected: the FAQ answer about maps was out of date, and the Honest Limits note on screenshots now mentions the new emulator figures.

What's new for version 4.11.1 (correction: favorite hearts are saved on your account and also appear on the website; earlier text in this manual that called them local-only was wrong. 4.11 added favorites and reorder): store cards have a heart saved on your account, Home has a Favorites chip, the Order again row now reorders in one tap, and the Orders tab and an order's screen have a Reorder button (section 3.1.2). Reorder fills the cart at today's prices; it never places the order.

What's new for version 4.10 (automatic order acceptance): the web Admin Overview has a new checkbox, Automatic order acceptance (demo mode). When it is on, every paid order is accepted, prepared, marked ready, assigned and picked up by itself about 3 seconds apart, so orders placed in this app can be followed from start to finish without any store or delivery-partner taps. The Admin is web-only, so nothing changes on the phone screens and there is no new phone screenshot; the 6-step tracker simply moves on its own.

This manual has been rewritten to match a 4-phase UberEats-style visual and structural redesign of the Customer App, done after the app's first build. The biggest change: the Customer App now opens into a bottom tab bar (Home / Orders / Account) instead of a plain stack of screens, and several screens moved from full pages to overlay-style bottom sheets. Nothing about what the app can do has changed — every feature from the first release still works the same way underneath — but where you find things, and how screens are presented, has changed throughout. Chapters 2 and 3 below describe the app as it exists today; if you used an earlier build, don't rely on old habits for where things live.

Since version 2.0 the whole app was re-skinned with a new orange / navy / green look (pill-shaped buttons, rounded cards, colored section backgrounds) and the colors used behind white text were darkened so buttons and badges are easy to read. Signing in and Account changed too: the app now always starts signed out (each cold launch asks you to log in), and your name plus a Reset password option now appear in the Account tab (Customer) and the dashboard header (Delivery Partner). The Customer App and Delivery Partner screenshots in Chapters 3 and 4 (sign-up, Home, Store Detail, Cart, Checkout, Orders, order detail, Account, the Delivery dashboard cards and History) are real captures from screen recordings of the app on a phone, with personal details blurred. The one exception is the Available order card in section 4.3, which is a wireframe drawn from the app's source code with demo data (an order is normally auto-assigned before it can be photographed in that list).

What's new for version 4.0 (order visibility): (1) Checkout now asks for a required Phone number. (2) The Orders tab shows richer rows — store, a colored status pill, date and time, up to three item thumbnails with an item count, and the total. (3) The order screen is now a full order detail: a six-step tracker (Placed, Accepted, Preparing, Ready, On the way, Delivered) with a single "Step N of 6" caption, a Deliver-to card, an Items card with photos, totals and payment, and a timeline of times. (4) Status wording changed: the old single "Out for delivery" is now two statuses, Partner assigned (a delivery partner accepted the order) and On the way (the order was picked up); status colors now match the web portals. (5) The Delivery Partner dashboard now shows only active work — Your active deliveries with the full drop-off details, then Available orders with an Accept button — and a new History screen lists finished deliveries. The old View address button and the "Claim" wording are gone. (6) Customers also receive an email when the restaurant accepts an order and when it is delivered. (7) You can now create a Customer account inside the app: the customer sign-in screen has a Log in / Sign up toggle (full name, email, password of at least 6 characters), and after sign-up you are signed in automatically.

What's new for version 4.1 (customer-completed delivery): delivery partners no longer mark an order delivered; they only tap Mark picked up, and their card then says "Customer is receiving the order...". After pickup, the customer's order detail screen plays a 15-second courier animation ("Your order is on the way!", counting down "Arriving in 15s") and the order is then marked Delivered automatically, which also sends the delivered email. If

the customer never opens the order, the system completes the delivery 20 seconds after pickup. See §3.6.1 and §4.4.

What's new for version 4.2: the courier animation now always plays, even when the phone's Reduce Motion accessibility setting is on, and the animation and the automatically delivered order are shown with real screenshots from an iPhone (see §3.6.1).

What's new for version 4.3: the Delivery Partner chapter now shows real phone screenshots of an assigned delivery with the Mark picked up button and of the same delivery after pickup ("Customer is receiving the order..."); the old screenshot with a Mark delivered button has been removed.

What's new for version 4.6: Ask Zippy can take you to checkout. Signed in as a customer, ask Zippy to check out and tap the Go to checkout card to open the Checkout screen for your current cart (section 6.3); you still enter your details and pay yourself, and Zippy never places or pays for an order. What's new for version 4.5: Ask Zippy can change your cart. Signed in as a customer, you can ask Zippy to add a dish, repeat a past order, change a quantity, remove a line or empty the cart, and tap Confirm on a card to apply it (section 6.3); this edition has no new screenshot for the cards. What's new for version 4.4: if the customer never opens the order, the system now marks it Delivered 20 seconds after pickup (it was 5 minutes), and the order screen does not need to be open for that to happen; the "Delivered! Enjoy your meal." modal no longer has a Done button and closes itself 3 seconds after it shows (a Close button appears only if delivery could not be confirmed). An older duplicate screenshot of the partner dashboard was removed from section 4.5.

What's new for version 4.7: Ask Zippy answers now appear word by word as they are written, instead of all at once at the end. When Zippy needs to look something up, a short lead-in line may appear and then disappear before the real answer; the Confirm, Dismiss and Go to checkout cards appear once the answer has finished.

What's new for version 4.7.1: Ask Zippy can now set, replace or clear your order note after you confirm a card (see the order note item in the Ask Zippy chapter). Cards now show option prices, for example "Spice level: Extra spicy (+₹20)", and a Try again button appears when confirming fails with an unexpected error.

What's new for version 4.8: the order screen has a live map while a partner is assigned or on the way, with S (store), H (your address) and D (partner) and a dashed straight line; it shows when the partner's location was last updated and about how far they are from your address, and says when a location may be out of date. There is no arrival time on the phone (the website shows a road route and an estimate). The map uses the phone's own maps: Apple Maps on iPhone and Google Maps on Android.

What's new for version 4.8.1: a new section, 2.6, explains step by step how to start the Android emulator on the PC, open the app in it, take screenshots and reset it.

What's new for version 4.9: the Customer Sign Up screen now also asks for a phone number and an address (Address line 1, optional Address line 2, City, State and a 6-digit Pincode), and the address is checked before the account is created. That address becomes your delivery location. The location bar on Home opens a new Delivery location sheet (section 3.1.1) where you can search for an address with live suggestions, use your current location or place a pin on the map; your saved location is kept on your account and restaurants are listed nearest first. Checkout has a Search for your address box and a Use my saved location link (section 3.4). When a delivery partner's last location is more than 5 minutes old, the order map shows only "Last seen ... (location may be out of date)" and no distance (section 3.6).

1.2 What's the Same as the Web App, and What's Different

Everything that matters to an end user — your account, your cart, your order history, your store's menu, live order status (the same six steps and the same status colors) — is shared with the web app because both talk to the same backend. What differs is purely presentational: the mobile app is a native phone interface (tab/stack navigation, native inputs, pull-to-refresh, bottom sheets) instead of a browser page, and a small number of

features that depend on hardware not available in this build (see the notes on maps and location below) are simplified the same way they are on the web.

1.3 Honest Limits of This Build

This is a functional demo/development build, and a few things are deliberately simplified or left as UI-only rather than fully built out:

- Maps are limited. Order tracking shows a map with a straight dashed line and an approximate distance, with no road route or arrival time (on the Android emulator the map tiles may stay blank), and address search depends on the build (see section 3.1.1).
- No real payments. Every payment method at checkout is a mock (Mock Card, Mock UPI, Cash on Delivery); no card or bank details are transmitted or stored, and no real money moves. Wallet credit comes only from referrals; it cannot be bought, withdrawn or sent to anyone.
- Push notifications are limited. Updates always appear in the Notifications screen and, as before, order and delivery screens re-check the server while they are open. A push notification (a banner when the app is in the background) needs an Expo push token: it works on an iPhone in Expo Go once an EAS project id is set in the app configuration, and Android Expo Go cannot receive remote push at all. Tapping a push opens the order (customer) or the Notifications screen (delivery partner), but only while the app is still running, not from fully closed. Text-message and WhatsApp alerts are not available yet.
- No background location tracking. The Delivery Partner App only shares a live location ping while the app is open and the partner is toggled online — it does not track location while the app is closed or backgrounded.
- Address search is not guaranteed in Expo Go. Searching for an address in the Delivery location sheet works in the Android native build; in Expo Go the sheet may say that address search is not available, and you can use your current location or move the pin instead (section 3.1.1).
- The cart's tip selector is UI-only. There is no tip column in the backend; a selected tip percentage is never added to your subtotal, delivery fee, or total, and is never sent to checkout — it is purely cosmetic, with a disclaimer shown directly under it in the app.
- Order-tracking's Call and Message buttons are demo stubs. Tapping either on the courier card shows an alert saying it isn't wired up to a real backend yet — there is no telephony or chat integration.
- Screenshots are captures from screen recordings of the real app running on a phone, with personal details blurred (the round blue gear button in them is the Expo developer menu of the test build, not part of the app). The Available order figure in section 4.3 is a wireframe drawn from the source code with demo data. Everything new in this version was also checked by type-check, automated tests and code review. The ratings and reviews figures (sections 3.2.1, 3.6.2 and 4.7) are captures from the Android emulator with throwaway test data.

None of these are bugs to report — they reflect the current scope of this build, matching the equivalent stubs already documented in the web app's own user manual.

Chapter 2 — Getting Started

2.1 Opening the App

When you open the app, you land on a role picker screen with three buttons: Customer, Delivery Partner and Admin. Tap the one that matches how you intend to use the app — each leads to its own sign-in screen. The Admin button is for administrators only: any other account that tries it is refused (see Chapter 7).

2.2 Signing In

Enter the email and password for your Fresh & Quick account and tap Log In. If you do not have an account yet, tap "Need an account? Sign up" under the form: the screen changes to Customer Sign Up, where you fill in the details described below and tap Sign Up. Signing up does not sign you in: a pop-up says "Your registration approval is in progress. We will email you once the admin has reviewed it." Tap OK and the form is cleared and you are back on Log In. Your account waits for an administrator to review it, and you receive an email when the administrator has decided. Accounts made in the app and accounts made on the web app are the same — the same email and password work on both, once the account is approved. (Only the Customer App has sign-up; delivery partner accounts are created by an administrator.) On the sign-up screen, "Have an account? Log in" switches back.

If your email or password is incorrect, the sign-in screen shows "Invalid login credentials" directly below the form. If your registration has not been approved yet, Log In instead shows "Your registration is still awaiting admin approval." If the administrator rejected it, it shows "Your registration was rejected. Please check your email for the reason." If the app cannot tell which applies, it shows "Your account is not active yet. Please try again later or check your email."

9:46

80

<

Fresh & Quick

Customer Log In



Customer Log In

Email

Password

Log In

Screenshot — Customer sign-in screen (email, password, Log In).

3:13

← Customer Log In

Customer Sign Up

Full name

Email

Password

Phone (10-digit mobile)

Address line 1

Address line 2 (optional)

City

State

Pincode (6 digits)

⚡ Ask Zippy

Sign Up

[Have an account? Log in](#)

Screenshot — Customer sign-up screen (full name, email, password, phone, address line 1 and 2, city, state, pincode, Sign Up).

New customers sign up with a full name, email, password (at least 6 characters), a Phone (a 10-digit Indian mobile number) and an address: Address line 1, Address line 2 (optional), City, State and a 6-digit Pincode. Before the account is created, the server checks the address with Google. If the address cannot be found, or the result is too vague or partial, you see “We could not find that address. Check the details and try again.” If the lookup service is not available you see “Address lookup is unavailable right now. Try again later.” In both cases no account is created and you can correct the form and try again. The address you register becomes your delivery location on Home; you can change it at any time (section 3.1.1). Sign-up also has an optional Referral code field; a code that does not exist is refused and no account is created (section 3.7.1). If you sign up again with an email that is already waiting for approval you see “Your registration is already awaiting approval.”; with an email that is already approved you see “An account with this email already exists. Please log in.” An email whose registration was rejected can sign up again, and you see the same in-progress pop-up.

Always signed out at launch: the app does not remember your last session. Every time you open it from scratch you land on the role picker and sign in again. Switching between apps and coming back does not sign you out.

2.3 Tab-Based Navigation (New)

Once signed in as a Customer, the app opens into a bottom tab bar with three tabs: Home, Orders, and Account. This replaces the earlier build's single stack of screens with no persistent navigation. The tab bar stays visible across Home, the Orders list, and the Account screen; it is intentionally hidden on screens you're meant to focus on one task at a time — Store Detail, Cart, Checkout, and an individual order's tracking screen — which are reached by tapping into them and dismissed with a back gesture or an explicit close/back control on that screen.

Note: The Delivery Partner App has no tab bar — it opens on a single dashboard once signed in, with History and Notifications links in its header that opens a second screen (see Chapter 4).

2.4 Switching Roles or Accounts

Each app is signed in as one role at a time. To use the app as a different role (for example, to also act as a delivery partner or an administrator), sign out from within that portal — for the Customer App, this is the Sign out row on the Account tab (§3.8); for the Delivery Partner App, it's the Sign out link in the dashboard header; for the Admin App, it's the Sign out link at the top right of the Overview screen — and pick the other role from the role picker screen shown at launch.

2.5 Connecting to the Backend (Web vs. Mobile)

The mobile app always talks to one backend address at a time, configured at build time via the EXPO_PUBLIC_API_BASE_URL environment variable — typically your development machine's LAN IP address (for example `http://192.168.1.42:3000`) so a phone on the same Wi-Fi network can reach it, since "localhost" on a phone means the phone itself, not your computer.

This is different from the web app's optional multi-port testing mode (four ports, one per role, so a customer, vendor, delivery partner, and admin can all be signed in at once in the same browser — see the web User Manual, section 2.5). That multi-port scheme is a browser-only convenience for testing multiple roles side by side; the mobile app doesn't need it and isn't affected by it — it simply signs in as one role at a time (Customer, Delivery Partner or Admin, see section 2.4) against the single server address it was built with.

2.6 Running the App on the Android Emulator (Windows PC)

If you do not have an Android phone, the Android emulator on this PC acts as one. It is a virtual Pixel 7 (Android 15) named Pixel_API_35 with Expo Go already installed. Follow these steps in order.

Step 1 — Start the services. Docker Desktop must be running with the Supabase stack and n8n, the web app must be running (port 3000), and Metro, the Expo server for the phone app, must be running on port 8081. If Metro is not running, open a terminal in the mobile folder and run: `npx expo start`

Step 2 — Start the emulator. Open PowerShell in the project folder and run the command below. It starts the virtual phone and then moves and resizes its window so that it sits in the middle of the screen with nothing cut off. The phone takes about one to two minutes to reach its home screen. Use PowerShell, not Git Bash, because an emulator started from Git Bash closes when that window closes.

```
.\scripts\start-emulator.ps1
```

Step 3 — Check the window. The emulator window should now be fully on the screen, with the phone on the left and its small toolbar on the right. This PC's screen is large (3840 by 2160 at 225% scaling) and the emulator on its own opens partly off-screen, which is why the script exists. If the window is ever in the wrong place, for example after you started the emulator without the script, run the same command again: it moves the window back without restarting the phone.

Step 4 — Open the app. Once the home screen is showing, run this command in PowerShell. 10.0.2.2 is the emulator's name for this PC, so it reaches Metro on port 8081. The first start takes up to a minute while the app loads. As a shortcut, step 2 and this step can be done together by running `.\scripts\start-emulator.ps1`

`-OpenApp`, which waits for the phone to finish booting and then opens the app.

```
& "$env:LOCALAPPDATA\Android\Sdk\platform-tools\adb.exe" shell am start -a android.intent.action.VIEW -d "exp://10.0.2.2:8081"
```

You can also open the Expo Go app on the emulator and type `exp://10.0.2.2:8081` into it. The app opens on "Who's using the app?"; sign in as described in section 2.2.

Step 5 — Take a screenshot (optional). This saves the emulator screen to a file called `shot.png` in the current folder:

```
cmd /c "`"$env:LOCALAPPDATA\Android\Sdk\platform-tools\adb.exe`" exec-out screencap -p > shot.png"
```

Good to know: on the emulator the map on the order screen shows blank tiles (Google Maps tiles do not load in the emulator's copy of Expo Go), so check maps on a real phone. To start with a clean app, with no saved cart, delivery location or sign-in, run `adb shell pm clear host.exp.exponent` (using the `adb.exe` path above). To close the emulator, run `.\scripts\stop-emulator.ps1` in PowerShell (it asks the phone to shut down and stops it by force if it does not answer within about 15 seconds); closing its window also works. If you type into a field that already has text, the new text is added to the old, so clear the field first.

Chapter 3 — Customer App


The Customer App is organized around three bottom tabs — Home, Orders, Account — plus four full-focus screens reached by tapping into them: Store Detail, Cart (a bottom sheet), Checkout, and an order's individual Tracking screen. This chapter covers each in the order you'd naturally move through them.

3.1 Home

Home is the Home tab's screen and opens on a pull-to-refresh scroll view with, from top to bottom:

- A location bar at the top, showing your saved delivery location (for example “Linking Road, Mumbai”) — tap it to open the Delivery location sheet (section 3.1.1).
- A search pill (“Search restaurants or dishes”) — typing filters the store list further down by store name, cuisine tag, or the name of any dish/product sold at that store, so searching for a specific dish surfaces every store that sells it, not just stores whose own name matches.
- A horizontally scrolling row of category chips (circular icons, one per cuisine/category) — tapping one filters the store list to that category; tapping the same chip again clears the filter.
- A promo carousel — swipeable banner cards for stores currently running a promotion, each showing the store's promo text over its banner photo. Only stores with an active promo appear here, and the row is hidden entirely when none do.
- An “Order again” row — up to 3 stores you've ordered from most recently, each with a Reorder button that refills your cart from that store's last order in one tap (a closed store shows Closed). Hidden for a new account with no order history.
- A “Restaurants near you” list — every open, non-suspended store as a photo-forward card: 16:9 banner image (or a plate emoji placeholder if none is set), a favorite heart in the photo's corner (saved on your account, see section 3.1.2), a promo badge overlaid on the photo when applicable, the store's name, and a single metadata line (star rating · average prep time · delivery fee, e.g. “★4.5 · 25 min · ₹30 delivery”).

Tapping a store card, a promo card, or a reorder card all open that store's Store Detail screen. Pulling down from the top of the list refreshes every section (stores, categories, promos, reorder row) in one action.




Screenshot — Home tab: search, category chips, Order again row, and store cards.

3.1.1 Setting Your Delivery Location


Tap the location bar at the top of Home to open the Delivery location sheet. It offers three ways to set where your order is delivered:

- Search — type at least 3 characters in Search for your address; live suggestions appear below the box. Choose one and the location is saved and the sheet closes.
- Use my current location — the phone shares its position and the location is saved at once.
- Move the pin — tap the map or drag the pin to the spot you want, then tap Confirm location to save it.


The saved location is kept on your account, so it follows you when you sign in again. It shows in the bar on Home, and the Restaurants near you list is ordered nearest first from it. Address search works in the Android native build; it is not guaranteed in Expo Go, where the sheet may say address search is not available (you can still use your current location or the pin).



Screenshot — Delivery location sheet: typing in Search for your address shows live suggestions; Use my current location sits under the box and the map is below.



Screenshot — Moving the pin on the map and saving with Confirm location. (This capture is from a build where address search was unavailable, so the sheet shows a note under the search box.)




Screenshot — Home after saving a location: the location bar shows “Linking Road, Mumbai” and stores are listed nearest first.


3.1.2 Favorites and Reorder

Signed-in customers can save favorite stores and refill the cart from an earlier order. Favorites are saved on your account, so they also appear on the website.


- Save a favorite - tap the heart on a store card; a filled heart means saved, tap again to remove it.
- See your favorites - on Home tap the Favorites chip; tap it again to see all stores. With none saved it says "No favorite stores here yet. Tap the heart on a store."
- Order again - the Order again row on Home shows up to three stores you ordered from most recently, each with a Reorder button (a closed store shows Closed). The Orders tab and an order's screen also have a Reorder button; it is not shown for cancelled or rejected orders.
- What Reorder does - it fills the cart with that order's items, options and notes at today's prices; it does not place the order, so open the cart and go to Checkout. Unavailable items are skipped and listed in the message. Reordering from a different store replaces the cart and the message says how many items were replaced; the same store adds the quantities together.



Screenshot - Home: Favorites chip, Order again row with Reorder buttons, and a heart on each store card.



Screenshot - After Reorder from another store: the message says the cart was replaced; the Favorites chip is on and the card heart is filled.



Screenshot - Orders tab: delivered orders have a Reorder button, the cancelled order does not.

3.2 Store Detail

The Store Detail screen opens with a full-width hero banner (the store's banner photo, or a plate emoji on a tinted background if none is set), with a back chip and a favorite-heart chip overlaid on its corners. Below the hero is the store's name, cuisine tags, rating, and average prep time, followed by a closed/suspended banner if the store currently can't take orders. Once customers have rated a dish, its row also shows the dish's average and number of ratings, for example ★ 5.0 (1); reviews of the store itself are at the bottom of the screen (section 3.2.1).

Below that, a row of category pills (e.g. Starters, Mains, Desserts) sticks to the top of the screen as you scroll past it, so you can always see which section you're in and tap a pill to jump straight to it — tapping a pill both scrolls to that section and highlights the pill; the highlight does not yet auto-update purely from scroll position, so it only changes when you tap a pill directly (see the Known Limitations note below).


The menu itself is grouped into sections matching the store's own category labels (uncategorized items fall into a trailing “Other” group). Each item row shows:

- A veg/non-veg indicator dot, the item name, and its description (up to 2 lines).
- Its price.
- A thumbnail image with a circular “+” Quick Add button overlaid on its corner.

Tapping an item with no configurable options adds it straight to your cart. Tapping an item that has size/add-on options (configured by the store owner) instead opens a bottom-sheet customization view, where you choose required and optional groups before adding it to your cart; a required group left with no valid options keeps Add-to-cart disabled rather than letting you submit an incomplete selection. Every item can also carry its own special-instructions note (e.g. “no onions”), entered in that same customization step.

Adding an item from a different store than what's already in your cart prompts a native confirmation dialog to clear the current cart first — a cart can only ever hold items from one store at a time.

Note: The pill-nav's active highlight only updates on tap, not on scroll — a minor known gap carried over from the web app's own scroll-spy nuance, not a functional bug (the pill row still scrolls correctly to every section).




Screenshot — Store Detail: hero photo, category pills, menu rows, and the floating cart pill.

3.2.1 Reviews on a Store Screen

At the very bottom of a store's screen, below the menu, a Reviews section appears once the store has at least one review. Its heading shows the average and the number of reviews, for example “Reviews · ★ 4.5 (2)”. Each review shows the customer's first name and last initial (for example “Meera K.”), the stars, the comment, the photo if one was added, the ratings given to dishes, and the store's reply if it has answered. The newest reviews come first, ten at a time; tap Load more reviews to see older ones. Until a store has its first review, the rating shown near the top of the screen is the starting rating the store was listed with.

To report a review that breaks the rules, tap Report under it and choose one of three reasons: Offensive or abusive, Spam or fake, or Not about this store. The review then shows “Reported, thank you” and the Fresh & Quick team looks at it. You cannot report your own review; the app shows a message instead. Reviews cannot be edited or deleted by customers.




Screenshot - Store screen, Reviews section: a review with a photo and dish ratings, a review with the store's reply, and the three Report reasons opened under it. Android emulator, throwaway test data.

3.3 Cart

The cart opens as a bottom sheet over whichever screen you were on, not a separate full page — a dimmed backdrop covers the screen behind it, the sheet has a drag-handle bar at its top, and an **X** close button returns you to where you were. Each line shows the item's thumbnail, name, any selected customization options, a quantity stepper (– / +), a Remove link, and a per-line note field. Below the line items:

- An order note field for the whole order (e.g. gate code, “leave at door”) — separate from each line's own special-instructions note.
- A Clear cart link.
- A tip selector (15% / 18% / 20% / Other) with an explicit disclaimer underneath it — see the stub note below.
- An order summary (Subtotal, Delivery fee, Total) and a Checkout button, pinned at the bottom of the sheet.

Not fully wired up yet: the tip selector is UI-only. Choosing a tip percentage highlights that button but never changes your subtotal, delivery fee, or total, and no tip value is sent at checkout — there is no tip column in the backend yet. The app tells you this directly under the selector.



Screenshot — Cart: item rows with quantity steppers, order note, tip selector, and pinned Checkout.


3.4 Checkout

Checkout is a single scrollable screen. A Contact details block (Name, Email and Phone; name and email are pre-filled from your account profile where available) sits at the top, followed by three collapsible rows — each shows a one-line summary when collapsed and expands in place to reveal its fields when tapped, with only one row open at a time:


Phone is required. Enter an Indian 10-digit mobile number that starts with 6, 7, 8 or 9; you may type it with an optional +91, 91 or 0 in front. It is saved as +91 followed by the 10 digits, so the delivery partner can call you and so it appears on your order. If the number is not valid, an error message appears under the field and Place order stays disabled; the server checks the number again when the order is placed.

- Delivery address — Address line 1 (required), Address line 2 (optional), City, State, and Pincode. A Search for your address box at the top fills Address line 1, City and State from a suggestion (type the Pincode yourself if it is left blank), and Use my saved location fills the form from your saved delivery location. To place a pin on a map, use the Delivery location sheet from Home (section 3.1.1).
- Delivery instructions — the same order-note text you may have already entered in the cart; editing it here updates the same value.
- Payment method — Mock Card (16-digit card number, MM/YY expiry, cardholder name), Mock UPI (a UPI ID such as name@bank), or Cash on Delivery. All three are simulated — no real payment processor is contacted.

Below the three rows, an Order summary block shows subtotal, the store's real delivery fee, any discount and wallet credit, and the total. A Place order button is pinned to the bottom of the screen (not part of the scrolling content) and stays disabled until every required field above is valid; while submitting, it shows a spinner in place of its label. After a successful submission, you're taken directly to that order's Tracking screen.



Screenshot — Checkout: collapsible rows with the payment options open and Place order ready.



Screenshot — Checkout, Delivery address row open: Search for your address (filled with “Linking Road”), Use my saved location, and the address fields filled from the suggestion with Pincode still blank.

3.4.1 Promo Code and Wallet Credit

Checkout has a Promo code section above the Order summary. It lets you take money off the order with a promo code, with wallet credit, or both.


- Promo code — type the code in Enter promo code (letters are capitalised for you) and tap Apply. Once accepted the box shows “<CODE> applied: -₹X” with a Remove button. Codes that currently work for your store appear underneath as tap-to-apply chips. Only one code can be used per order, and it is not remembered: if you change your cart you may have to apply it again.
- What a code takes off — a percentage or a fixed rupee amount off the subtotal (the food), never the delivery fee and never more than the subtotal. A percentage code can have a maximum discount.
- If a code is refused — the message under the box says why: the code does not exist, is paused, has expired or not started, belongs to a different store, needs a bigger order, has been fully used, has already been used by you, or is only for a first order.
- Use wallet credit — a switch with “Balance ₹X”, shown only when you have credit. Credit is applied after any promo code and never goes beyond what is left to pay.

The Order summary then lists Subtotal, Delivery fee, Discount (CODE), Wallet credit and Total, and the Place order button shows the final amount. The server works the amounts out again when the order is placed. If the order is later rejected or cancelled (including a failed payment) the code counts as unused again and any wallet credit you used is returned to your wallet. The order screen shows the Discount and Wallet credit lines too.

Not illustrated in this version: the Promo code section is described in text only.

3.5 Orders (tab)

The Orders tab (heading "Your orders") lists every order you've placed, most recent first. Each row shows the store name, a colored status pill (for example Placed, Preparing, On the way, Delivered), the date and time the order was placed, up to three small item photos with an item count such as "2 items", and the order total. Tapping a row opens that order's detail screen (§3.6). If you have no orders the tab says "No orders yet." The list reloads each time you return to the tab, so a new order appears without restarting the app. The tab bar stays visible on this list.



Screenshot — Orders tab: each order row shows the store, date and time, a colored status pill, up to three item thumbnails with an item count, and the total.

3.6 Order Detail and Tracking

Tapping an order opens its detail screen. At the top is the heading "Order #" followed by the first eight characters of the order id, with the status pill beside it, then the store name and the time the order was placed, and a one-line status message (for example "Restaurant is preparing your order"). Below that is the order tracker: six numbered circles joined by lines — Placed, Accepted, Preparing, Ready, On the way, Delivered — with finished steps checked and the line filled up to the current step. Because six labels do not fit a phone's width, the tracker shows a single caption under the circles instead, such as "Step 3 of 6 · Preparing". The two delivery statuses share step 5: Partner assigned and On the way both show "Step 5 of 6 · On the way" (the status pill and message tell them apart). If the restaurant rejects the order, or the order is cancelled, a red banner ("Restaurant rejected your order — payment refunded" or "Order cancelled") replaces the tracker. If payment

failed, the screen shows "Payment failed. Your order was not placed — please try checking out again." instead of the tracker.


Below the tracker the screen shows: a Deliver to card (your name, email and phone — the phone is a tap-to-call link when it is a normal +91 number, otherwise plain text — then your delivery address and, if you entered one, the delivery note, or "No delivery address on file"); an Items card with each item's photo, quantity, chosen options, any special instructions and line total; a totals block (Subtotal, Delivery fee, Total, and Payment, for example "Paid · Cash on delivery"); and a timeline of times for the stages the order has reached (Placed, Accepted, Picked up, Delivered).

Demo mode: when the Admin has ticked Automatic order acceptance on the web, a paid order moves through Accepted, Preparing, Ready, Partner assigned and On the way by itself, about 3 seconds per step, so the tracker above advances without the store or the delivery partner doing anything; the courier animation then delivers it.


Once a delivery partner is assigned (status Partner assigned or On the way), a courier card appears below the tracker with a "Delivery partner" label (the partner's name is not shown), an initials circle and Call / Message icon buttons.

Not fully wired up yet: the courier card's Call and Message buttons. Both show an alert ("isn't wired up to a real backend yet") rather than placing a call or opening a chat — there is no telephony or messaging integration in this build.


While a partner is assigned or on the way, a map below the courier card shows the store (S), your delivery address (H) and, once the partner has reported a position, the partner (D), joined by a dashed straight line. Under it the screen says when the position was last updated and about how far the partner is from your address; when the partner's last position is more than 5 minutes old, the screen shows only "Last seen ... (location may be out of date)" and no distance. The distance is a straight-line estimate, not the road route, and there is no arrival time on the phone. After delivery the map stays as a final store-to-address view. The map is drawn by the phone's own maps (Apple Maps on iPhone, Google Maps on Android); if it cannot be shown, the partner's coordinates are shown as text instead. The whole detail screen refreshes automatically every 3 seconds while it's open, and stops refreshing once the order reaches a final status (Delivered, Cancelled or Rejected).




Screenshot — Order detail just after placing: "Step 1 of 6 · Placed", the Deliver to card (blurred here), the Items card with photos, and totals.



Screenshot — Order detail with a delivery partner assigned: six-step tracker at "Step 5 of 6 · On the way", the courier card and the live map card. The map area is shown here from the web app, which draws a road route; the phone's own map shows the same pins (S store, H your address, D partner) joined by a dashed straight line, because the phone has no road route. Demo data.



Screenshot — Order detail once delivered: all six steps checked ("Step 6 of 6 · Delivered"). Personal details blurred.



Screenshot — Order detail scrolled down: items, totals and payment, and the timeline of times (Placed, Accepted, Picked up, Delivered). Personal details blurred.

3.6.1 Courier Animation and Automatic Delivery

Delivery partners only mark an order picked up; they cannot mark it delivered. Once your order is On the way, its detail screen opens a "Your order is on the way!" modal with an animated courier scene and a countdown that reads "Arriving in 15s". The animation always plays for a full 15 seconds from the moment the modal first appears, however long ago the partner picked the order up. The animation always plays, even if the phone's Reduce Motion accessibility setting is on.

Your order is on the way!


Your Fresh & Quick rider is heading to you.



Arriving in 8s

Screenshot — The courier animation modal on a phone: "Your order is on the way!", the rider scene and the 15-second countdown (here "Arriving in 8s").

When the countdown ends the modal briefly shows "Confirming delivery...", then "Delivered! Enjoy your meal.", and the order becomes Delivered (step 6 of 6); there is no Done button: the modal closes itself 3 seconds after it shows. The delivered email is sent at that moment, once per order. If you leave the screen part-way through and come back while the app stays open, the animation resumes where it left off. If delivery could not be confirmed straight away, the modal says "We couldn't confirm delivery just yet — your order will be marked delivered shortly." and shows a Close button. This flow has been checked on a real iPhone.



Screenshot — The order marked *Delivered* automatically when the animation ends: status pill "*Delivered*" and "*Step 6 of 6 · Delivered*".
Personal details blurred.


If you never open the order after pickup, nothing is lost: the platform completes the delivery by itself 20 seconds after pickup and sends the same single delivered email, so the order screen does not need to be open for delivery to complete. Either way an order is delivered exactly once.

3.6.2 Rating Your Order

Once an order is Delivered you can rate it. Open the order from the Orders tab: a Rate your order card appears below the items. Only the store rating is required. The card has these parts:


- The store - tap 1 to 5 stars (tap the same star again to clear it) and, if you like, write a comment of up to 1,000 characters.
- Add a photo - optional, one photo from your photo library (JPEG, PNG or WebP, up to 3 MB). Its file name is shown with a Remove link until you send the review.
- The dishes - optional stars for each dish in the order; a short comment box (up to 500 characters) appears for each dish you rate.
- The delivery - optional stars for the delivery partner, with a comment of up to 500 characters. The card asks you to rate the rider's handling and courtesy, not the restaurant's wait. This part appears only when a delivery partner delivered the order.

Tap Submit review to send it. Each order can be reviewed once and a review cannot be edited or deleted afterwards, so check it before you send. If something is wrong, for example the photo is too large or the wrong type, a red message appears above the button and nothing is sent. A review does not trigger a refund; for a wrong or missing item contact support.



Screenshot - A delivered order: the line "Your delivery partner · New partner" and the Rate your order card with star rows for the store, the dishes and the delivery. Android emulator, throwaway test data.

After you send, the card is replaced by Your review: your stars, comment, photo, the dish and delivery ratings, and the store's reply if it has answered. If the Fresh & Quick team has hidden your review, the card says so.



Screenshot - After sending: the Your review card with the stars, comment, photo and the dish and delivery ratings.


The line “Your delivery partner” above the card shows the partner's average stars and number of ratings, for example “★ 4.6 (12 ratings)”, once the partner has 5 ratings; until then it says “New partner”. It appears as soon as a partner is assigned. Everyone who opens the store's screen can see your first name and last initial, stars, comment, photo and dish ratings, plus the store's reply. Your delivery rating and its comment go to the delivery partner without your name, and to the Fresh & Quick team. About an hour after delivery an email asking how your order was is sent to the address you entered at checkout; it is not sent if you have already reviewed the order.

3.7 Account (tab, new)

The Account tab replaces the earlier build's separate top-level navigation to account-related screens with a single screen. At the top is a profile card showing your name and email, with a Reset password link underneath: tapping it sends a password-reset email to your account address, and the link changes to “Reset email sent” once the server accepts it. Below the card are four rows:

- Notifications — opens the Notifications screen (section 3.7.2). A red badge on the row shows how many notifications are unread.
- Wallet — opens your wallet: credit balance, referral code and credit history (section 3.7.1). No real card or bank details are ever stored or shown, since this app uses mock payments only.
- Help — opens a static FAQ screen covering finding stores, placing and tracking orders, cancellation, and payment methods — the same content as Chapter 5 of this manual.

- Sign out — confirms with a native dialog, then signs you out and returns you to the role picker.



Screenshot — Account tab: your name and email (blurred here), Reset password, Notifications with its unread badge, Wallet, Help and Sign out.

3.7.1 Wallet and Referrals

The Wallet screen has three cards:

- Wallet credit — your balance. Credit comes only from referrals: you cannot add money, withdraw it or send it to someone else, and it does not expire. Use it at checkout with the Use wallet credit switch (section 3.4.1).
- Refer a friend — your referral code with a Share button that opens the phone's share sheet with a ready message. A friend types the code in the optional Referral code field when they sign up. When the friend's first order is delivered and its subtotal is ₹100 or more, you and your friend each get ₹50. You can earn up to 10 referral rewards and cannot refer yourself. The card also shows Friends joined and Rewards earned.
- History — every credit and use, newest first, each with a date and signed amount: Referral reward, Welcome bonus (the friend's ₹50), Used at checkout, Refunded credit (returned when an order is cancelled or rejected) and Adjustment. With none it says “No wallet activity yet.”

Not illustrated in this version: the Wallet screen is described in text only.

3.7.2 Notifications and Push

The Notifications screen lists your updates newest first: an update for every status change of your orders (placed, accepted, preparing, ready, partner assigned, on the way, delivered, and so on) and wallet events (referral reward, welcome bonus, refunded credit). Unread items are shown in bold; Mark all read clears them, and Load more shows older ones. The badge on the Account tab's Notifications row counts what is unread.

Settings are at the bottom of the same screen: switches for Order updates, Wallet updates, Promotions and Push notifications. Switching a category off stops new notifications of that kind; Push notifications switches off push only. SMS and WhatsApp are listed but disabled with “Not available yet”. Emails are not controlled here.

Push: the first time you open the Account tab (customers) or the dashboard (delivery partners) the phone asks permission to send notifications and registers its Expo push token with your account; signing out removes it. A push arrives as a normal banner. Tapping it opens the order it is about (customers) or the Notifications screen, but only while the app is still running. Push needs an Expo push token, so it works on an iPhone in Expo Go once

an EAS project id is set; Android Expo Go cannot receive remote push, and if registration is not possible the app simply carries on without it. The inbox works either way.

Not illustrated in this version: the Notifications screen is described in text only.

3.8 Where Things Moved From the Previous Build

If you used the app before this redesign, here's a quick map from old to new:

- Home, Cart, Checkout as separate always-visible nav links → Home is now a tab; Cart is a bottom sheet reached via the floating cart pill (see below) or the Checkout screen's back button; Checkout is reached from the cart.
- A single long checkout form → the same fields, now grouped into three tap-to-expand rows plus a separate contact-details block, with the submit button pinned to the bottom of the screen instead of scrolling with the form.
- Wallet and Help as their own reachable screens → both now live one tap deeper, under the Account tab.
- A plain order-status text line → the six-step order tracker described in §3.6, inside a full order detail screen.

One more piece of new chrome: whenever your cart has at least one item, a floating pill (“N items · View cart · ₹total”) appears above the tab bar on the Home and Store Detail screens — tapping it opens the cart bottom sheet directly. It's hidden on the Cart, Checkout, Account, and Orders screens themselves.

Chapter 4 — Delivery Partner App

The Delivery Partner App opens on a dashboard once you're signed in, mirroring the web delivery portal's dashboard, with a second History screen reached from a History link in the header. The header also shows your name with a Reset password link (same behavior as the Customer Account tab, see §3.7). The dashboard shows only active work: your active deliveries first, then orders available to accept. A My rating card sits under the Online/Offline toggle (section 4.7).

4.1 Signing In


From the role picker, choose Delivery Partner and sign in with your delivery partner account's email and password.

4.2 Going Online and Offline

At the top of the dashboard is a large Online/Offline toggle. Tap it to switch status; while toggling, a loading indicator shows in place of the label. While you are Offline the Available orders section only says "Go online to see available orders."; you only see available orders, and only send location pings, while toggled Online.

4.3 Available Orders

The Available orders section lists orders that have reached Ready status and that no partner has accepted yet. Each card shows the store name and pickup address, the items in the order (with photos), the order amount, and an Accept button. To protect the customer's privacy, the customer's name, phone number and address are not shown here — the card says "Customer details appear after you accept." Tap Accept to take the order: it moves into Your active deliveries and is no longer visible to other partners. With nothing available the section says "None right now." The list refreshes automatically every 10 seconds while you're online. Note: when the n8n automation is running, a ready order is assigned automatically within about 10 seconds to the nearest online partner (by last-known location), so it usually appears straight under Your active deliveries instead of waiting here; the Available list only holds an order when no online partner has a location.




Wireframe — Delivery dashboard with an Available order card (pickup store and address, items, Accept). Drawn from the app's source with demo data: this card could not be captured on the phone because, in this build, a ready order is auto-assigned to a partner within seconds (see below).

4.4 Your Deliveries and Advancing Status

The Your active deliveries section lists the orders you have accepted that are not finished yet (status Partner assigned or On the way); with none it says "No active deliveries." Each card shows the order number, a status pill, the amount, the Pickup store and its address, the Drop-off details (see §4.5), and the items with photos. A single action button advances the order: Mark picked up while the order is Partner assigned. After you mark it picked up the order is On the way and the card shows "Customer is receiving the order..." in place of a button — there is no Mark delivered button. The customer's app plays a 15-second courier animation and then marks the order Delivered automatically (or the system does it 20 seconds after pickup if the customer never opens the order). There is no way to skip a step or move an order backward. A delivered order leaves this list and moves to History. (The first figure below shows an assigned delivery with the Mark picked up button; the second shows the same delivery after pickup.)

Demo mode: when the Admin has ticked Automatic order acceptance on the web, an assigned order is picked up automatically about 3 seconds after it is assigned, so you do not need to tap Mark picked up (the button still works).




Screenshot — An assigned delivery on the partner dashboard, with the Mark picked up button. Drop-off details masked.


4.5 Drop-off Details and History

Once you have accepted an order, its active card shows the drop-off details: the recipient's name, their phone number (tap it to call when it is a normal +91 number), the full delivery address and the delivery note, if there is one. You can see a customer's phone and address only while the order is Partner assigned or On the way for you; the old View address button no longer exists because the details are shown directly on the card. This build has no Google Maps key configured, matching the Customer App's own coordinate-only tracking view.

The History link in the dashboard header opens the History screen: your finished orders, newest first, up to your 50 most recent. Each card shows the pickup store, who the order was delivered to, when it happened and a short summary of the items — no phone number or address is shown for finished orders. A Refresh button reloads the list and a Back to dashboard link returns you to the dashboard; with nothing finished yet it says "No completed deliveries yet."



Screenshot — The active delivery after Mark picked up: status "On the way" and the note "Customer is receiving the order...". The partner has no further button; the customer's phone completes the delivery. Drop-off details masked.



Screenshot — Delivery History screen: finished deliveries with pickup store, delivered-to name (blurred here), time and items summary.


4.6 Location Sharing

While you're toggled Online, the app asks for permission to use your device's foreground location and, once granted, sends a location ping to the server roughly every 15 seconds so the platform has a rough sense of where online partners are. This only happens while the app is open in the foreground and you're online — the app does not track or share your location in the background or while offline, and a missed ping (for example, if location is briefly unavailable) is not shown as an error; it's simply skipped until the next successful reading.

4.7 My Rating

The Dashboard shows a My rating card under the Online/Offline toggle. It shows your average stars and how many ratings you have, for example “★ 4.5 (2 ratings)”. With none yet it says “No ratings yet.” While you have fewer than 5 ratings the card adds a note that customers see “New partner” until you have 5 ratings. Below that are up to your three most recent customer comments with their stars. Comments never show the customer's name or the order.

Customers rate the delivery after an order is Delivered, and it is optional for them, so many deliveries are never rated. You cannot reply to or remove a rating.



Screenshot - Delivery Dashboard with the My rating card: average, number of ratings, the New partner note and recent comments. Android emulator, throwaway test data.

4.8 Notifications

The dashboard header has a Notifications link that shows the unread count, for example “Notifications (2)”. It opens the Notifications screen (the same screen customers use, section 3.7.2), where a New delivery notification (“Order #... from <store> is assigned to you.”) appears when an order is assigned to you. Mark all read, Load more and the settings card work as described there; for a delivery partner the settings are Order updates and Push notifications. A tapped push opens the Notifications screen while the app is running.

Chapter 5 — FAQ & Troubleshooting

These are the same questions shown on the Customer App's own Help screen (Account tab → Help), plus a couple of mobile-specific notes.

Question	Answer
How do I find restaurants or stores?	Use the search pill on Home, or tap a category chip. Home also shows a scrollable list of nearby open stores, plus an "Order again" row if you have order history.
How do I place an order?	Add items to your cart from a store's menu screen (configuring options first if the item has any), review the cart bottom sheet, then go to Checkout to enter contact details, delivery address, and a payment method.
Can I order from more than one restaurant at once?	No — a cart can only hold items from one store at a time. Adding an item from a different store prompts you to clear your current cart first.
How do I track my order?	After placing an order you land on its detail screen, which shows a six-step tracker (Placed, Accepted, Preparing, Ready, On the way, Delivered) with a "Step N of 6" caption, plus your items, delivery details and totals. It refreshes automatically every 3 seconds. You can also find current and past orders under the Orders tab.
How do I cancel an order?	Orders can only be cancelled by the store before they accept it, or automatically if payment fails. Once a store accepts an order, it can no longer be cancelled from the app.
What payment methods are supported?	This is a demo app — all payments are mocked. Choose Mock Card, Mock UPI, or Cash on Delivery at checkout; no real payment is ever processed and no real card or bank details are stored.
Why doesn't tapping the tip buttons in my cart change my total?	The tip selector is UI-only in this build — there's no backend column for it yet, so a selected tip is never added to your order. The cart screen says this directly under the selector.
Why does tapping Call or Message on my delivery partner just show a pop-up?	Those buttons on the courier card are demo stubs — there's no telephony or chat integration in this build. The pop-up is expected, not an error. (Your own phone number on the order, if it is a normal +91 number, is a real tap-to-call link.)
The app can't reach the server / nothing loads	This is a demo/development build that points at one specific server address (your development machine's LAN IP, set via EXPO_PUBLIC_API_BASE_URL — see section 2.5). If Home, Store Detail, or any other screen fails to load data, the development server is most likely not running, or the phone is not on the same Wi-Fi network as it — this is expected for a local/dev deployment, not a bug to work around in the field. Contact whoever set up your build to confirm the server address.
Does the app show my delivery partner's location on a map?	In the Customer App, yes: while a partner is assigned or on the way, the order screen has a map with the store, your address and, once the partner has reported a position, the partner, joined by a dashed straight line with an approximate

Question	Answer
	distance (section 3.6). It is not turn-by-turn tracking and has no arrival time. The Delivery Partner App shows the drop-off address as text (section 4.5).
Will I get an email about my order?	Yes. An email is sent to the email address you entered at checkout when the restaurant accepts your order and again when the order is delivered. About an hour after delivery you also get an email asking how your order was, unless you have already reviewed it (section 3.6.2).
Why does checkout ask for my phone number?	A valid Indian 10-digit mobile number is required so the delivery partner can reach you. It is shown on your order and, to the delivery partner, only while your order is assigned to them or on the way.
What can a delivery partner see about me?	Partners who have not accepted your order see only the store, items and amount. After a partner accepts, they see your name, phone, address and delivery note until the order is delivered; finished orders in their History show only who it was delivered to.
How do I create an account?	On the Customer sign-in screen tap "Need an account? Sign up", enter your full name, email and a password of at least 6 characters, and tap Sign Up. You are not signed in automatically: a pop-up says your registration approval is in progress, and you receive an email once the administrator has reviewed it. You can log in after it is approved. The same account also works on the web app. Delivery partner accounts cannot be created in the app — an administrator adds them.
Why did my order turn Delivered by itself?	Delivery partners only mark an order picked up. After pickup, your order screen plays a 15-second courier animation ("Arriving in 15s") and the order is then marked Delivered automatically, and the delivered email is sent. If you never open the order, the system marks it Delivered 20 seconds after pickup. See §3.6.1.
Can I rate my order or leave a review?	Yes. Once an order is Delivered, open it from the Orders tab and fill in the Rate your order card: stars for the store (required) and, optionally, a comment, one photo, dish ratings and a rating for the delivery partner. Each order can be reviewed once and a review cannot be edited or deleted afterwards (section 3.6.2).
Who can see my review, and how do I report one?	Everyone who opens the store's screen can see your first name and last initial, stars, comment, photo and dish ratings, plus the store's reply. Your delivery rating and its comment go to the delivery partner without your name and to the Fresh & Quick team. To report someone else's review tap Report under it and choose a reason; you cannot report your own review (section 3.2.1).
Why does my delivery partner show "New partner"?	A partner's average is shown only after the partner has 5 ratings, so a partner with fewer than 5 shows New partner instead of a number. Delivery partners see their own rating on their Dashboard (section 4.7).
How do I use a promo code?	On Checkout, find the Promo code section, type the code and

Question	Answer
	tap Apply, or tap one of the suggested codes. The discount and the new total appear straight away; Remove takes the code off. One code per order, and it takes money off the food, never the delivery fee. If a code is refused, the message under the box says why.
What is my wallet and how do I get credit?	Open the Account tab, then Wallet. It shows your credit balance, your referral code and every credit and use. Credit comes only from referrals: when a friend you referred has their first order delivered (subtotal ₹100 or more), you and your friend each get ₹50. Use it at checkout with the Use wallet credit switch. It cannot be bought or withdrawn.
Where are my notifications?	Account tab, then Notifications (delivery partners: the Notifications link on the dashboard). Settings for order updates, wallet updates, promotions and push are at the bottom of that screen; SMS and WhatsApp are not available yet. Push banners need an iPhone in Expo Go with an EAS project id set.


Chapter 6 — Ask Zippy

6.1 What Ask Zippy Is

Ask Zippy is the platform's built-in help assistant. You type a question in plain words and Zippy answers it in a chat sheet, so you do not have to leave your order or search the manual. It is available in both the Customer App and the Delivery Partner App.

6.2 Opening Zippy and Asking a Question

An orange Ask Zippy button (marked with a lightning bolt) floats near the bottom-right of the Customer App and Delivery Partner App screens. Tap it to open the chat sheet, which slides up over the screen, and tap the close button to dismiss it. A new chat opens with a short welcome message and three suggested questions; tap one or type your own and send it. The answer appears word by word as Zippy writes it, and it ends with a short note naming the guide it came from. Ask Zippy needs you to be signed in. If you are signed out and tap the button, a pop-up says “I am sorry I cannot respond to you till you register and log in. This is necessary to ensure that only validated people are allowed to use the Application & Chat.” It has two buttons: Close, which dismisses it, and Register or log in, which opens Customer Log In.




Screenshot — Ask Zippy in the Customer App: the button on the Home tab (left), a new chat with suggested questions (middle) and Zippy's answer to "How do I place an order?" (right).

6.3 Asking about stores and menus

Zippy can answer questions about stores and dishes using their current details. Examples: "Is Dosa Corner open right now?", "What does the Cheese Dosa cost?", "Which stores have free delivery?", "What options does the Cheese Dosa have?"

- Prices, delivery fees and open or closed status are looked up when you ask and can change at any time, so check them again in the cart and at checkout before you pay.
- When Zippy needs to look up store details, a short lead-in line may appear and then disappear before the real answer starts appearing word by word, so a store question can still take a few seconds to begin. Any card appears when the answer has finished. If you start a new chat, open History or sign out while an answer is still being written, it stops and is not saved; closing the chat panel lets it finish.
- For questions about nearby stores, Zippy uses your phone's location. The first time you ask, your phone asks permission to share it while the app is open; if you say no, Zippy cannot sort by distance but can still answer about ratings, delivery fees and which stores are open. The location is used only for that question and is not saved.
- Zippy can also look up your own orders when you are signed in as a customer and ask about them: the status, what was in the order, the totals, the payment, and the delivery details on it. Example: "Where is my order?" It cannot see anyone else's orders, and it cannot place, change, cancel or pay for an order. Order details are used only to answer the question you asked.
- When you are signed in as a customer, Zippy can also change your cart for you. Ask, for example, "Add two Cheese Dosas to my cart", "Order what I had last time", "Make the Cheese Dosa three", "Remove the lassi" or "Empty my cart". Zippy does not change the cart by itself: it shows a card describing the change, and nothing happens until you tap Confirm. Tap Dismiss to ignore the card. Each card can be confirmed once.
- Adding from a different store than the one already in your cart replaces the cart when you confirm, and the card says so beforehand, for example "Confirming replaces the 3 items from Dosa Corner in your cart." Closed or suspended stores and unavailable dishes are refused; when you ask to repeat a past order, unavailable dishes are skipped and listed. Quantities are 1 to 20, a reply shows at most 3 cards, and for a dish with a required choice (such as a size) Zippy asks which option you want before showing the card.



Screenshot — Ask Zippy proposing a cart change in the Customer App: the Add to cart card with Confirm and Dismiss. This card says that confirming replaces the items already in the cart from another store; nothing changes until you tap Confirm. Demo data.

- Zippy does not place, pay for or cancel orders. (Order notes are covered below.) After confirming a change you still review the cart and check out yourself (or ask Zippy for the Go to checkout card, below). Cart changes are available only to signed-in customers; stores, delivery partners and admins get none. Confirm works anywhere in the Customer App.
- Checkout from chat: when you are signed in as a customer, ask Zippy to check out, for example "Check out for me" or "Take me to checkout", and it shows a Go to checkout card. Tap it once and the chat sheet closes and the Checkout screen opens for your current cart. Zippy refuses, with no card, if your cart is empty, the store is closed or suspended, or a dish is unavailable. You enter your own name, contact details and delivery address and pay on the Checkout screen; Zippy never places or pays for an order and never asks for those details or card numbers. If your cart changed to a different store after the card was shown, the card says "Your cart changed, ask me again."
- Order note from chat: when you are signed in as a customer and your cart is not empty, ask Zippy to add, change or remove a note for the store, for example "No onions please". Zippy shows a card with the exact note and nothing changes until you tap Confirm. The note is the order's delivery note, so the store and the delivery partner can read it. It can be at most 500 characters; a longer note is refused, not cut, so shorten it and ask again. Double quotes in the note are saved as single quotes, and Zippy uses only your own words. If your cart changed after the card appeared, the tap says "Your cart changed, ask me again."

6.4 Chats, History and New Chat

Tap New chat to start a fresh conversation. Your chats are saved and a history button lets you see earlier chats and continue one. History is shared with the website, so a chat started there can be continued on your phone and the other way round.

6.5 What it can and cannot do

Zippy answers how-to questions about using Fresh & Quick, such as placing an order, tracking it, what each order status means, payments, and managing your account. It answers from the platform's own guides and says which guide the answer came from. Zippy is role-aware: a customer is shown customer guides, and a vendor, delivery partner or admin is shown the guides for their own portal.

Zippy can look up stores, dishes, prices, options and whether a store is open, using their current details (see the section on asking about stores and menus). When you are signed in as a customer it can also look up your own orders, and it cannot see anyone else's. It cannot place, change, cancel or pay for an order. The only thing it can change is your cart, and only after you tap Confirm on a card, and it can open the Checkout screen for you with a Go to checkout card (see section 6.3). If the guides do not cover a question, Zippy says so instead of guessing.

6.6 Limits, privacy and support

- Each question can be up to 1,000 characters.
- By default, each signed-in user can send up to 10 questions per minute and 60 per day (the site owner can change these). If you go over, Zippy tells you how many seconds to wait, or to try again tomorrow; if Zippy is busy for everyone, it asks you to try again in a few minutes.
- Your questions are sent to Anthropic (Claude) and OpenAI to produce the answer. Do not type passwords or card numbers into the chat. When a question needs your order details, those details are sent too.
- Under the platform's policy, saved Zippy chats with no activity for 30 days are deleted by a nightly cleanup. Orders are kept, and may be deleted on request. To have your orders deleted, or for a problem Zippy cannot solve, contact support at vishalshah1973@gmail.com or +919820020000.

Chapter 7 — Admin App

The Admin App is a small phone version of the web Admin Portal for administrators. It has two screens: a read-only Overview and a Registrations screen for approving or rejecting new customer registrations. Everything else in the Admin Portal (orders, vendors, delivery partners, coupons, reviews, the Automatic order acceptance setting) is still web-only. This chapter has no screenshots; the screens are described in text.

7.1 Admin Log In

On the start screen tap Admin. Enter your administrator email and password and tap Log In. If the email or password is wrong, the screen shows the error under the form. If the account is not an administrator (for example a customer account), the screen shows “This account is not an admin account.” and you are signed out. The Admin button is visible to everyone, but only an administrator account gets in, and the server checks the role again on every admin request. Like the other apps, it does not remember your session: you sign in again each time you open it from scratch.

7.2 Overview and Registrations Tabs

After logging in, the Admin App opens with two tabs at the bottom: Overview and Registrations. The Registrations tab shows a number badge with how many registrations are waiting for approval; the badge refreshes by itself every 30 seconds and right after you approve or reject a registration.

7.3 Overview

The Overview shows four tiles: Registrations awaiting approval (tap it to open the Registrations tab), Active orders, Vendors and Revenue (revenue does not include cancelled or rejected orders). It is read-only. Pull down to refresh. If the numbers cannot be loaded, a red message appears at the top. A Sign out link at the top right of the screen signs you out and returns you to the start screen.

7.4 Registrations

When someone signs up in the Customer App or on the website, their account waits here for an administrator. The Registrations screen has two tabs at the top: Pending and History. The list refreshes every 30 seconds while the screen is open, and you can pull down to refresh it. While the list loads it says “Loading registrations...”; an empty Pending tab says “No registrations are waiting for approval.” and an empty History tab says “No decisions yet.”

Each card shows the person's name, email, phone number, address (line 1, city and pincode) and when they registered. A Pending card has two buttons:

- Approve — approves the registration at once. The customer can then log in, and is emailed that the account is approved.
- Reject — opens a box titled with the person's name. A reason is required (up to 500 characters) and the box says the reason is emailed to the customer. If the reason is empty, a message appears in the box and nothing is sent. Tap Reject in the box to confirm, or Cancel to go back.

Only one decision is saved at a time, so the buttons are disabled while one is being processed. If another administrator has already decided the same request, you see “This request was already decided.” and the list refreshes. The History tab lists decided registrations with Approved or Rejected and the time of the decision; a rejected card also shows the reason you gave.

Approving or rejecting from the phone sends the same emails as doing it on the web Registrations page. Because those emails are real, only decide registrations you mean to decide.

Appendix A — Order Status Reference

Every order moves through a fixed status chain. The table below lists every possible status, the label shown in the app, and the step of the six-step tracker it maps to (Placed 1, Accepted 2, Preparing 3, Ready 4, On the way 5, Delivered 6). This applies identically to orders viewed in the Customer App and the Delivery Partner App, since both read the same underlying order record, and the status colors match the web portals.

Status	Meaning
placed (label: Placed)	Tracker step 1 of 6. The customer has submitted the order and payment is being resolved; waiting for the restaurant.
accepted (label: Accepted)	Tracker step 2 of 6. The store has accepted the order and will begin preparing it.
preparing (label: Preparing)	Tracker step 3 of 6. The store is actively preparing the order.
ready (label: Ready)	Tracker step 4 of 6. The order is ready for pickup; it now appears in online delivery partners' Available orders list (or is assigned automatically within seconds when the automation is running).
assigned (label: Partner assigned)	Tracker step 5 of 6. A delivery partner has accepted the order and is on the way to the store.
picked_up (label: On the way)	Tracker step 5 of 6. The delivery partner has collected the order and is on the way to the customer. The customer's order screen then plays a 15-second courier animation, after which the order becomes Delivered automatically.
delivered (label: Delivered)	Tracker step 6 of 6. The order has been handed to the customer. Final state. It is set by the customer's app after the animation (or by the system 20 seconds after pickup); delivery partners cannot set it.
cancelled (label: Cancelled)	No tracker step; a red banner is shown instead. The order was cancelled, for example because payment failed. Final state.
rejected (label: Rejected)	No tracker step; a red banner is shown instead. The restaurant rejected the order and payment is refunded. Final state.