Package 'adbcdrivermanager'

September 6, 2024

September 6, 2021
Title 'Arrow' Database Connectivity ('ADBC') Driver Manager
Version 0.14.0
Description Provides a developer-facing interface to 'Arrow' Database Connectivity ('ADBC') for the purposes of driver development, driver testing, and building high-level database interfaces for users. 'ADBC' https://arrow.apache.org/adbc/ is an API standard for database access libraries that uses 'Arrow' for result sets and query parameters.
License Apache License (>= 2)
Encoding UTF-8
RoxygenNote 7.3.2
Suggests testthat (>= 3.0.0), withr
Config/testthat/edition 3
Config/build/bootstrap TRUE
<pre>URL https://github.com/apache/arrow-adbc,</pre>
https://arrow.apache.org/adbc/current/r/adbcdrivermanager/
BugReports https://github.com/apache/arrow-adbc/issues
Imports nanoarrow (>= 0.3.0)
NeedsCompilation yes
Author Dewey Dunnington [aut, cre] (https://orcid.org/0000-0002-9415-4582), Apache Arrow [aut, cph], Apache Software Foundation [cph]
Maintainer Dewey Dunnington <dewey@dunnington.ca></dewey@dunnington.ca>
Repository CRAN
Date/Publication 2024-09-06 15:10:02 UTC
Contents
adbc_connection_get_info

```
      adbc_connection_join
      5

      adbc_database_init
      6

      adbc_driver_log
      7

      adbc_driver_monkey
      8

      adbc_driver_void
      8

      adbc_error_from_array_stream
      9

      adbc_statement_init
      10

      adbc_statement_set_sql_query
      11

      adbc_xptr_move
      12

      read_adbc
      13

      with_adbc
      14

Index
```

adbc_connection_get_info

Connection methods

Description

Connection methods

Usage

```
adbc_connection_get_info(connection, info_codes = NULL)
adbc_connection_get_objects(
  connection,
  depth = 0L,
  catalog = NULL,
  db_schema = NULL,
  table_name = NULL,
  table_type = NULL,
  column_name = NULL
)
adbc_connection_get_table_schema(connection, catalog, db_schema, table_name)
adbc_connection_get_table_types(connection)
adbc_connection_read_partition(connection, serialized_partition)
adbc_connection_commit(connection)
adbc_connection_rollback(connection)
adbc_connection_cancel(connection)
```

```
adbc_connection_get_statistic_names(connection)

adbc_connection_get_statistics(
   connection,
   catalog,
   db_schema,
   table_name,
   approximate = FALSE
)

adbc_connection_quote_identifier(connection, value, ...)
```

Arguments

connection	An adbc_connection
info_codes	A list of metadata codes to fetch, or NULL to fetch all. Valid values are documented in the adbc.h header.
depth	The level of nesting to display. If 0, display all levels. If 1, display only catalogs (i.e., catalog_schemas will be null). If 2, display only catalogs and schemas (i.e., db_schema_tables will be null). If 3, display only catalogs, schemas, and tables.
catalog	Only show tables in the given catalog. If NULL, do not filter by catalog. If an empty string, only show tables without a catalog. May be a search pattern.
db_schema	Only show tables in the given database schema. If NULL, do not filter by database schema. If an empty string, only show tables without a database schema. May be a search pattern.
table_name	Constrain an object or statistics query for a specific table. If NULL, do not filter by name. May be a search pattern.
table_type	Only show tables matching one of the given table types. If NULL, show tables of any type. Valid table types can be fetched from GetTableTypes. Terminate the list with a NULL entry.
column_name	Only show columns with the given name. If NULL, do not filter by name. May be a search pattern.
serialized_par	tition
	The partition descriptor.
approximate	If FALSE, request exact values of statistics, else allow for best-effort, approximate, or cached values. The database may return approximate values regardless, as indicated in the result. Requesting exact values may be expensive or unsupported.
value	A string or identifier.
• • •	Driver-specific options. For the default method, these are named values that are

converted to strings.

adbc_connection_init

Value

- adbc_connection_get_info(), adbc_connection_get_objects(), adbc_connection_get_table_types(), and adbc_connection_read_partition() return a nanoarrow_array_stream.
- adbc_connection_get_table_schema() returns a nanoarrow_schena
- adbc_connection_commit() and adbc_connection_rollback() return connection, invisibly.

Examples

```
db <- adbc_database_init(adbc_driver_void())
con <- adbc_connection_init(db)
# (not implemented by the void driver)
try(adbc_connection_get_info(con, 0))</pre>
```

```
adbc_connection_init Connections
```

Description

Connections

Usage

```
adbc_connection_init(database, ...)
adbc_connection_init_default(database, options = NULL, subclass = character())
adbc_connection_release(connection)
adbc_connection_set_options(connection, options)
adbc_connection_get_option(connection, option)
adbc_connection_get_option_bytes(connection, option)
adbc_connection_get_option_int(connection, option)
adbc_connection_get_option_double(connection, option)
```

```
database An adbc_database.

Driver-specific options. For the default method, these are named values that are converted to strings.

A named character() or list() whose values are converted to strings.
```

adbc_connection_join 5

subclass An extended class for an object so that drivers can specify finer-grained control

over behaviour at the R level.

connection An adbc_connection
option A specific option name

Value

An object of class 'adbc_connection'

Examples

```
db <- adbc_database_init(adbc_driver_void())
adbc_connection_init(db)</pre>
```

Description

It is occasionally useful to return a connection, statement, or stream from a function that was created from a unique parent. These helpers tie the lifecycle of a unique parent object to its child such that the parent object is released predictably and immediately after the child. These functions will invalidate all references to the previous R object.

Usage

```
adbc_connection_join(connection, database)
adbc_statement_join(statement, connection)
```

Arguments

connection A connection created with adbc_connection_init()

database A database created with adbc_database_init()

statement A statement created with adbc_statement_init()

Value

The input, invisibly.

6 adbc_database_init

Examples

```
# Use local_adbc to ensure prompt cleanup on error;
# use join functions to return a single object that manages
# the lifecycle of all three.
stmt <- local({
    db <- local_adbc(adbc_database_init(adbc_driver_log()))

    con <- local_adbc(adbc_connection_init(db))
    adbc_connection_join(con, db)

    stmt <- local_adbc(adbc_statement_init(con))
    adbc_statement_join(stmt, con)

    adbc_xptr_move(stmt)
})
# Everything is released immediately when the last object is released adbc_statement_release(stmt)</pre>
```

adbc_database_init

Databases

Description

Databases

Usage

```
adbc_database_init(driver, ...)
adbc_database_init_default(driver, options = NULL, subclass = character())
adbc_database_release(database)
adbc_database_set_options(database, options)
adbc_database_get_option(database, option)
adbc_database_get_option_bytes(database, option)
adbc_database_get_option_int(database, option)
adbc_database_get_option_double(database, option)
```

adbc_driver_log 7

Arguments

driver	An adbc_driver().
• • •	Driver-specific options. For the default method, these are named values that are converted to strings.
options	A named character() or list() whose values are converted to strings.
subclass	An extended class for an object so that drivers can specify finer-grained control over behaviour at the R level.
database	An adbc_database.
option	A specific option name

Value

An object of class adbc_database

Examples

```
adbc_database_init(adbc_driver_void())
```

adbc_driver_log	Log calls to another driver	

Description

Useful for debugging or ensuring that certain calls occur during initialization and/or cleanup. The current logging output should not be considered stable and may change in future releases.

Usage

```
adbc_driver_log()
```

Value

An object of class 'adbc_driver_log'

```
drv <- adbc_driver_log()
db <- adbc_database_init(drv, key = "value")
con <- adbc_connection_init(db, key = "value")
stmt <- adbc_statement_init(con, key = "value")
try(adbc_statement_execute_query(stmt))
adbc_statement_release(stmt)
adbc_connection_release(con)
adbc_database_release(db)</pre>
```

8 adbc_driver_void

adbc_driver_monkey

Monkey see, monkey do!

Description

A driver whose query results are set in advance.

Usage

```
adbc_driver_monkey()
```

Value

An object of class 'adbc_driver_monkey'

Examples

```
db <- adbc_database_init(adbc_driver_monkey())
con <- adbc_connection_init(db)
stmt <- adbc_statement_init(con, mtcars)
stream <- nanoarrow::nanoarrow_allocate_array_stream()
adbc_statement_execute_query(stmt, stream)
as.data.frame(stream$get_next())</pre>
```

adbc_driver_void

Create ADBC drivers

Description

Creates the R object representation of an ADBC driver, which consists of a name and an initializer function with an optional subclass to control finer-grained behaviour at the R level.

Usage

```
adbc_driver_void()
adbc_driver(x, entrypoint = NULL, ..., subclass = character())
```

x, entrypoint	An ADBC driver may be defined either as an init function or as an identifier
	with an entrypoint name. A driver init func must be an external pointer to a
	$DL_FUNC \ with \ the \ type \ AdbcDriverInitFunc \ specified \ in \ the \ adbc.h \ header.$
	Further key/value parameters to store with the (R-level) driver object.
subclass	An optional subclass for finer-grained control of behaviour at the R level.

```
adbc_error_from_array_stream
```

Value

An object of class 'adbc_driver'

Examples

```
adbc_driver_void()
```

```
adbc_error_from_array_stream
```

Get extended error information from an array stream

Description

Get extended error information from an array stream

Usage

```
adbc_error_from_array_stream(stream)
```

Arguments

stream

A nanoarrow_array_stream

Value

NULL if stream was not created by a driver that supports extended error information or a list whose first element is the status code and second element is the adbc_error object. The acbc_error must not be accessed if stream is explicitly released.

```
db <- adbc_database_init(adbc_driver_monkey())
con <- adbc_connection_init(db)
stmt <- adbc_statement_init(con, mtcars)
stream <- nanoarrow::nanoarrow_allocate_array_stream()
adbc_statement_execute_query(stmt, stream)
adbc_error_from_array_stream(stream)</pre>
```

10 adbc_statement_init

adbc_statement_init Statements

Description

Statements

Usage

```
adbc_statement_init(connection, ...)
adbc_statement_init_default(connection, options = NULL, subclass = character())
adbc_statement_release(statement)
adbc_statement_set_options(statement, options)
adbc_statement_get_option(statement, option)
adbc_statement_get_option_bytes(statement, option)
adbc_statement_get_option_int(statement, option)
adbc_statement_get_option_double(statement, option)
```

Arguments

An adbc_connection
 Driver-specific options. For the default method, these are named values that are converted to strings.
 A named character() or list() whose values are converted to strings.
 An extended class for an object so that drivers can specify finer-grained control over behaviour at the R level.
 An adbc_statement
 A specific option name

Value

An object of class 'adbc_statement'

```
db <- adbc_database_init(adbc_driver_void())
con <- adbc_connection_init(db)
adbc_statement_init(con)</pre>
```

Description

Statement methods

Usage

```
adbc_statement_set_sql_query(statement, query)
adbc_statement_set_substrait_plan(statement, plan)
adbc_statement_prepare(statement)
adbc_statement_get_parameter_schema(statement)
adbc_statement_bind(statement, values, schema = NULL)
adbc_statement_bind_stream(statement, stream, schema = NULL)
adbc_statement_execute_query(
   statement,
   stream = NULL,
   stream_join_parent = FALSE
)
adbc_statement_execute_schema(statement)
adbc_statement_cancel(statement)
```

statement	An adbc_statement	
query	An SQL query as a string	
plan	A raw vector representation of a serialized Substrait plan.	
values	A nanoarrow_array or object that can be coerced to one.	
schema	A nanoarrow_schema or object that can be coerced to one.	
stream	A nanoarrow_array_stream or object that can be coerced to one.	
stream_join_parent		
	Use TRUE to invalidate statement and tie its lifecycle to stream.	

12 adbc_xptr_move

Value

- adbc_statement_set_sql_query(), adbc_statement_set_substrait_plan(), adbc_statement_prepare(), adbc_statement_bind(), adbc_statement_bind_stream(), and adbc_statement_execute_query() return statement, invisibly.
- adbc_statement_get_parameter_schema() returns a nanoarrow_schema.

Examples

```
db <- adbc_database_init(adbc_driver_void())
con <- adbc_connection_init(db)
stmt <- adbc_statement_init(con)
# (not implemented by the void driver)
try(adbc_statement_set_sql_query(stmt, "some query"))</pre>
```

adbc_xptr_move

Low-level pointer details

Description

- adbc_xptr_move() allocates a fresh R object and moves all values pointed to by x into it. The original R object is invalidated by zeroing its content. This is useful when returning from a function where lifecycle helpers were used to manage the original object.
- adbc_xptr_is_valid() provides a means by which to test for an invalidated pointer.

Usage

```
adbc_xptr_move(x, check_child_count = TRUE)
adbc_xptr_is_valid(x)
```

Arguments

```
x An 'adbc_database', 'adbc_connection', 'adbc_statement', or 'nanoarrow_array_stream' check_child_count
```

Ensures that x has a zero child count before performing the move. This should almost always be TRUE.

Value

- adbc_xptr_move(): A freshly-allocated R object identical to x
- adbc_xptr_is_valid(): Returns FALSE if the ADBC object pointed to by x has been invalidated.

read_adbc 13

Examples

```
db <- adbc_database_init(adbc_driver_void())
adbc_xptr_is_valid(db)
db_new <- adbc_xptr_move(db)
adbc_xptr_is_valid(db)
adbc_xptr_is_valid(db_new)</pre>
```

read_adbc

Read, write, and execute on ADBC connections

Description

These are convenience methods useful for testing connections. Note that S3 dispatch is always on db_or_con (i.e., drivers may provide their own implementations).

Usage

```
read_adbc(db_or_con, query, ..., bind = NULL)

execute_adbc(db_or_con, query, ..., bind = NULL)

write_adbc(
  tbl,
  db_or_con,
  target_table,
  ...,
  mode = c("default", "create", "append"),
  temporary = FALSE
)
```

db_or_con	An adbc_database or adbc_connection. If a database, a connection will be opened. For read_adbc(), this connection will be closed when the resulting stream has been released.
query	An SQL query
	Passed to S3 methods.
bind	A data.frame, nanoarrow_array, or nanoarrow_array_stream of bind parameters or NULL to skip the bind/prepare step.
tbl	A data.frame, nanoarrow_array, or nanoarrow_array_stream.
target_table	A target table name to which tbl should be written.
mode	One of "create", "append", or "default" (error if the schema is not compatible or append otherwise).
temporary	Use TRUE to create a table as a temporary table.

14 with_adbc

Value

```
read_adbc(): A nanoarrow_array_stream
execute_adbc(): db_or_con, invisibly.
write_adbc(): tbl, invisibly.
```

Examples

```
# On a database, connections are opened and closed
db <- adbc_database_init(adbc_driver_log())
try(read_adbc(db, "some sql"))
try(execute_adbc(db, "some sql"))
try(write_adbc(mtcars, db, "some_table"))

# Also works on a connection
con <- adbc_connection_init(db)
try(read_adbc(con, "some sql"))
try(execute_adbc(con, "some sql"))
try(write_adbc(mtcars, con, "some_table"))</pre>
```

with_adbc

Cleanup helpers

Description

Managing the lifecycle of databases, connections, and statements can be complex and error-prone. The R objects that wrap the underlying ADBC pointers will perform cleanup in the correct order if you rely on garbage collection (i.e., do nothing and let the objects go out of scope); however it is good practice to explicitly clean up these objects. These helpers are designed to make explicit and predictable cleanup easy to accomplish.

Usage

```
with_adbc(x, code)
local_adbc(x, .local_envir = parent.frame())
```

Arguments

x An ADBC database, ADBC connection, ADBC statement, or nanoarrow_array_stream returned from calls to an ADBC function.

code Code to execute before cleaning up the input.

.local_envir The execution environment whose scope should be tied to the input.

with_adbc 15

Details

Note that you can use adbc_connection_join() and adbc_statement_join() to tie the lifecycle of the parent object to that of the child object. These functions mark any previous references to the parent object as released so you can still use local and with helpers to manage the parent object before it is joined. Use stream_join_parent = TRUE in adbc_statement_execute_query() to tie the lifecycle of a statement to the output stream.

Value

- with_adbc() returns the result of code
- local_adbc() returns the input, invisibly.

```
# Using with_adbc():
with_adbc(db <- adbc_database_init(adbc_driver_void()), {</pre>
  with_adbc(con <- adbc_connection_init(db), {</pre>
    with_adbc(stmt <- adbc_statement_init(con), {</pre>
      # adbc_statement_set_sql_query(stmt, "SELECT * FROM foofy")
      # adbc_statement_execute_query(stmt)
      "some result"
    })
 })
# Using local_adbc_*() (works best within a function, test, or local())
  db <- local_adbc(adbc_database_init(adbc_driver_void()))</pre>
  con <- local_adbc(adbc_connection_init(db))</pre>
  stmt <- local_adbc(adbc_statement_init(con))</pre>
  # adbc_statement_set_sql_query(stmt, "SELECT * FROM foofy")
  # adbc_statement_execute_query(stmt)
  "some result"
})
```

Index

adbc_connection, $3, 5, 10$	<pre>(adbc_connection_get_info), 2</pre>
adbc_connection_cancel	adbc_connection_set_options
<pre>(adbc_connection_get_info), 2</pre>	<pre>(adbc_connection_init), 4</pre>
adbc_connection_commit	adbc_database, 4, 7
<pre>(adbc_connection_get_info), 2</pre>	adbc_database_get_option
<pre>adbc_connection_get_info, 2</pre>	<pre>(adbc_database_init), 6</pre>
adbc_connection_get_objects	adbc_database_get_option_bytes
<pre>(adbc_connection_get_info), 2</pre>	<pre>(adbc_database_init), 6</pre>
adbc_connection_get_option	adbc_database_get_option_double
<pre>(adbc_connection_init), 4</pre>	<pre>(adbc_database_init), 6</pre>
adbc_connection_get_option_bytes	adbc_database_get_option_int
<pre>(adbc_connection_init), 4</pre>	<pre>(adbc_database_init), 6</pre>
adbc_connection_get_option_double	<pre>adbc_database_init, 6</pre>
<pre>(adbc_connection_init), 4</pre>	<pre>adbc_database_init(), 5</pre>
adbc_connection_get_option_int	adbc_database_init_default
<pre>(adbc_connection_init), 4</pre>	<pre>(adbc_database_init), 6</pre>
adbc_connection_get_statistic_names	adbc_database_release
<pre>(adbc_connection_get_info), 2</pre>	<pre>(adbc_database_init), 6</pre>
adbc_connection_get_statistics	adbc_database_set_options
<pre>(adbc_connection_get_info), 2</pre>	<pre>(adbc_database_init), 6</pre>
adbc_connection_get_table_schema	<pre>adbc_driver(adbc_driver_void), 8</pre>
<pre>(adbc_connection_get_info), 2</pre>	adbc_driver(), 7
adbc_connection_get_table_types	adbc_driver_log,7
<pre>(adbc_connection_get_info), 2</pre>	adbc_driver_monkey, 8
adbc_connection_init, 4	adbc_driver_void, 8
<pre>adbc_connection_init(), 5</pre>	adbc_error_from_array_stream, 9
adbc_connection_init_default	adbc_statement, 10, 11
<pre>(adbc_connection_init), 4</pre>	adbc_statement_bind
adbc_connection_join, 5	<pre>(adbc_statement_set_sql_query)</pre>
<pre>adbc_connection_join(), 15</pre>	11
adbc_connection_quote_identifier	adbc_statement_bind_stream
<pre>(adbc_connection_get_info), 2</pre>	<pre>(adbc_statement_set_sql_query);</pre>
adbc_connection_quote_string	11
<pre>(adbc_connection_get_info), 2</pre>	adbc_statement_cancel
adbc_connection_read_partition	<pre>(adbc_statement_set_sql_query)</pre>
<pre>(adbc_connection_get_info), 2</pre>	11
adbc_connection_release	adbc_statement_execute_query
<pre>(adbc_connection_init), 4</pre>	<pre>(adbc_statement_set_sql_query)</pre>
adbc connection rollback	11

INDEX 17

```
adbc_statement_execute_query(), 15
adbc_statement_execute_schema
        (adbc_statement_set_sql_query),
adbc_statement_get_option
        (adbc_statement_init), 10
adbc_statement_get_option_bytes
        (adbc_statement_init), 10
adbc_statement_get_option_double
        (adbc_statement_init), 10
adbc_statement_get_option_int
        (adbc_statement_init), 10
adbc_statement_get_parameter_schema
        (adbc_statement_set_sql_query),
        11
adbc_statement_init, 10
adbc_statement_init(), 5
adbc_statement_init_default
        (adbc_statement_init), 10
adbc_statement_join
        (adbc_connection_join), 5
adbc_statement_join(), 15
adbc_statement_prepare
        (adbc_statement_set_sql_query),
adbc_statement_release
        (adbc_statement_init), 10
adbc_statement_set_options
        (adbc_statement_init), 10
adbc_statement_set_sql_query, 11
adbc_statement_set_substrait_plan
        (adbc_statement_set_sql_query),
adbc_xptr_is_valid (adbc_xptr_move), 12
adbc_xptr_move, 12
execute_adbc (read_adbc), 13
lifecycle helpers, 12
local_adbc (with_adbc), 14
nanoarrow_array, 11, 13
nanoarrow_array_stream, 4, 9, 11, 13, 14
nanoarrow_schema, 11, 12
nanoarrow_schena, 4
read_adbc, 13
with_adbc, 14
write_adbc (read_adbc), 13
```