

Yet Another Linda (YAL) for Zibo Mod - User Manual

Version 1.5 (based on features as of October 2025)

(C) WAHLTHO & OBUTLER 2023-2025

VIRTUAL COPILOT PLUGIN FOR ZIBO MOD 738

1. Installation & Requirements

Installation: 1. Copy the main YAL folder into your X-Plane `X-Plane 11/Resources/plugins` folder. 2. Launch X-Plane and configure YAL via the settings window at "Plugins" -> "Yet Another Linda" -> "Settings".

Requirements: * X-Plane 11 or 12 (Windows, Mac/Intel/Arm, Linux) * Aircraft: B737-800 by Zibo * Optional: X-Camera plugin (will be detected automatically)

Please Note: * YAL has virtually no FPS impact as its main functions run once per second, not every frame. * When flying aircraft other than the Zibo B738, YAL remains idle and all its menus are inactive. * All custom commands for key/joystick assignment can be found in the X-Plane keyboard/joystick settings under the YAL/ . . . group.

2. Custom Commands

These commands can be assigned to keyboard keys or joystick buttons in the X-Plane settings menu.

Core Functions

- **Reset:** Resynchronizes YAL's internal state with the current aircraft state. Use this if a procedure seems stuck or the plugin appears out of sync.
- **Reset for New Flight:** Completely resets all procedure progress for a new flight. This should be used at the gate after landing to ensure a clean start for the next leg.
- **Cycle Through Procedures:** Manually triggers the next logical, uncompleted procedure (e.g., from "Engine Start" to "Before Taxi").

- **Skip Procedure Step:** Skips the current active step in a running procedure.
- **Abort Procedure:** Immediately stops the currently active procedure.

General Aircraft Control

- **Toggle Sim Freeze:** Freezes the aircraft's motion but allows you to interact with cockpit controls.
- **Master Caution + FMS CLR:** Acknowledges Master Caution, clears FMC messages, and silences the altitude alert horn.
- **Sync AP Heading with Ground Track:** Sets the MCP heading dial to the aircraft's current ground track.
- **Copy NAV1/MMR1 to NAV2/MMR2:** Copies the active frequency and course from the captain's side to the first officer's side.

Lights & Wipers

- **Both Wipers Up / Down:** Moves both wipers one step up or down.
- **Toggle Taxi Lights:** Toggles the taxi lights on/off.
- **Toggle Collision Lights:** Toggles the beacon lights on/off.
- **Toggle Landing Lights:** Toggles all landing lights on/off.
- **Toggle Logo Light:** Toggles the logo light on/off.
- **Toggle Runway Lights:** Toggles the runway turnoff lights on/off.
- **Toggle Position Lights:** Cycles the position lights between STEADY and STROBE & STEADY.

Systems

- **Toggle Transponder:** Toggles the transponder between STANDBY and TA/RA.
- **Toggle Both Flight Directors:** Toggles both FDs on/off.
- **Toggle Both Weather Radars:** Toggles both WXR displays on/off.
- **Toggle Both Terrain Radars:** Toggles both TERR displays on/off.
- **Toggle Window Heat:** Toggles all four window heat switches on/off.
- **Toggle Probe Heat:** Toggles both probe heat switches on/off.
- **Toggle Ice Protection:** Toggles wing and engine anti-ice systems on/off.

Plugin Control

- **Toggle Auto Functions:** A master switch to enable or disable all automatic functions of YAL.
- **Toggle Voice Readback:** Enables or disables voice confirmations for actions.
- **Toggle Voice Advice Only:** Switches YAL between executing actions automatically and only giving verbal advice.

3. Procedures

Manually Triggered Procedures

These checklists can be started at any time via the "Plugins" -> "Yet Another Linda" menu or by assigning their corresponding `YAL/ . . .` command to a key.

- **Cold and Dark Startup:** A full procedure from a completely powered-down state to a "Turnaround State" (APU running, systems ready for engine start).
- **Cockpit Initialization:** Prepares the cockpit for a new flight by setting lights, displays, and systems according to your preferences. It also resets the FMC and can trigger a flight plan import if YANSH is installed.
- **APU Startup:** Starts the APU and configures the electrical and bleed air systems.
- **Engine Startup:** Performs the full two-engine start sequence. Requires the APU to be running and providing bleed air.
- **Engine Shutdown:** A flexible procedure that can be used for a quick turnaround (leaving the APU running) or as part of a final shutdown.
- **Shutdown:** Powers down all aircraft systems and returns the aircraft to a "Cold & Dark" state.
- **Tests:** Executes a sequence of system tests (Fire, Stall Warning, etc.).

Automatically Triggered Procedures

These procedures are triggered automatically based on specific pilot actions or flight parameters.

- **Before Taxi Procedure**
 - **Trigger:** Taxi lights are switched ON **and** both engines are running.
 - **Actions:** Sets probe/window heat, starters to CONT, FDs on, etc.
- **Before Takeoff Procedure**
 - **Trigger:** Aircraft is on the runway, aligned with the correct heading, speed is zero, **AND** the transponder is set to TA/RA.
 - **Actions:** Sets position lights to STROBE, landing lights ON, autobrake to RTO.
- **After Takeoff Procedure**
 - **Trigger:** Automatically after liftoff.
 - **Actions:** Retracts gear above 200ft RA and disarms the autobrake.
- **During Climb Procedure**

- **Trigger:** During the climb phase.
- **Actions:** Sets Baro to Standard above transition altitude, handles flap retraction according to FMC speeds.
- **Above 10000 Feet Procedure**
 - **Trigger:** Climbing through the "Lower Airspace Altitude" (default 10000 ft).
 - **Actions:** Retracts landing lights, turns off seatbelt sign, sets engine starters to AUTO.
- **During Descent Procedure**
 - **Trigger:** During the descent phase.
 - **Actions:** Sets speed restrictions in the FMC, sets local QNH below transition level, handles flap extension.
- **Below 10.000 feet Procedure**
 - **Trigger:** Descending through the "Lower Airspace Altitude".
 - **Actions:** Turns on landing lights and seatbelt sign, sets the autobrake, and tunes ILS/GLS frequencies/courses.
- **Below 2.500 feet (RA) Procedure**
 - **Trigger:** Descending through 2,500 ft radio altitude.
 - **Actions:** Sets starters to CONT, extends landing gear (if flaps are set accordingly).
- **Below 1.000 feet (RA) Procedure**
 - **Trigger:** Descending through 1,000 ft radio altitude.
 - **Actions:** Sets final landing configuration (lights, speedbrake armed, landing flaps).
- **After Landing Procedure**
 - **Trigger:** After vacating the runway.
 - **Actions:** Configures the aircraft for taxiing to the gate (lights, transponder, flaps up, etc.).
- **At Parking Position Procedure**
 - **Trigger:** Parking brake is set at the gate.
 - **Actions:** Turns off taxi lights, seatbelt signs, and prepares for engine shutdown.

4. Settings

The settings window allows detailed customization of all automatic features.

General: * **Use Ground Power...**: If available, the plugin will use ground power instead of starting the APU during the Cold & Dark startup. *

Command Voice Readback: Provides voice announcements for most actions performed by the plugin. * **Automatic Functions:** A master switch for all automatic procedures and background tasks. * **Sim exit after Pause at TOD:** If the sim is paused at the Top of Descent, it will automatically save and

quit after the specified number of seconds (9999 to disable). * **Override**

Wake Effects: Suppresses wake turbulence effects from other aircraft. *

Automatic Anti Icing: Automatically enables wing and engine anti-ice when icing is detected. *

Automatic Wipers: Automatically controls wiper speed based on rain intensity. *

Automatic Center Tank Handling: Manages the center tank fuel pumps automatically. *

Automatic Baro Settings: Sets the altimeter to Standard or local QNH when passing transition altitude/level. *

Automatic Fueling (requires YANSH): When Automatic Functions are enabled, this automatically refuels the aircraft to match the Simbrief flight plan's ramp fuel during the Cockpit Initialization Procedure. *

View Changes during Procedures: Allows YAL to automatically switch to relevant cockpit views during procedures.

Customising: * **Set Speed Restriction 250:** Automatically sets the FMC speed restriction below 10,000 ft to 250 knots. *

* **Set Vref 30:** Automatically configures the FMC for a Flaps 30 landing. *

* **Lower Airspace Altitude (feet):** Sets the altitude for the "Above/Below 10000" procedures. *

* **Maximum Bank Angle (1-4):** Sets the bank angle selector during cockpit initialization. *

* **Set Lower Display Unit:** Configures the lower DU to your preferred setting on startup. *

* **Default Transponder Code:** Sets a default squawk code during initialization.

Views: * Assigns the corresponding X-Plane Quick Look or X-Camera view numbers for automatic view changes.

Instrument Panel Brightness: * Allows you to pre-configure all panel and display brightness levels, which will be applied during the Cockpit Initialization procedure. *

* **Ignore All Brightness Settings:** Prevents YAL from making any changes to panel lighting.

Misc: * **Debug mode log:** Enables verbose logging to the Log.txt file for troubleshooting.