

MqttMessageService
AlarmService
Station
AlarmBuilder
Frontend (AlarmOverview/Start)
evalTemps(station, currentTemp)
currentlyActive = overheatActive.get(gemId, false)
alt
!currentlyActive AND temp >= OVERHEATING_THRESHOLD
sendOverheatingAlarm(station, temp)
setLatestAlarmKind("Overheating Alarm")
setLatestAlarmMessage(msg)
setState(OVERHEATED)
build Alarm (status=ACTIVE, kind="Overheating Alarm")
attach Alarm
overheatActive.put(gemId, true)
setAlarmCount(activeAlarmCount +1)
currentlyActive AND temp <= OVERHEATING_CLEAR_THRESHOLD
clearOverheatAlarm(station, temp)
setState(isExecuting ? ACTIVE:POWER_ON_IDLE)
buildAlarm(status=CLEARED, kind="Notice Alarm")
attach Alarm
overheatActive.put(gemId, false)
setAlarmCount(activeAlarmCount -1)
(OVERHEATING_CLEAR_THRESHOLD<temp<OVERHEATING_THRESHOLD AND currentlyActive) OR (temp<OVERHEATING_CLEAR_THRESHOLD AND !currentlyActive)
no action
evalWear(station, wearIndex)
alt
wearIndex>=1.0 AND Alarm not already active
sendMaintenanceDueAlarm(station)
setLatestAlarmKind("Maintenance Due Alarm")
setLatestAlarmMessage(msg)
buildAlarm(status=ACTIVE, kind="Maintenace Due Alarm")
attach Alarm
setAlarmCount(alarmCount+1)
maintenanceDueActive.put(gemId, true)
wearIndex<0.8
maintenanceDueActive.put(gemId, false)
getAlarmList() getAlarmCount()
getLatestAlarmKind() getLatestAlarmMessage()
Alarm data for AlarmOverview & Dashboard