

CineShot Setup


Tutorial

From the first camera to the recorded trailer

CineShot Setup 1.0 · Unity 6 · Cinemachine 3

Contents

- 1 Set the first camera**
Workflow
- 2 CAMERAS card**
Reference
- 3 Shape the move with sliders**
Workflow
- 4 CONTROLS card**
Reference
- 5 Add a second key, add some shake**
Workflow
- 6 TIMELINE card**
Reference
- 7 Dolly zoom, and the transition types**
Workflow
- 8 Chain cameras into a trailer**
Workflow
- 9 SEQUENCE and AUDIO cards**
Reference
- 10 Fine-tune a transition by dragging**
Workflow
- 11 Roll, and what the status light tells you**
Workflow
- 12 Bake, then record**
Workflow
- 13 Bake and Data bar**
Reference



Set the first camera

1

Frame your shot in the Scene View, then press Set Camera (1). The yellow Game-View frame (2) shows exactly what the camera sees. Pick the LookAt target from the list (3), or hover the object in the Scene View and click it. Skip = assign later, Cancel = delete the camera.

CAMERAS card

Everything about creating cameras and what the Scene View shows you while you work.

1 Set Camera

Creates a CinemachineCamera at the current Scene-View position and opens the target list. Every camera you make this way gets its own moves and its own timeline.

2 Decouple / Couple

Decouple frees the Scene View from the camera so you can fly around and inspect the shot. Couple locks it back onto the camera. The button label switches between the two states.

3 Show Game-Frame in Scene


Draws the steady yellow frame with thirds grid and centre cross in the Scene View, matching the Game View's aspect and FOV. Also hides Cinemachine's own flickering frustum. Off = Cinemachine frustum back to normal.


4 Show Camera-Path in Scene

Draws the blue flight path of the selected camera with its key markers and the Start marker in the Scene View. Great for judging an orbit or crane before you play it.

5 Move SceneCamera too

The Scene View camera follows the preview while you drag sliders or scrub. Off = only the Game View moves, the Scene View stays where you left it.





Shape the move with sliders

3

Drag Orbit horizontal (1) and the camera swings around its target - the value field accepts typed numbers too. Duration (2) sets how long the move takes. The moment you touch a slider a Key1 appears in the timeline (3). Shift while dragging = 10x finer, Ctrl = 10x faster.

CONTROLS card


All sliders are relative: they move the live camera away from the start pose of the selected key. Zero = the pose you started from.

- 1 Keep View (selected key)**
Orbit, Orbit vertical and Crane keep your current framing instead of snapping onto the target. Tick it BEFORE picking a target: the pivot is then placed on your view axis at the object's depth, so the object sits dead centre and slider 0 shows exactly the view you had. Off = the pivot goes to the object's centre and the camera turns onto it the moment you pick. Keep View pivots are per camera (Cam1_Pivot, Cam2_Pivot ...).
- 2 Orbit horizontal / vertical (°)**
Circle around the target sideways or over the top. Range up to four full turns horizontally.
- 3 Pan side / up-down / forward-backward (m)**
Straight moves in camera space: truck left-right, pedestal up-down, dolly in-out. Metres, so 0.5 is half a metre.
- 4 Zoom FOV (°) / Dolly Zoom**
Zoom changes the field of view. Dolly Zoom moves the camera and counter-zooms at the same time - the vertigo effect: the subject stays the same size, the background stretches.
- 5 Crane (m)**
Lifts or lowers the camera while it keeps looking at the target - a jib arm.
- 6 Roll / Yaw / Tilt (°)**
Rotate the camera itself: roll = dutch angle, yaw = turn left-right, tilt = nod up-down. Yaw and tilt break the target lock, use them for free looks.
- 7 Duration (s)**
How long this key plays. Also draggable directly at the right edge of the key bar in the timeline.

CONTROLS

Adjust sliders to move the selected camera. Each camera remembers its own values.

1	☐ Keep View (selected key)	
2	Orbit horizontal (°)	310.6
	Orbit vertical (°)	0
	Pan side (m)	0
3	Pan up/down (m)	0
	Pan forward/backward (m)	0
	Zoom FOV (°)	0
4	Dolly Zoom	0
	Crane (m)	0
5	Roll (°)	0
	Yaw (°)	0
6	Tilt (°)	0
	Duration (s)	3
7		



5


Add a second key, add some shake


Press + Add Key (5) after the orbit: the sliders reset to zero and Key2 (2) continues from where Key1 ended. Now drag Crane (1) - the green Crane bar (3) shows which channel moves. Shake/Noise (4) adds handheld wobble to the selected key. Play All / Play Current (6) previews it.

TIMELINE card

The timeline is where you shape timing. Click a key bar to select it, Shift-click for a range.

- 1 Key Reverse**
Plays the selected key backwards: from its end pose back to its start pose, easing mirrored. Following keys continue from the start pose.
- 2 Key bars**
One bar per key, width = duration. Drag the RIGHT EDGE of the selected bar to change its duration. Drag a bar sideways to reorder keys. Del removes the selected key(s).
- 3 Ease buttons + flags**
The two vertical buttons (Smooth) cycle the ease-in and ease-out mode: Smooth > Linear > Slow > Fast. The small triangles on top are the ease flags: drag them to set how long the ease-in / ease-out phase lasts. Slow = long soft start, Fast = snappy start.
- 4 Channel bars + eye**
One coloured bar per active channel (Orbit, Crane ...). The eye at its right end mutes the channel: the value is kept, the channel just stops moving the camera. Click again to unmute.
- 5 Scrub slider**
Drag to scrub through the selected key(s). The Game View follows.
- 6 Shake/Noise (selected Key)**
Handheld noise on top of this key. Strength = amplitude, Speed = frequency. Window: Full Length = across the whole key. Start / End = a short wobble of the given length centred on the key boundary, half of it bleeding into the neighbour for a smooth hand-over. Preview (GameView) plays the shake in place.
- 7 + Add Key**
Snapshots the current slider pose as a new key and resets the sliders to zero. The next move continues from here.
- 8 Stop / Play All / Play Current / Loop**
Play All runs the whole camera timeline, Play Current only the selected key. Loop repeats. Both also work in Play Mode, so particles and VFX simulate.
- 9 Reset Key / Reset selected Keys**
Resets the TIMING of a key (ease curves and modes), motion values and duration stay. The plural version does it for all Shift-selected keys in one undo step.
- 10 Delete Key / Delete all Keys**
Removes the selected key, or all keys of this camera. Both undoable with Ctrl+Z.





7

Dolly zoom, and the transition types

Cam2 uses Pan forward + Dolly Zoom (1): the camera drives in while the FOV opens, so the frame (2) shrinks but the subject keeps its size - the vertigo shot. On the right: the '+' on a selected shot opens the transition menu (3): Linear, Ease In, Ease Out, Ease In-Out or Fade Black.

Unity 6 | W | Asset Store | AI | Unity VCS | Play | Pause | Stop

Hierarchy | Scene | Game | Package Manager | Asset Store Validator | Asset Store Uploader | Recorder | MCP For Unity

Inspector | CineShot Setup

6

Game-View

1

2

3

4

5

Project | Console

Assets > CineShot Setup

Bake FPS: 120 FPS

Output: Assets/CineShot Setup/Animations

Data: Export... Import...

Step 1 - bake the trailer (activates the trailer camera)

Bake Trailer Animation (3 Cams) Status: ●

Step 2 - open the Recorder, set output, then press Record

Open Recorder

Trailer: 13,30 s · 1596 frames @ 120 FPS

CineShot Setup v1.0

[CineShot] Pivot 'Cam3_Pivot' created at (4.50, 1.26, 3.01) (child of 'Prop_Pillar'), set as LookAt + Tracking target.

Chain cameras into a trailer

8

Select the cameras in the Hierarchy (6) and press + Add selected cameras (2): each becomes a shot in the strip (1). Click a shot to load its keys, drag it sideways to reorder. The small orange key between Cam1 and Cam2 is a transition, its settings open below (4). Drop a music clip into AUDIO (5), then Play Sequence (3).

SEQUENCE and AUDIO cards

The trailer is a chain of shots. Every shot plays that camera's whole timeline, transitions sit between them.

- 1 Sequence strip**
Click a shot to select it (its keys load in the TIMELINE card and the time slider jumps to its start). Drag sideways to reorder. The '+' on the selected shot inserts a transition to the next one. Del / Backspace removes the selected shot or transition.
- 2 + Add selected cameras / Delete All**
Adds every camera selected in the Hierarchy as a shot at the end. Delete All empties the whole sequence (undoable).
- 3 Stop / Play Sequence / Play selected Cam / Loop**
Play Sequence runs the whole trailer with transitions and music. Play selected Cam plays only the selected camera's timeline, handy for comparing one shot against the whole cut. Both work in Play Mode.
- 4 Time slider**
Scrubs through the trailer. Follows during playback. Clicking a shot moves it to that shot's start.
- 5 Transition box**
Opens when you click a transition key. Type: Linear, Ease In, Ease Out, Ease In-Out, Fade Black. Duration by dragging the key sideways in 0.1 s steps. Preview (GameView) plays just this transition.
- 6 Shake/Noise (transition)**
Impact shake anchored at the cut: Start (at the cut) hits right when the new shot begins, End (transition done) hits after the blend has settled. Strength, Speed and Duration as in the timeline shake.
- 7 Music clip**
Drop an AudioClip here. It plays along with Play All and Play Sequence and ends up in the recording if your Recorder preset captures audio.
- 8 Waveform**
Drag the waveform left or right to shift where the music starts. The yellow line is the current playhead. Times below show clip position and length.

SEQUENCE (TRAILER)

Chain cameras into a trailer. Click a camera key to select it, drag it sideways to reorder, use the '+' for a transition. Del removes the selected key.

1

Cam1

2

Cam2

3

Cam3

2

+ Add selected cameras

Delete All

3

Stop

Play Sequence

Play selected Cam

Loop

4

3 shots · 13,30s

5

Transition: CinemachineCamera_1 → CinemachineCamera_2 · 1,0s

Ease In

Preview (GameView)

☒ Shake/Noise

End (transition done)

Strength

0.4

Speed

8

Duration (s)

0.3

6

AUDIO

Drop a music clip. Drag the waveform to shift the music. Plays with Play / Play Sequence.

7

Music clip

epic-cinematic-trailer-427977


8

0:00 / 1:04

Reference

9


SEQUENCE and AUDIO cards



10

Fine-tune a transition by dragging


Grab the orange transition key (1) and drag it sideways: its length changes in 0.1 s steps and the yellow label shows the value, here 2.9 s. Hover the strip for the built-in cheat sheet (2): click to select, drag to reorder, '+' adds a transition, Del removes.



11

Roll, and what the status light tells you

Roll (1) tilts the horizon - a dutch angle. Note the status light (2): it turned yellow because the trailer was baked earlier and you changed a key since. Red = not baked (or the baked files were deleted), yellow = changed since the bake, green = up to date. Bake again before recording.



Bake, then record

12

Bake Trailer Animation (1) writes the whole trailer onto a generated CineShot Trailer Camera (5) as an AnimationClip. Status turns green (2). Open Recorder (3) activates that camera and opens Unity's Recorder (4): set format, resolution and output, then Start Recording. Bake info (6) tells you the exact frame count.

Bake and Data bar

The bar at the bottom is always visible. It turns your moves into files and hands over to the Recorder.

- 1 Bake FPS**
Sample density of the generated AnimationClip: keyframes per second. 60 is enough for most moves, 120 for very fast ones, Custom = your own value.
- 2 Output**
Folder for the generated .anim and .controller files. Click to pick one inside Assets. Created automatically if missing, overwritten by the next bake.
- 3 Data: Export / Import**
Export saves ALL camera moves and the sequence as JSON: backups, version control, sharing. Import loads such a file and merges by camera - existing cameras get their data replaced, others keep theirs. Your working data lives in UserSettings/CineShotData.json.
- 4 Bake Camera / Trailer Animation + Status**
With a sequence the button bakes the trailer onto the CineShot Trailer Camera, without one it bakes the selected camera. Status: red = not baked or baked result deleted, yellow = changed since bake, green = up to date.
- 5 Open Recorder**
Makes the camera you are about to record the live one, then opens Unity's Recorder window. Your Recorder settings are never touched. Optional package - without it the button is disabled.
- 6 Bake info**
Exact clip length and frame count - the number the Recorder's end frame wants.

1 | Bake FPS 120 FPS

2 | Output Assets/CineShot Setup/Animations

3 | Data

Export...

Import...

Step 1 · bake the trailer (activates the trailer camera)

4 |

Bake Trailer Animation (3 Cams)

 Status:

Step 2 · open the Recorder, set output, then press Record

5 |

Open Recorder

6 |

Trailer: 13,30 s · 1596 frames @ 120 FPS

CineShot Setup v1.0

Reference