## **Termux-services**

From Termux Wiki

Jump to: navigation, search

termux-services 
contains a set of scripts for controlling services. Instead of putting commands in ~/.bashrc or ~/.bash\_profile, they can be started and stopped with termux-services.

Only a few packages so far contain the necessary service scripts, these are:

- mpd 🗗
- tor
- transmission
- sshd 🗗
- ftpd 🗗
- telnetd
- emacsd

To install termux-services, run

```
pkg install termux-services
```

and then restart termux so that the service-daemon is started.

To then enable and run a service, run

```
sv-enable <service>
```

If you only want to run it once, run

```
sv up <service>
```

To later stop a service, run:

```
sv down <service>
```

Or to disable it

```
sv-disable <service>
```

A service is disabled if `\$PREFIX/var/service/<service>/down` exists, so the `sv-enable` and `sv-disable` scripts touches, or removes, this file.

termux-services uses the programs from runit 

to control the services. A bunch of example scripts are available from the same site 

If you find a script you want to use, or if you write your own, you can use set it up by running:

```
mkdir -p $PREFIX/var/service/<PKG>/log
ln -sf $PREFIX/share/termux-services/svlogger $PREFIX/var/service/<PKG>/log/r
un
```

and then put your run script for the package at \$PREFIX/var/service/<PKG>/run and make sure that it is runnable.

You can then run

```
sv up <PKG>
```

to start it.

Log files for services are situated in \$PREFIX/var/log/sv/<PKG>/ with the active log file named "current".

## Starting termux-services on boot

If you want your services to start on device boot, see the example in <a href="Termux:Boot">Termux:Boot</a>