CUBEROOT · GOLF TOGETHER

# The Marker Complete Illustrated User Guide

Your hole-by-hole golf companion.
With The Scorecard, or on its own.

Keep scores for one to four players. Score yourself or let a caddie enter scores from another phone. Sign in to post eligible rounds to The Scorecard, or play without an account and keep and share your card.

Instructions updated 29 October 2026: Caddie (0.7.1) and Follower (0.8.1) · Large-print edition. New Caddie and Follower screens use current version 0.8.3 source; earlier scoring screens are from 0.6.4.

**Open The Marker →**

> The illustrations below use The Marker's actual screen markup and stylesheet, with fictional example names and scores. They are read-only examples, not screenshots from a personal account. Use the View this screen larger link for an expanded view.

1. Choose how to play
2. Sign in and recover access
3. Set up the round
4. Choose the round date
5. Find and check a course
6. Enter a course yourself
7. Read the club card from a photo
8. Confirm the photo reading
9. Choose one to four players
10. Attach an available game
11. Enter scores, one golfer at a time
12. Enter all players together
13. Fix scores before posting
14. Understand the totals
15. Post eligible rounds to Scorecard
16. Confirm the posting result
17. Correct a posted card
18. Re-post after rounds were deleted
19. Share a card
20. Resume, keep and delete cards

## 21. When something goes wrong


## 22. The Menu bubble during play

## 23. Let a caddie score

## 24. Follow a card live

# 1. Choose how to play

The Marker is a companion to The Scorecard and a complete standalone scorecard for one to four players.





Source-matched illustration with fictional example data. **View this screen larger**.

# 1. Choose how to play: steps

1. Choose **Sign in with The Scorecard** to use your existing account and pick golfers from your groups. Eligible finished rounds can be posted for those golfers.
2. Choose **Play without an account** to type player names, keep the card on this device and share it. No Scorecard account is required.
3. **Continue your round** appears when a round is already saved. A saved correction or re-post instead shows **Continue your correction** or **Continue your re-post**. Open the web app while connected before leaving for the course.

# 2. Sign in and recover access

Use the same email address and password as The Scorecard.





Source-matched illustration with fictional example data. **View this screen larger**.

# 2. Sign in and recover access: steps

1. Enter your Scorecard email and password, then tap **Sign in**. On the start screen, tap **Start a new round**.
2. For a forgotten password, enter your email and tap **Forgot the password? Send a reset email**. Follow the email to reset your shared Scorecard password.
3. Signing in needs an internet connection. If you have no account, return and choose **Play without an account**. Account and group setup are handled in The Scorecard.

# 3. Set up the round

Check these choices before you tee off.





Source-matched illustration with fictional example data. **View this screen larger**.

# 3. Set up the round: steps

1. Tap the date to open the calendar. Select the month, year and day played, or type the date as year, month, day. Future dates are blocked. Choose the course and the tee actually used.
2. Choose **18 holes**, **Front 9** or **Back 9**. A nine-hole card can be shared but cannot be posted to The Scorecard.
3. Set the **Starting hole** for a shotgun start. An 18-hole round starting on 10 goes through 18, then 1 through 9.
4. Choose your score-entry layout. The selected course and tee apply to everyone on this card; use separate cards for different tees.

# 4. Choose the round date

Use the app’s calendar to select a past date or today.





Current app screen with fictional data. **View this screen larger**.

# 4. Choose the round date: steps

1. Tap the date in **Set up the round** to open the calendar. Use the arrows for the previous or next month. Tap the month name or year to choose it directly.
2. Tap the day you played. The calendar closes with that date selected. Future days cannot be selected.
3. For another date, use **Or type it**: enter year, month, day, for example **2025 05 18** or **20250518**, then tap **Use what I typed**. Invalid or future dates show an error.
4. **Today** selects today. **Use this date** closes the calendar keeping the selected date. Changing the date clears the chosen game; check **Part of a game** again.

# 5. Find and check a course

Check the course data against the club’s current scorecard.




Source-matched illustration with fictional example data. **View this screen larger**.

# 5. Find and check a course: steps

1. Tap **Choose a course**. Enter a name and choose **Show saved** or **Search online**. Select the right club and tee.
2. Back in setup, tap **Check the holes (par, yards, handicap)** when available. Compare the hole details with the club’s card.
3. If details are missing or wrong, use the correction option or **Enter a course yourself**. Online search needs a connection; previously saved courses are available locally.
4. Withdrawn course details cannot be used. Follow the message to find corrected data or enter the current club card. Shared course administration belongs in The Scorecard. If a locally saved course has a **Delete** button, it removes that course from this device only, after confirmation. Shared-library entries do not show this button.

# 6. Enter a course yourself

Manual entry is available even when you cannot read a photo.




Source-matched illustration with fictional example data. **View this screen larger**.

# 6. Enter a course yourself: steps

1. Choose **Enter a course yourself**. Type the course name and tee. Copy rating and slope from the club card if you intend to post.
2. Check every hole’s par: the form starts with par 4, so change it where needed. Yards are optional.
3. Enter each HCP / Handicap / S.I. number exactly as printed. Use each number from 1 to 18 once, or leave all blank. Missing HCP makes stroke allocation approximate.
4. Tap **Use this course**. Manually entered data can be used for eligible Scorecard rounds; a photo or provider verification is not required.

# 7. Read the club card from a photo

This reads course details, not the players’ handwritten scores.





Source-matched illustration with fictional example data. **View this screen larger**.

# 7. Read the club card from a photo: steps

1. Open **Enter a course yourself**. Type the course name and use a photo button. Lay the club card flat in good light.
2. Include all 18 holes, every tee, ratings, slopes, par, handicap numbers and printed totals. Avoid glare and cut-off edges.
3. Wait for the reading spinner. If asked, take a closer picture of the missing or unclear half.
4. Photo reading needs internet and an available daily allowance. Check the displayed pictures-left message. If unavailable, enter the details by hand.

# 8. Confirm the photo reading

A green check means the app’s checks passed. You must still compare the values with the printed card.





Source-matched illustration with fictional example data. **View this screen larger**.

# 8. Confirm the photo reading: steps

1. Review both nines and **every tee**, not just the tee you will play. Check rating, slope, yards, par, handicap numbers and totals.
2. Red marks indicate missing or problematic values. Retake the requested part, or choose **Correct it by hand instead** and select a tee.
3. Read any warning about the printed card’s own totals. Confirm only when the displayed data matches the card.
4. Tap **This matches the card** when available. Signed-in, verified data becomes shared course data; without an account it is saved on this device. Then choose your tee.

# 9. Choose one to four players

Group golfers can be posted; typed guests are scored and shared only.





Source-matched illustration with fictional example data. **View this screen larger**.

# 9. Choose one to four players: steps

1. Tap **Choose the players**. Signed-in users select a group and tap existing golfers. You may select golfers from your own groups, up to four total.
2. Add other people by typing a name and tapping **Add**. Without an account, enter each player this way. Typed names are guests, even if they resemble a member’s name.
3. Tap a selected member again to deselect; use **Remove** for a typed player. Check the names, then tap **Tee off on hole …**.

# 10. Attach an available game

Game selection is optional and appears during setup for signed-in users when games are available.





Source-matched illustration with fictional example data. **View this screen larger**.

# 10. Attach an available game: steps

1. Set the correct date first. Under **Part of a game**, choose the appropriate listed game or leave **Not part of a game** selected.
2. Only available games covering that date are listed. Group access affects which games you can see.
3. For a card containing golfers from different groups, the game attaches only to rounds in the game’s group. Create and manage games in The Scorecard.

# 11. Enter scores, one golfer at a time

Enter the strokes actually taken. The app calculates its handicap adjustment separately.





Source-matched illustration with fictional example data. **View this screen larger**.

# 11. Enter scores, one golfer at a time: steps

1. Tap the golfer’s name, then tap their score tile. The entered value is highlighted. Tap another value to correct it.
2. Tap the next golfer’s name and enter that score. Use **Type a score** for a whole number from 1 to 20.
3. Use **Picked up** when the player did not finish the hole. This records X; it is not a zero.
4. When everyone has an entry, tap the next-hole button. After the final hole, tap **Finish**. Watch for save errors before continuing.

# 12. Enter all players together

Switch layouts at any time without losing scores.





Source-matched illustration with fictional example data. **View this screen larger**.

# 12. Enter all players together: steps

1. Choose **All four together** in setup, or use **Menu** to switch during play. It also works with fewer than four players.
2. Tap **+** on an empty score to start at par. Then use minus or plus, or tap the score field and type a whole number from 1 to 20.
3. Type **X** for picked up. If your keyboard does not offer X, switch to one-golfer mode and tap **Picked up**.
4. Enter a score for everyone, then advance. Blank fields remain unfinished; they do not count as par.

# 13. Fix scores before posting

Return to the totals directly after changing a hole.





Current app screen with fictional data. **View this screen larger**.

# 13. Fix scores before posting: steps

1. On **Round finished**, tap **Fix a score**, or open **Review card**. Tap the row for the hole you want to change.
2. Choose the golfer and change their score in either scoring layout. Tap **Done fixing — back to the totals** when the card is complete.
3. Check the totals again, then post eligible rounds or keep/share the card. You no longer need to walk through the remaining holes after fixing a completed card.

# 14. Understand the totals

Illustrative 18-hole example: gross 90, adjusted 88 and course handicap 10.





Source-matched illustration with fictional example data. **View this screen larger**.

# 14. Understand the totals: steps

1. **Gross** adds entered strokes. For an X, the app substitutes that hole’s handicap limit, so it is not a count of strokes actually finished on that hole.
2. **Adjusted** caps high hole scores at the app’s handicap limit: normally par + 2 + strokes received. With no known course handicap, the app uses par + 5.
3. **Net** is gross minus course handicap when the round is complete and a handicap is available. Do not use a nine-hole net display as a posted 18-hole result.
4. **E** means even with par. + and − show over and under par. Stroke notes depend on the selected tee, the player’s index and hole handicap data.

# 15. Post eligible rounds to Scorecard

Posting and sharing are different actions.





Source-matched illustration with fictional example data. **View this screen larger**.

# 15. Post eligible rounds to Scorecard: steps

1. Check all totals. Tap **Post … rounds to The Scorecard** when shown. The number counts eligible group golfers, not guests.
2. Posting requires a signed-in card, at least one selected group golfer, 18 holes, rating and slope, and a score on every required hole. The server checks the submission too.
3. Nine-hole cards, standalone cards and typed guests are kept and shared instead. Read the reason if no Post button is available.
4. A standalone card does not become postable just by signing in later. Start in signed-in mode and select the actual group golfers when posting is your goal.

# 16. Confirm the posting result

Do not treat Waiting or Checking as a successful post.





Source-matched illustration with fictional example data. **View this screen larger**.

# 16. Confirm the posting result: steps

1. **Waiting** means the card is saved locally for sending. Reopen The Marker on the same browser, sign in to the original account if needed and leave it open with a connection.
2. **Checking** means the submission reached the service and is being processed. Allow a few minutes and check again.
3. **Posted** ✓ confirms acceptance. Open The Scorecard to verify the rounds. The service recalculates the posting data, so its final values are authoritative.
4. For **Not posted**, read the reason and keep or share the card. Do not re-enter the same rounds while the original submission is still waiting or being checked.

# 17. Correct a posted card

The Marker can now correct hole scores on an eligible posted card. A connection is required.





Current app screen with fictional data. **View this screen larger**.

# 17. Correct a posted card: steps

1. Sign in and open **Your cards → Correct a posted card**, then select a card. You can also open a posted card saved on this device and tap **Correct this card**. Finish or end another active round first.
2. The original scorer can correct the card for **24 hours after posting**. An owner or admin of **every group represented on the card** can correct it at any time. The service checks your access.
3. Tap **Fix a score**, tap the hole’s row, choose the golfer and change the strokes. Tap **Done fixing — back to the totals** to return directly. Repeat for other errors.
4. Review the totals and tap **Save the correction**. Wait for **Corrected in The Scorecard**. The affected rounds and handicap indexes are updated together. If no score changed, the app says nothing was saved.
5. A correction changes hole scores only. It keeps the original players, date, course, tee and game. If someone has changed a round directly in Scorecard, read the refusal and ask an owner/admin to resolve it there.
6. **Cancel the correction** discards the current correction after confirmation. Menu offers the same cancel action while correcting. If the connection fails, keep the screen and try again online.

# 18. Re-post after rounds were deleted

Use Re-post only for the cards the app identifies under Deleted in The Scorecard.





Current app screen with fictional data. **View this screen larger**.

# 18. Re-post after rounds were deleted: steps

1. Open **Your cards**. Under **Deleted in The Scorecard**, the app names the golfers whose rounds were deleted. Tap **Re-post**. Opening a saved original card may instead offer **Edit and re-post**.
2. The scorer, or an owner/admin of every group on the original card, may re-post. Finish or end another active round first. Only golfers with deleted rounds are put on the new card; surviving rounds are kept.
3. Use **Fix a score**, select the hole, change the strokes, then tap **Done fixing — back to the totals**. Check the date, golfers and totals shown.
4. Tap **Post … rounds to The Scorecard**. This creates a new card for the deleted rounds. Wait for **Posted ✓**. Once accepted, the new card replaces the original copy in this device’s card history.
5. **Hide** takes the deleted-round reminder off that list after confirmation; it changes no Scorecard round. If the original card remains on this device, opening it still offers **Edit and re-post**.
6. **Cancel the re-post** discards the current re-post without sending it. If the service says a round still exists or the card was already re-posted, check the current records before proceeding.

# 19. Share a card

Share during play, after finishing or from Your cards.





Source-matched illustration with fictional example data. **View this screen larger**.

# 19. Share a card: steps

1. Tap **Share the card**. Your device may show its native share sheet; otherwise choose WhatsApp, Email, Text message or Copy.
2. Choose the recipients in your messaging app and send when ready. Sharing sends a text summary with hole scores; it does not post rounds to The Scorecard.
3. If Copy is blocked, press and hold the displayed text and copy it manually. An unfinished card can also be shared; missing holes appear as dashes.

# 20. Resume, keep and delete cards

Local cards belong to this device and browser.





Source-matched illustration with fictional example data. **View this screen larger**.

# 20. Resume, keep and delete cards: steps

1. Return to the start screen through **Menu**. Use **Continue your round** to resume. To stop permanently without posting, choose **End this round without posting** and confirm.
2. **Your cards** shows cards saved on this device (up to 30), and signed-in users can also see eligible cards whose rounds were deleted in Scorecard. Open a local card to view, share or use its available correction action.
3. **Delete this card** is available only when allowed. Deletion is permanent; posted cards and cards being checked cannot be deleted here.
4. Clearing browser data or changing devices does not carry local cards across. Share important cards before clearing data or exceeding the history limit.

# 21. When something goes wrong

Keep the card and resolve the displayed message first.





Source-matched illustration with fictional example data. **View this screen larger**.

# 21. When something goes wrong: steps

1. **No signal:** a loaded round can save scores locally. Search, sign-in, photo reading and posting need internet. This web release does not guarantee a fresh offline launch; keep the loaded page available.
2. **Save error:** do not assume the latest score was kept. Check browser storage, avoid private browsing and retry. Share a copy before clearing anything.
3. **Missing golfer:** check the group and connection. A typed guest cannot be posted as that group golfer. Manage membership in The Scorecard.
4. **Photo or posting problem:** read the message, use manual course entry when needed, and check posting status online. For help, use Support on the app’s start screen.

# 22. The Menu bubble during play

The **Menu** control appears at the top of the hole screen beside the saved indicator. Tap it without leaving your round.





Source-matched illustration with fictional example data. **View this screen larger**.

# 22. The Menu bubble during play: steps

1. Tap **Menu** at the top right while entering scores.
2. Choose **Switch** to change the score-entry view. Your entered scores stay saved.
3. **See the whole card** lets you review holes; **Share the card** sends a score summary. **Let others follow this card** shows a code and QR link for live, read-only viewing.
4. **Go to the start screen** keeps the active round for **Continue your round**. **End this round without posting** is different: it ends the round and keeps a historical card without posting.
5. While correcting a posted card, **Cancel the correction** replaces End this round without posting. It abandons the correction after confirmation. Tap **Back to hole** to return to scoring.

# 23. Let a caddie score on a second phone

The caddie enters scores for the golfer but cannot post rounds, access Scorecard groups, or view the account's personal information. The member who owns the card reviews it and is responsible for posting.




Screen rendered from The Marker 0.8.3 source code using fictional names and scores; the illustrated code cannot be used to join a real card. **View this screen larger**.

## 23A. Start the caddie card

1. **Member:** Sign in using the Scorecard account. Choose the round date, course, tee, players and score-entry layout.
2. On the player selection screen, tap **Let my caddie score**. The golfer's phone creates a unique six-character code and displays a QR square. Starting the session requires internet access.
3. Ask the caddie to open The Marker and tap **Caddie** at the bottom of the start screen, without signing in. Type the code and tap **Join the card**.
4. Alternatively, scan the QR square with the caddie's phone camera. The link opens The Marker on a compatible installed iPhone or Android app, or the web

app otherwise. The code is already in the Join field; tap **Join the card**.

**The Marker: Caddie Join screen with large code input and Join the card button**

Screen rendered from The Marker 0.8.3 source code using fictional names and scores; the illustrated code cannot be used to join a real card. **View this screen larger**.

## 23B. Score the round

1. The caddie sees only the information needed for scoring: the course, tee, holes, player names and course handicaps. The caddie can score one player at a time or all players together, and correct scores.
2. As the caddie records scores, they are sent to the golfer's phone. The golfer's screen shows **Your caddie is scoring**, the card, and when it last received a score. Updates appear every few seconds while the screen is open.
3. The golfer can put the phone away and return through **Continue your round**. If the golfer wants to score personally, select **Take over scoring myself**. The scores already transmitted remain. A connection is required so the caddie's access can be stopped first.
4. One caddie can be active on each card. Codes stop working after the card is finished or taken over, or at most 12 hours after creation.




Screen rendered from The Marker 0.8.3 source code using fictional names and scores; the illustrated code cannot be used to join a real card. **View this screen larger**.

## 23C. Finish and hand back

1. On the caddie's phone, complete the final hole and tap **Finish**. Review or fix the scores, then tap **Hand the card back to the golfer**.
2. The golfer receives the finished card, reviews every hole, fixes any mistakes, and uses the usual **Post … rounds to The Scorecard** option for eligible 18-hole member rounds. Guest and nine-hole cards cannot be posted.
3. The caddie cannot post to The Scorecard and cannot reuse the code after hand-back.

## 23D. Connection problems

1. If connectivity drops, the caddie's entered scores remain on that phone. The app retries sending them when a signal returns.
2. If hand-back says **Not sent yet: no signal**, keep The Marker open on the caddie's phone until sending succeeds. The golfer must check that the latest scores actually arrived before posting.
3. Do not clear browser or app storage while unsent scores remain. If the golfer takes over, use a working

connection so the app can stop the caddie first and preserve transmitted scores.

> **Illustration note:** All three Caddie illustrations above use actual Marker 0.8.3 screen functions with fictional data. Score entry uses the same illustrated scoring controls shown earlier in this guide.

# 24. Follow a scorecard live

Follower is a read-only view designed for other golfers on the card who want to watch the score develop on their own phones. The owner still enters or delegates scores, checks the card, and posts eligible rounds to The Scorecard.




Screen rendered from The Marker 0.8.3 source code using fictional names and scores; the illustrated code cannot be used to join a real card. **View this screen larger**.

## 24A. The owner starts following

1. Sign in with The Scorecard, start the round, and enter scores normally—or use **Let my caddie score** to delegate scoring to a caddie.
2. During your own scoring, tap **Menu → Let others follow this card**. When a caddie is scoring, tap **Let others follow this card** on **Your caddie is scoring**.
3. The Marker shows a six-character follow code and a QR square. To see it again, choose **Show the follow code**.
4. Give the code or QR square to golfers who should be able to view the scorecard. A follow code is separate from the caddie's scoring code.




Screen rendered from The Marker 0.8.3 source code using fictional names and scores; the illustrated code cannot be used to join a real card. **View this screen larger**.

## 24B. A golfer joins as a Follower

1. On another phone, open The Marker. Tap **Follow** at the bottom of the start screen.
2. Type the six-character code in **Follow code**, then tap **Follow the card**. No Scorecard account is needed.
3. Or scan the QR square using the phone's camera. The link uses the Cuberoot follow page and opens The Marker in a supported installed iPhone or Android app, or the web app otherwise. The code is supplied through the link.
4. The **Following** screen shows the course, tee, golfer names, hole scores, and scorecard as the round progresses. Scores refresh automatically about every 12 seconds while this screen is open.




Screen rendered from The Marker 0.8.3 source code using fictional names and scores; the illustrated code cannot be used to join a real card. **View this screen larger**.

## 24C. While following

1. The Follower cannot change, correct, delete or post any scores. Only the golfer or their caddie enters scores; the golfer remains responsible for the final review and posting.
2. The Follower sees whichever scores the owner or caddie sends. When a caddie is scoring, the Follower can still watch the same live card.
3. If the signal drops, the screen warns that it is showing older scores. Wait for the connection to return; do not mistake a stale scorecard for the latest card.
4. The start screen may offer **Follow: [course name]** so the Follower can reopen the card. To leave, tap **Stop following**.
5. Once the round finishes, the Follower can still see the completed card until the code expires. All follow codes stop working after at most **12 hours**.

## 24D. Privacy and limitations

1. **Anyone with the follow code can view the card**, even if they are not a golfer listed on it. The feature is designed for the playing group, but it does not enforce membership in that group. Share the code only with intended viewers.
2. Followers can view the shared scorecard; they cannot inspect the owner's Scorecard groups, change a card, or submit rounds.
3. Live updates require an internet connection on the scoring phone and the Follower's phone. The view

refreshes while open, not by push notification.

> **Illustration note:** All three Follower illustrations above use actual Marker 0.8.3 screen functions with fictional data. The codes shown are examples only and have no access to a real card.