CUBEROOT · GOLF TOGETHER

The Marker Complete Illustrated User Guide

Your hole-by-hole golf companion.
With The Scorecard, or on its own.

Keep scores for one to four players. Sign in to post eligible rounds to The Scorecard, or play without an account and keep and share your card.

Web app version 0.5.4 · 17 October 2026 · Large-print edition

Open The Marker →

> The illustrations below use The Marker's actual screen markup and stylesheet, with fictional example names and scores. They are read-only examples, not screenshots from a personal account. Use the View this screen larger link for an expanded view.

1. Choose how to play 2. Sign in and recover access 3. Set up the round 4. Find and check a course 5. Enter a course yourself 6. Read the club card from a photo 7. Confirm the photo reading 8. Choose one to four players 9. Attach an available game 10. Enter scores, one golfer at a time 11. Enter all players together 12. Review and correct before posting 13. Understand the totals 14. Post eligible rounds to Scorecard 15. Confirm the posting result 16. Share a card 17. Resume, keep and delete cards 18. When something goes wrong 19. The Menu bubble

1. Choose how to play

The Marker is a companion to The Scorecard and a complete standalone scorecard for one to four players.

HOLE-BY-HOLE SCORECARD

The Marker

Sign in with The Scorecard

Pick golfers from your groups. Scores are posted for them.

Play without an account

Type the players' names. Keep and share the card; nothing is posted.

Every score is saved on this phone the moment you enter it, so a lost signal or a flat battery loses nothing.



Source-matched illustration with fictional example data. **View this screen larger**.

1. Choose **Sign in with The Scorecard** to use your existing account and pick golfers from your groups. Eligible finished rounds can be posted for those golfers.
2. Choose **Play without an account** to type player names, keep the card on this device and share it. No Scorecard account is required.
3. **Continue your round** appears when a round is already saved. Open the web app while connected before leaving for the course.

2. Sign in and recover access

Use the same email address and password as The Scorecard.

WITH YOUR SCORECARD ACCOUNT

Sign in

Use the same email and password as The Scorecard.

EMAIL


Email address

PASSWORD

••••••••••••

Sign in

Forgot the password? Send a reset email



Source-matched illustration with fictional example data. **View this screen larger**.

1. Enter your Scorecard email and password, then tap **Sign in**. On the start screen, tap **Start a new round**.
2. For a forgotten password, enter your email and tap **Forgot the password? Send a reset email**. Follow the email to reset your shared Scorecard password.
3. Signing in needs an internet connection. If you have no account, return and choose **Play without an account**. Account and group setup are handled in The Scorecard.

3. Set up the round

Check these choices before you tee off.

PLAYING WITHOUT AN ACCOUNT

Set up the round

DATE

− 17 Oct 2026 +

COURSE

Sample Links Golf Club ▸

TEE

✓ **White**
70.1 / 125 · par 72


Blue
72.2 / 130 · par 72

Check the holes (par, yards, handicap)

HOLES

18 holes | Front 9 | Back 9

STARTING HOLE



Source-matched illustration with fictional example data. **View this screen larger**.

1. Use the date minus and plus buttons to select the day played. Choose the course and the tee actually used.
2. Choose **18 holes**, **Front 9** or **Back 9**. A nine-hole card can be shared but cannot be posted to The Scorecard.
3. Set the **Starting hole** for a shotgun start. An 18-hole round starting on 10 goes through 18, then 1 through 9.
4. Choose your score-entry layout. The selected course and tee apply to everyone on this card; use separate cards for different tees.

4. Find and check a course

Check the course data against the club’s current scorecard.

SAVED COURSES, OR SEARCH

Choose a course

COURSE OR CLUB NAME

Sample


Show saved

Search online

SAVED COURSES

- [ ] **Sample Links Golf Club**
  2 tees
- [ ] **River Bend Golf Course**
  1 tee

Enter a course yourself



Source-matched illustration with fictional example data. **View this screen larger**.

1. Tap **Choose a course**. Enter a name and choose **Show saved** or **Search online**. Select the right club and tee.
2. Back in setup, tap **Check the holes (par, yards, handicap)** when available. Compare the hole details with the club’s card.
3. If details are missing or wrong, use the correction option or **Enter a course yourself**. Online search needs a connection; previously saved courses are available locally.
4. Withdrawn course details cannot be used. Follow the message to find corrected data or enter the current club card. Course administration belongs in The Scorecard.

5. Enter a course yourself

Manual entry is available even when you cannot read a photo.

FROM THE SCORECARD AT THE CLUB

Enter a course

COURSE NAME

Sample Links Golf Club

TEE

White

RATING

70.1


SLOPE

125

Rating and slope are needed only to post rounds to The Scorecard.

EACH HOLE: PAR, YARDS AND HANDICAP NUMBER (HCP)

HOLE	PAR	YARDS	HCP
1	4	376	1
2	5	382	2



Source-matched illustration with fictional example data. **View this screen larger**.

1. Choose **Enter a course yourself**. Type the course name and tee. Copy rating and slope from the club card if you intend to post.
2. Check every hole’s par: the form starts with par 4, so change it where needed. Yards are optional.
3. Enter each HCP / Handicap / S.I. number exactly as printed. Use each number from 1 to 18 once, or leave all blank. Missing HCP makes stroke allocation approximate.
4. Tap **Use this course**. Manually entered data can be used for eligible Scorecard rounds; a photo or provider verification is not required.

6. Read the club card from a photo

This reads course details, not the players’ handwritten scores.

FROM THE SCORECARD AT THE CLUB

Enter a course

READ IT FROM A PICTURE OF THE CLUB'S SCORECARD

Take one picture of the whole card: all 18 holes and every tee. Lay it flat, in good light.

📷 Take a photo

🖼 Photos or Files

COURSE NAME

Sample Links Golf Club

TEE

White

RATING


70.1

SLOPE

125

Rating and slope are needed only to post rounds to The Scorecard.

EACH HOLE: PAR, YARDS AND HANDICAP NUMBER (HCP)



Source-matched illustration with fictional example data. **View this screen larger**.

1. Open **Enter a course yourself**. Type the course name and use a photo button. Lay the club card flat in good light.
2. Include all 18 holes, every tee, ratings, slopes, par, handicap numbers and printed totals. Avoid glare and cut-off edges.
3. Wait for the reading spinner. If asked, take a closer picture of the missing or unclear half.
4. Photo reading needs internet and an available daily allowance. Check the displayed pictures-left message. If unavailable, enter the details by hand.

7. Confirm the photo reading

A green check means the app’s checks passed. You must still compare the values with the printed card.

SAMPLE LINKS GOLF CLUB

Check against the card

✓ **Everything on the card was read, and it all adds up.**
2 tees, par 72. Compare it with the card one last time.

OUT · HOLES 1–9

TEE	1	2	3	4	5	6	7	8	9
White	4	5	3	4	4	5	3	4	4
Blue	4	5	3	4	4	5	3	4	4

IN · HOLES 10–18

The same check is performed for each tee and nine.

✓ This matches the card
Used on this phone. Sign in to share it with every scorer.



Source-matched illustration with fictional example data. **View this screen larger**.

1. Review both nines and **every tee**, not just the tee you will play. Check rating, slope, yards, par, handicap numbers and totals.
2. Red marks indicate missing or problematic values. Retake the requested part, or choose **Correct it by hand instead** and select a tee.
3. Read any warning about the printed card’s own totals. Confirm only when the displayed data matches the card.
4. Tap **This matches the card** when available. Signed-in, verified data becomes shared course data; without an account it is saved on this device. Then choose your tee.

8. Choose one to four players

Group golfers can be posted; typed guests are scored and shared only.

SAMPLE LINKS GOLF CLUB · WHITE 3 of 4

Who's playing?

GROUP


Weekend Golfers (2 chosen)

- [x] **Alex Green** Index 12.4
- [x] **Sam Reed** Index 18.1
- [ ] **Tina Brooks** Index 22.6
- [ ] **Jordan Lee** Index 9.8

Only golfers already in your groups can be posted. Anyone else: add them below as a guest.

GUESTS · SCORED AND SHARED, NOT POSTED

- [x] **Pat Morris** Guest — Remove



Source-matched illustration with fictional example data. **View this screen larger**.

1. Tap **Choose the players**. Signed-in users select a group and tap existing golfers. You may select golfers from your own groups, up to four total.
2. Add other people by typing a name and tapping **Add**. Without an account, enter each player this way. Typed names are guests, even if they resemble a member’s name.
3. Tap a selected member again to deselect; use **Remove** for a typed player. Check the names, then tap **Tee off on hole …**.

9. Attach an available game

Game selection is optional and appears during setup for signed-in users when games are available.

PLAYING WITHOUT AN ACCOUNT

Set up the round

DATE

− 17 Oct 2026 +

COURSE

Sample Links Golf Club ▸

TEE

✓ **White**
70.1 / 125 · par 72


Blue
72.2 / 130 · par 72

Check the holes (par, yards, handicap)

HOLES

18 holes | Front 9 | Back 9

STARTING HOLE



Source-matched illustration with fictional example data. **View this screen larger**.

1. Set the correct date first. Under **Part of a game**, choose the appropriate listed game or leave **Not part of a game** selected.
2. Only available games covering that date are listed. Group access affects which games you can see.
3. For a card containing golfers from different groups, the game attaches only to rounds in the game’s group. Create and manage games in The Scorecard.

10. Enter scores, one golfer at a time

Enter the strokes actually taken. The app calculates its handicap adjustment separately.

SAMPLE LINKS GOLF CLUB · WHITE · HOLE 1 OF 18

✓ Saved Menu

Hole 1 Par 4

384 yards Handicap 11

Alex 4 | Sam 5 | Pat


Golfer 1 of 3

Alex Green

Gets 1 stroke here · handicap limit 6

Entered: 4. Tap another number to change it, or tap the next name above.

2 Eagle	3 Birdie	4 ✓ Entered
5 Bogey	6 Double	7 Triple



Source-matched illustration with fictional example data. **View this screen larger**.

1. Tap the golfer’s name, then tap their score tile. The entered value is highlighted. Tap another value to correct it.
2. Tap the next golfer’s name and enter that score. Use **Type a score** for a whole number from 1 to 20.
3. Use **Picked up** when the player did not finish the hole. This records X; it is not a zero.
4. When everyone has an entry, tap the next-hole button. After the final hole, tap **Finish**. Watch for save errors before continuing.

11. Enter all players together

Switch layouts at any time without losing scores.

SAMPLE LINKS GOLF CLUB · WHITE · HOLE 1 OF 18

✓ Saved

Menu

Hole 1 Par 4

384 yards Handicap 11

Alex Green +0 thru 1

− 4 +

No index · handicap limit 6

Sam Reed +1 thru 1


− 5 +

No index · handicap limit 6

Pat Morris

− X +

Guest · not posted · No index · handicap limit 6



Source-matched illustration with fictional example data. **View this screen larger**.

1. Choose **All four together** in setup, or use **Menu** to switch during play. It also works with fewer than four players.
2. Tap **+** on an empty score to start at par. Then use minus or plus, or tap the score field and type a whole number from 1 to 20.
3. Type **X** for picked up. If your keyboard does not offer X, switch to one-golfer mode and tap **Picked up**.
4. Enter a score for everyone, then advance. Blank fields remain unfinished; they do not count as par.


12. Review and correct before posting

The whole card lets you return to a particular hole.

TAP A HOLE TO GO BACK AND CHANGE IT

The card

HO…	PAR	YDS	HCP	ALEX	SAM
1	4	356	1	4	5
2	4	363	2	4	5
3	3	370	3	4	5
4	4	377	4	4	5
5	4	384	5	4	5
6	3	391	6	4	5
7	4	398	7	4	5
8	4	361	8	4	5
9	3	368	9	4	5
10	4	375	10	4	5
11	4	382	11	4	5
12	3	389	12	4	5
13	4	396	13	4	5
14	4	359	14	4	5
15	3	366	15	4	5
16	4	373	16	4	5



Source-matched illustration with fictional example data. **View this screen larger**.

1. Tap **Card** while playing, or **Review card** on the finish screen. Scroll the card if needed to see every hole.
2. Tap the hole you want to change. Select the golfer and enter the correct score.
3. Continue through the round and return to **Finish**. Check the totals before posting. A saved historical card is a viewing screen; make corrections while the round is active.
4. After posting, changes to official rounds belong in The Scorecard with the appropriate access. The Marker does not provide a posted-round editor.

13. Understand the totals

Illustrative 18-hole example: gross 90, adjusted 88 and course handicap 10.

SAMPLE LINKS GOLF CLUB · 17 OCT 2026

Round finished

Check the totals before posting. Adjusted applies net double bogey on each hole, worked out for you.

Alex Green

Weekend Golfers

90	88	80
Gross	Adjusted	Net (CH 10)

Sam Reed


Weekend Golfers

94	92	82
Gross	Adjusted	Net (CH 10)

Pat Morris

Guest · shared only, not posted

96	—	—
Gross	Adjusted	Net (CH 10)



Source-matched illustration with fictional example data. **View this screen larger**.

1. **Gross** adds entered strokes. For an X, the app substitutes that hole’s handicap limit, so it is not a count of strokes actually finished on that hole.
2. **Adjusted** caps high hole scores at the app’s handicap limit: normally par + 2 + strokes received. With no known course handicap, the app uses par + 5.
3. **Net** is gross minus course handicap when the round is complete and a handicap is available. Do not use a nine-hole net display as a posted 18-hole result.
4. **E** means even with par. + and − show over and under par. Stroke notes depend on the selected tee, the player’s index and hole handicap data.

14. Post eligible rounds to Scorecard

Posting and sharing are different actions.

SAMPLE LINKS GOLF CLUB · 17 OCT 2026

Round finished

Check the totals before posting. Adjusted applies net double bogey on each hole, worked out for you.

Alex Green

Weekend Golfers

90	88	80
Gross	Adjusted	Net (CH 10)

Sam Reed


Weekend Golfers

94	92	82
Gross	Adjusted	Net (CH 10)

Pat Morris

Guest · shared only, not posted

96	—	—
Gross	Adjusted	Net (CH 10)



Source-matched illustration with fictional example data. **View this screen larger**.

1. Check all totals. Tap **Post … rounds to The Scorecard** when shown. The number counts eligible group golfers, not guests.
2. Posting requires a signed-in card, at least one selected group golfer, 18 holes, rating and slope, and a score on every required hole. The server checks the submission too.
3. Nine-hole cards, standalone cards and typed guests are kept and shared instead. Read the reason if no Post button is available.
4. A standalone card does not become postable just by signing in later. Start in signed-in mode and select the actual group golfers when posting is your goal.

15. Confirm the posting result

Do not treat Waiting or Checking as a successful post.

POSTING

The Marker


Posted to The Scorecard

The rounds are in The Scorecard now, and the handicap indexes are up to date.

Alex Green · 90
Weekend Golfers
Posted ✓

Sam Reed · 90
Weekend Golfers
Posted ✓

Each one shows "Posted" only once The Scorecard has actually saved it.



Source-matched illustration with fictional example data. **View this screen larger**.

1. **Waiting** means the card is saved locally for sending. Reopen The Marker on the same browser, sign in to the original account if needed and leave it open with a connection.
2. **Checking** means the submission reached the service and is being processed. Allow a few minutes and check again.
3. **Posted** ✓ confirms acceptance. Open The Scorecard to verify the rounds. The service recalculates the posting data, so its final values are authoritative.
4. For **Not posted**, read the reason and keep or share the card. Do not re-enter the same rounds while the original submission is still waiting or being checked.

16. Share a card

Share during play, after finishing or from Your cards.

WHATSAPP, EMAIL, TEXT OR COPY

Share the card


WhatsApp

Email

Text message

Copy

```
Sample Links Golf Club
17 Oct 2026
Alex: 90
Sam: 94
```



Source-matched illustration with fictional example data. **View this screen larger**.

1. Tap **Share the card**. Your device may show its native share sheet; otherwise choose WhatsApp, Email, Text message or Copy.
2. Choose the recipients in your messaging app and send when ready. Sharing sends a text summary with hole scores; it does not post rounds to The Scorecard.
3. If Copy is blocked, press and hold the displayed text and copy it manually. An unfinished card can also be shared; missing holes appear as dashes.

17. Resume, keep and delete cards

Local cards belong to this device and browser.


KEPT ON THIS PHONE

Your cards

Sample Links Golf Club
17 Oct 2026 · Alex, Sam · not posted

River Bend
17 Oct 2026 · Alex, Sam · not posted

Oak Ridge
17 Oct 2026 · Alex, Sam · posted



Source-matched illustration with fictional example data. **View this screen larger**.

1. Return to the start screen through **Menu**. Use **Continue your round** to resume. To stop permanently without posting, choose **End this round without posting** and confirm.
2. **Your cards** holds the most recent 30 saved cards. Open one to view its scorecard, totals and posting status, or share it.
3. **Delete this card** is available only when allowed. Deletion is permanent; posted cards and cards being checked cannot be deleted here.
4. Clearing browser data or changing devices does not carry local cards across. Share important cards before clearing data or exceeding the history limit.

18. When something goes wrong

Keep the card and resolve the displayed message first.

POSTING

The Marker


Posted to The Scorecard

The rounds are in The Scorecard now, and the handicap indexes are up to date.

Alex Green · 90
Weekend Golfers
Posted ✓

Sam Reed · 90
Weekend Golfers
Posted ✓

Each one shows "Posted" only once The Scorecard has actually saved it.



Source-matched illustration with fictional example data. **View this screen larger**.

1. **No signal:** a loaded round can save scores locally. Search, sign-in, photo reading and posting need internet. This web release does not guarantee a fresh offline launch; keep the loaded page available.
2. **Save error:** do not assume the latest score was kept. Check browser storage, avoid private browsing and retry. Share a copy before clearing anything.
3. **Missing golfer:** check the group and connection. A typed guest cannot be posted as that group golfer. Manage membership in The Scorecard.
4. **Photo or posting problem:** read the message, use manual course entry when needed, and check posting status online. For help, use Support on the app’s start screen.

19. The Menu bubble during play

The **Menu** control appears at the top of the hole screen beside the saved indicator. Tap it without leaving your round.

SAMPLE LINKS GOLF CLUB · WHITE · HOLE 1

Menu

Switch to all four together

The scores already entered stay as they are.

See the whole card

Every hole, with par, yards and handicap number. Tap a hole to go to it.

Share the card

WhatsApp, email or text message.

Go to the start screen

The round stays on this phone. "Continue your round" brings you back to this hole.

End this round without posting

The card is kept under "Your cards" and is never posted.



Source-matched illustration with fictional example data. **View this screen larger**.

1. Tap **Menu** at the top right while entering scores.
2. Choose **Switch** to change the score-entry view. Your entered scores stay saved.
3. **See the whole card** lets you review holes; **Share the card** sends a score summary.
4. **Go to the start screen** keeps the active round for **Continue your round**. **End this round without posting** is different: it ends the round and keeps a historical card without posting.
5. Tap **Back to hole** to continue scoring without changing anything.