CHAPTER 6

EDITING SCREEN FILE MENU

The File menu includes commands to open, close, save, and print files, prepare files for fax transmission, and other commands to manage files.

File

Open/Switch...	^OK
Close	
Save	^KS
Save As...	^KT
Save and Close	^KD
Print...	^KS^KP
Fax...	^K\
Change Printer...	^P?
Copy...	^KO
Delete...	^KJ
Rename...	^KE
Change Drive/Directory...	^KL
Run DOS Command...	^KF
Status	^O?
Exit WordStar	^KQX

OPEN/SWITCH

Pull-down: ***ALT F, W***
Classic: ***^OK***

Opens a window so that you can look at two documents at once, or at two parts of the same document. If two windows are already open, moves the cursor to the other window.

Follow these steps to open a new window or to move the cursor to the other window:

1. Choose File→Open/Switch, or use the ^OK classic command.

2. In the Open dialog box, specify the name of the file to open. You can open either an existing file or a new one.

   A filename can have up to eight characters and an optional extension of up to three characters. Type a period between the filename and the extension. Don't use spaces between the characters. Filenames can include letters, numbers, and these symbols:

   $ & # ! % ' ` ( ) { } - _ ~ @

   Note: Files with the extensions .COM, .EXE, .OVR, .SYS, .DCT, .CRT, .WSF, .PDF, .DCC, .INF, .PRD, .WSM, and .$?? (where ? can be any character) do not appear in the WordStar filenames lists, so don't use them to name your text files. You can change this list of filename extensions using WSCHANGE (CEC).

3. Press F10 or choose OK. The screen splits in half. The cursor is located in the new file on the bottom half of the screen.

You can edit in either window. To move the cursor to the other window, use this command or choose View→Open/Switch Window, or use the ^OK classic command.

The title bar shows a [1] when the cursor is in the top window and a [2] when the cursor is in the bottom window. It also shows the name of the file where the cursor is currently located. You can use a mouse to switch to the other window by clicking this number.

The file in the second window is always opened as a document if the file in the first window is a document, or as a nondocument if the file in the first window

is a nondocument. If you want to be able to open a document and a nondocument at the same time, use WSCHANGE (DCGG) to turn on the prompt that asks you whether to open a document or a nondocument when you open a second window.

TIP *If you want to see how the document you're editing looked before you made your most recent editing changes, you can open a second window on the same document. The second window shows the version that you saved last, in protected mode, because you can't make changes to both copies.*

Keep these points in mind when working with two windows:

- To change the sizes of the windows, choose View→Change Window Size, or use the ^OM classic command. You can also press ^– (hyphen) to enlarge the current window one line at a time. For more information, see "Change Window Size" in "Editing Screen View Menu."

- You can mark blocks in both windows at once. To copy a block between windows, choose Edit→Copy→Block from Other Window, or press ^KA. To move a block between windows, choose Edit→Move→Block from Other Window, or press ^KG. For more information, see "Copy" and "Move" in "Editing Screen Edit Menu."

- You cannot edit notes or macros when you have a document in the second window.

CLOSE

Pull-down: ALT + F, C

Closes the file you are editing.

If you have made any changes to the file since you last saved it, WordStar asks if you want to save the changes, abandon them, or cancel the operation. The default is to save the changes.

You can also use the ^KQ classic command to close the file and abandon changes. If you press ^KQ, and you have made changes to the file since you last saved it, WordStar tells you that you've made changes and asks whether you want to abandon it anyway. The default is Yes, to abandon. If you choose

No, WordStar returns you to editing; if you choose Save, WordStar saves the changes and closes the file.

SAVE

Pull-down: ***ALT + F, S***
Classic: ***^KS***

Saves the file you're editing, then resumes editing in the same place.

It's a good idea to use this command periodically when you're working in a file. It guarantees you won't lose your work if you have a power failure or other problem.

When you edit an existing file, the original file stays on disk while you work on a copy in the computer's memory. Each time you save the file, the copy in memory (with all your changes) goes back on the disk and replaces the original file. The original is saved as the backup file, with the .BAK extension.

SAVE AS

Pull-down: ***ALT + F, A***
Classic: ***^KT***

Saves the file you are editing and allows you to rename the file.

Follow these steps to save and name a file.

1. Choose File→Save As, or use the ^KT classic command.
2. In the Save As dialog box, specify the name for the file. Include a directory path if necessary.
3. Press F10 or choose OK to save the file.

If you keep the same filename, the previous version of the file is saved as the backup file. If you give the file a different name than it originally had, the original file is unchanged.

TIP *If the current disk is full and you want to save the file to another disk, just specify the new drive as part of the filename.*

SAVE AND CLOSE

Pull-down: ***ALT + F, L***
Classic: ***^KD***

Saves the file and returns you to the Opening screen.

This command saves the file with the same name it had when you opened it.

When you edit an existing file, the original file stays on disk while you work on a copy in the computer's memory. Each time you save the file, the copy in memory (with all your changes) goes back on the disk and replaces the original file. The original is saved as the backup file, with the .BAK extension.

TIP *If you try to save a file and WordStar tells you there is insufficient disk space to save it, you can choose File→Save As (or use ^KT) to save it to a different disk, or you can choose File→Run DOS Command (or use ^KF) to delete files from the disk so that you can save the file.*

PRINT

Pull-down: ***ALT + F, P***
Classic: ***^KS^KP***

Saves the current file and then prints it.

This command saves the current file and then prints it (or prints another file that you specify). The file is not closed; you can continue editing it, although your changes aren't printed. Follow these steps:

1. Choose File→Print, or use the classic commands ^KS (to save the file) and then ^KP (to print it).

2. In the Print dialog box, change any of the print options you want. The print options and their defaults are described below.

```
                              Print
Filename: REVIEW.DOC                                  OK

Page Numbers:                                 Pages:        Cancel
        ◆ All                                  o Odd
        o Selected Pages:                      o Even
                                               ◆ Both

     Copies: 1

                                          [X] Use Form Feeds
    Printer: DRAFT                        [ ] Pause Between Pages
                                          [ ] Print Unformatted Text
Redirect To:                              [X] Interpret Merge Variables
```

Filename Specify the file to print. The default is the file you are currently editing.

Page Numbers Select All (the default) to print every page in the file. To specify the pages to print, select Selected Pages and type the page numbers, separated with spaces. You can specify a range by using a hyphen. For example, to print pages 1 through 3 and pages 5 and 7, type **1-3 5 7**. (If you've reassigned page numbers, when you use Selected Pages, printing starts at the first occurrence of the first number specified, and ends at the first occurrence of the last number specified.)

Copies You can print more than one copy of the document. The default is one copy. To change it, type the number of copies you want. (If you always want the file printed a certain number of times, you can use Utilities→Merge Print Commands→Print File n Times, or the **.rp** dot command. See "Merge Print Commands" in "Editing Screen Utilities Menu.")

Printer WordStar displays the name of the printer assigned to the file. To change it, type another printer name or select a name from the list of your installed printers.

Redirect To The output normally goes to whatever port you specified for the printer you are using. If you want to redirect the output to another port, type the name of the port. If you want to redirect output to a disk file, type the filename. For more information, see "Printing to Disk" in "Print" in "Opening Screen File Menu."

Pages To print only odd or only even pages, choose Odd or Even. The default is Both.

Use Form Feeds If you want WordStar to send a form feed to the printer when moving to the next page of a printout, select this check box. Form feeds are required for a laser printer or other sheet feeder. The default depends on the type of printer you are using. You can use PRCHANGE to specify a different default for each of your printers. Clear this box whenever you print on paper shorter than 11 inches.

Pause Between Pages If you need to have the printer pause between pages so you can feed individual sheets of paper to it, select this check box. You can use PRCHANGE to specify a different default for each of your printers. The default is no pause. If you select this option, WordStar pauses before the second page and each subsequent page.

Print Unformatted Text If you select this option, WordStar prints all the dot commands and does not execute them. Always use this option for printing nondocuments. The check box is clear as a default.

Interpret Merge Variables Merge print variables and commands are interpreted as a default. If you clear this check box, variable names are printed in the text rather than the variables, and merge print commands are ignored. For more information on merge print commands and variables, see "Merge Print Commands" in "Editing Screen Utilities Menu."

Note: You can change the default settings for many of the print options using WSCHANGE or PRCHANGE.

3 Press F10 or choose OK to print the file.

WordStar normally prints in the background so that you can continue with what you were doing before you started printing. The word *Printing* appears in the status line. If printing stops during background printing, *Print Wait* replaces *Printing*. You can use WSCHANGE (BDCA) to turn background printing off. This makes printing faster.

If your file contains any Ask for Variable, Pause Print, or Clear Screen commands, and you are using background printing, the *Print Wait* message appears in the status line. You must press P to go to the Printing screen (described below), and then enter the required response. If your file contains any Display

Message commands, you don't see the messages unless you go to the Printing screen.

TIP *The default speed for printing is full speed. However, some printers can't receive the printing input fast enough. If you're printing while editing, you may notice a time lag between pressing keys and the resulting onscreen operation. To eliminate this lag, use PRCHANGE to change the printing speed to a slower setting.*

The Printing Screen shows messages and commands related to printing. The Printing screen is hidden during background printing. You must display the Printing screen before you can see a printing-related message or enter a printing-related command during printing. To display this screen, choose File→Print or use the classic command P at the Opening screen or ^KP while editing.

```
                              Printing

   P Pause                                  F Print at Full Speed
   C Continue after Pausing                Esc Cancel Printing
   B Print from Background
```

Messages appear below the Printing screen commands. The commands are described below.

COMMAND	DESCRIPTION
P	Pauses printing temporarily
C	Continues printing after a pause
B	Starts background printing and exits the Printing screen
F	Starts full-speed printing if you used PRCHANGE to choose a slower printer speed
Esc	Cancels printing completely and exits the Printing screen

During printing, the Printing screen status line shows the page number that is currently being printed. It also shows the copy number that is currently being printed. This is useful if you are printing more than one copy of a document.

FAX

Pull-down: ***ALT + F, F***
Classic: ***^K***

Creates files that you can send with a fax board.

This command creates fax files in .PCX format. These files can be transmitted directly through a fax board using the software that came with the fax board. The resulting faxes look like the output to the printer, including all the fonts and other formatting.

Note: Most fax boards can transmit .PCX files. However, if your board does not support .PCX format, you must convert the .PCX file to a format supported by the board. Most fax board software includes a conversion utility that can do this.

One .PCX file is created for each page in a document. All the .PCX files you create are placed in the WS\FAX directory, which WordStar creates the first time you create a fax file. You can specify another fax file directory using WSCHANGE (CD4I).

Follow these steps to create fax files:

1. Choose File→Fax, or use the ^K\ classic command.

2. In the Fax dialog box, specify the name of the file to fax. If necessary, specify the path with the filename.

3. If you want to change the displayed name for the first fax file to create, specify the name you want. The default is the first five letters of the original filename, followed by three digits that represent the page number, starting with 001. Fax files for subsequent pages are numbered sequentially. The filename extension is always .PCX.

   If the filename you specify is the name of an existing file, WordStar asks if you want to overwrite the file. If you choose Overwrite (or press Y), WordStar deletes the old file and replaces it with the new file. If you choose Cancel (or press N), WordStar does not create the fax files. You can start again and use a different filename.

   TIP *To avoid confusion, always choose a unique filename when you create fax files, and delete fax files promptly when you no longer need them.*

4 Change any of the options you want. These options are described below.

```
                                  Fax
      File to Fax: C:\WS\SHAKE.DOC                          OK
Fax File Location: C:\WS\FAX                                Cancel
 Name of Fax File: SHAKE 001.PCX                 Resolution:      View
                                                   o Low
 Fax Page Numbers:                                 ◆ High
    ◆ All                                          o Special 300 dpi
    o Selected Pages:                              o 9-pin Dot Matrix
                                                   o 24-pin Dot Matrix
```

Fax Page Numbers Select All (the default) to create fax files for every page. To specify pages, select Selected Pages and type the page numbers, separated with spaces. You can specify a range by using a hyphen. For example, for pages 1 through 3 and pages 5 and 7, type **1-3 5 7**.

IMPORTANT When you use Selected Pages, you must specify the physical page numbers, even if you've reassigned page numbers. For example, if you have a three-page document with no page number on the first page, and the second and third pages are numbered 1 and 2, you must specify 2-3 (or 2 3) to create fax files for the last two pages. If you're not sure about the physical page numbers, you can choose View→Preview (or ^OP). Preview displays the physical page numbers at the top of the screen or, if more than one page is displayed, above each page.

Resolution Select the resolution your fax board uses. High resolution, the default, is 200x200 dots per inch (dpi), and low resolution is 200x100 dpi. The Special 300 dpi option is provided for fax drivers that use this resolution. The 9-Pin Dot Matrix and 24-Pin Dot Matrix settings are not used for creating fax files. They create files that can be printed on a dot matrix printer using a utility (not provided with WordStar) for printing .PCX files.

If the setting does not match the setting in your fax software, the file may not look right when it is faxed. High resolution produces much better-looking output. (Be sure to send the fax using the same resolution you create it with.)

View You can choose the View button to preview the file in order to decide which pages to create fax files for. While you are previewing the file, you can use all the usual Preview commands, including the Options

command to create fax files. If you create fax files in Preview, you return to editing when you exit Preview; otherwise, you return to the Fax dialog box. For more information about Preview, see "Preview" in "Editing Screen View Menu."

5 When you finish, press F10 or choose OK. WordStar creates the fax file or files, displaying the progress.

You can press Esc to cancel fax file creation after the current page, or press Esc twice to cancel it immediately.

After you create a fax file, you can use the SHOWPCX utility to identify the file, to make sure you've processed the correct pages, and to check the quality of the fonts. Start at the system prompt, type **showpcx fax*filename*** (you don't need to type the .PCX extension) and press Enter. The fax file appears on the screen in half-size format, so that you can see more of the page. Press the Plus (+) key on the numeric keypad to view it in maximum resolution. You can use the scrolling commands and PgUp and PgDn to move around on the page. When you finish viewing the file, press Esc to exit SHOWPCX. (Depending on your monitor and the resolution you specified for the fax file, the image may not have the proper proportions.)

When you are working with fax files, keep these things in mind:

- The fax file is a graphic representation of the printed page and is created using the same process as Preview. All the features and limitations of Preview apply to creation of fax files. For example: The same fonts are available, and a 72-point font is used for fonts that are larger than 72 points. Colors other than white are changed to black. System variables (such as date and time) and merge print variables are not replaced with the corresponding data.

- For the best appearance of fonts in fax files, it's best to use the FAX.PDF printer driver for the document. This printer driver supplies fonts comparable to Hewlett-Packard LaserJet III fonts, including Courier, Line Printer, and scalable Times and Univers fonts. FAX.PDF is installed when you install WordStar. You can add your own fonts to this PDF using PRCHANGE.

- The best way to determine how the fax will look is by using Preview at 4x zoom. Usually (depending on your monitor resolution), this option corresponds most closely with the fax file resolution.

- Creating fax files requires up to 27K of memory in addition to what WordStar usually needs. You may need to free up memory for optimum performance with fax files. For guidelines on memory usage, see *Installing and Customizing*. If your fax driver software remains in memory, you may need to remove it before starting WordStar, and send your faxes after exiting WordStar.

- If the appearance of fonts (especially large fonts) is blocky, WordStar may need more memory while creating screen fonts. If less than 512K is available when you start WordStar, you can remove memory-resident programs or use WSCHANGE settings to make more memory available, and then run the DELCRT utility to delete the blocky fonts. Then start WordStar and create the fax files again. You can also improve these fonts by creating .WSF files for large fonts using smaller symbol sets. For more information on .WSF files, see the *Installing and Customizing* booklet.

- Fax files are large, and take up a lot of disk space. You may want to delete them regularly. Also, .CRT files are created when you create fax files. You can delete .CRT files that you no longer need using the DELCRT utility. For more information, see "Preview Files" in "Preview" in "Editing Screen View Menu."

CHANGE PRINTER

Pull-down: ***ALT + F, H***
Classic: ***^P?***

Changes the printer assigned to the file you are editing.

When you choose this command, WordStar displays a list of the available printer description files (PDFs), and you can choose the one you want. Follow these steps:

1. Choose File→Change Printer, or use the ^P? classic command.

2. In the Change Printer dialog box, specify the name of the printer to use. The list below the dialog box shows the available printers.

3. Press F10 or choose OK.

After you change the printer, you can use Style→Font (or ^P=) to see the fonts available for that printer. See "Font" in "Editing Screen Style Menu."

After you change the printer and any fonts you need to change, be sure to reformat your document (Utilities→Reformat→Rest of Document or the ^QU classic command).

COPY

Pull-down: ***ALT + F, O***
Classic: ***^KO***

Copies a file.

Copying makes an exact duplicate of the file being copied; the original is saved, not erased. Follow these steps to copy a file:

1. Choose File→Copy, or use the ^KO classic command.

2. In the Copy dialog box, specify the name of the file to copy. If the file is not on the current drive and directory, specify the path with the filename.

3. Specify the name of the file to copy to. You can put the copy on another drive or directory by specifying the path with the filename.

   You can use the same filename if you copy from one drive or directory to another, but you cannot have two files with the same name in the same directory. If the filename you give for the new copy is the name of an existing file, WordStar asks if you want to overwrite the file. If you choose Overwrite (or press Y), WordStar deletes the old file and replaces it with the new file. If you choose Cancel (or press N), WordStar does not copy the file. You can start again and use a different filename.

4. Press F10 or choose OK to copy the file.

DELETE

Pull-down: ALT + F, T
Classic: ^KJ

Deletes a file.

Follow these steps to delete a file:

1. Choose File→Delete, or use the ^KJ classic command.
2. In the Delete dialog box, specify the name of the file to delete. If the file is not on the current drive and directory, specify the path with the filename.
3. Press Y or Enter to confirm you want to delete the file.
4. Press F10 or choose OK to delete the file.

RENAME

Pull-down: ALT + F, E
Classic: ^KE

Renames a file.

Follow these steps to rename a file:

1. Choose File→Rename, or use the ^KE classic command.
2. In the Rename dialog box, specify the name of the file to rename. If the file is not on the current drive and directory, specify the path with the filename.
3. Type a new name for the file.

   If the filename you type is the name of an existing file, WordStar tells you that that file already exists. Type a different name.
4. Press F10 or choose OK to rename the file.

TIP *You can move a file when you rename it by specifying the path with the filename. The new location must be on the same disk drive.*

CHANGE DRIVE/DIRECTORY

Pull-down: ***ALT + F, V***
Classic: ***^KL***

Changes the logged drive and directory.

The logged drive or directory is the one you're currently working in. WordStar looks for and stores files on the logged drive and directory unless you tell it otherwise.

1. Choose File→Change Drive/Directory, or use the ^KL classic command.
2. In the Change Drive/Directory dialog box, specify the name of the drive and directory to change to.
3. Press F10 or choose OK.

CAUTION When you change disks in a floppy disk drive, log on to the drive again. If you don't, the operating system may refuse to write to the disk, or it may damage data on the new disk. (Never remove a floppy disk while you're editing a file on it and then log on to the drive again.)

RUN DOS COMMAND

Pull-down: ***ALT + F, R***
Classic: ***^KF***

Allows you to run a DOS command without leaving WordStar.

When you use this command, WordStar temporarily moves into the background, and you can type the DOS command you want. For example, you can start Lotus 1-2-3 and look up information on a spreadsheet, or you can use the DOS CHKDSK command to check how much free disk space you have.

1. Choose File→Run DOS Command, or use the ^KF classic command.
2. In the Run DOS Command dialog box, type the DOS command to run.
3. Press F10 or choose OK.

TIP *If you want to run more than one DOS command without returning to WordStar, type* ***command*** *and press Enter to run the DOS command processor. You can then run as many commands as you want. When you finish using DOS commands, type* ***exit*** *and press Enter. Then press any key to return to WordStar.*

The amount of memory you can use to run DOS commands depends on how much memory WordStar is using, whether you are using any memory-resident programs, how much EMS memory is available to WordStar, and how much disk space is available.

CAUTION *Never load a memory-resident program (such as DOS PRINT, Inset or Sidekick) using this command. If you plan to use such a program from within WordStar, be sure you load it before you start WordStar.*

STATUS

Pull-down: ***ALT + F, U***
Classic: ***^O?***

Displays the Status screen.

```
                                   Status
Current Filename: C:\WS\SHAKE.DOC                                Continue

      Byte count: 128
     Markers set: (none)
           Inset: Not Loaded
 Current printer: HP3

         Release: WordStar for DOS North American Version 7.0 Rev. A
   Serial Number: 12345678
        Language: United States   (001)

 Memory Usage
 ┌──────────────────────────────────────────────────────────────────────┐
 │      WordStar:   210k      Messages:     2k      Hyphenation:     0k  │
 │  Text and Data:  108k      Printing:     0k        Thesaurus:     0k  │
 │                                                     Spelling:      0k  │
 │                                                                        │
 │   Conventional Memory        In Use:   298k     Available:   278k     │
 │                                                                        │
 │  Expanded Memory (EMS)       In Use:   256k     Available:  4336k     │
 └──────────────────────────────────────────────────────────────────────┘
```

The Status screen gives information on the current filename, byte count from the beginning of the file to the cursor position, markers set, Inset status, printer, WordStar version and serial number, language, and memory usage.

EXIT WORDSTAR

Pull-down: ***ALT + F, X***
Classic: ***^KQX***

Closes the file without saving changes, then immediately exits WordStar.

If you've made changes to the file since the last time you saved it, WordStar prompts you to verify that you want to abandon your changes.

If you're printing in the background when you use the Exit command, the Printing screen appears after you exit the file. You must wait until printing finishes, or press Esc to cancel printing, before you exit WordStar.