RPMGLOBAL

AMT EPF Adapter SDK

Reference 9.0



© 2025 RPMGLOBAL | All Rights Reserved

Contents

1 **Business Background** 8

2 **Considerations and Assumptions** 8

3 **Decision Points and Configuration Options** 8

4 **Prerequisites** 9

5 **Integration Patterns** 10

5.1 Supported Integration Patterns 10

5.2 Integration Service Address 12

5.3 Synchronous Transaction Patterns 13

6 **Field Descriptions** 14

6.1 Customer Identification 14

6.2 Customer 14

6.3 Model 16

6.4 Cost Centre 16

6.5 Supplier 17

6.6 Currency 17

6.7 Organisation 17

6.8 Cost Bearer 17

6.9 Source of Supply 18

6.10 Part Type 18

6.11 Notification Type 18

6.12 Asset Planning Type 18

6.13 Equipment Class 19

6.14 Equipment Group 19

6.15 Unit Of Measure 19

6.16 Manufacturer 19

6.17 Labour Activity 20

6.18 Cost Expense 20

6.19 User 20

6.20 Planning Group 21

6.21 Labour Rate 22

6.22 Symptom 22

6.23 Cause 22

6.24 Priority 22

6.25 Work Group 23

6.26 Fleet 23

6.27 Catalogue Profile 24

7 Error Handling 25

8 Integration Functions 26

8.1 ProcessCustomer 26

8.2 CancelCustomer 29

8.3 GetCustomer 29

8.4 GetModel 30

8.5 GetCostCentre 31

8.6 GetSupplier 32

8.7 GetCurrency 33

8.8 GetOrganisation 33

8.9 GetCostBearer 34

8.10 GetSourceOfSupply 35

8.11 GetPartType 35

8.12 ProcessNotificationType 36

8.13 GetAssetPlanningType 38

8.14 ProcessCostCentre 38

8.15 GetEquipmentClass 40

8.16 GetEquipmentGroup 40

8.17 ProcessEquipmentClass 42

8.18 ProcessEquipmentGroup 42

8.19 ProcessUnitOfMeasure 43

8.20 GetManufacturer 44

8.21 ProcessManufacturer 45

8.22 GetLabourActivity 46

8.23 ProcessLabourActivity 46

8.24 ProcessCostExpense 48

8.25 ProcessUser 49

8.26 ProcessPlanningGroup 52

8.27 ProcessLabourRate 53

8.28 ProcessSymptom 54

8.29 ProcessCause 55

8.30 ProcessPriority 56

8.31 ProcessWorkGroup 57

8.32 ProcessModel 58

8.33 ProcessFleet 59

8.34 ProcessCatalogueProfile 63

8.35 GetSymptom 63

8.36 GetCause 64

8.37 GetWorkGroup 65
9 Response Formats 67
9.1 Respond Customer 67
9.2 ShowCustomer 67
9.3 ShowModel 68
9.4 ShowCostCentre 68
9.5 ShowSupplier 69
9.6 ShowCurrency 69
9.7 ShowOrganisation 70
9.8 ShowCostBearer 70
9.9 ShowSourceOfSupply 70
9.10 ShowPartType 71
9.11 RespondNotificationType 71
9.12 ShowAssetPlanningType 72
9.13 RespondCostCentre 72
9.14 ShowEquipmentClass 73
9.15 ShowEquipmentGroup 73
9.16 RespondEquipmentGroup 74
9.17 RespondUnitOfMeasure 74
9.18 ShowManufacturer 75
9.19 RespondManufacturer 75
9.20 ShowLabourActivity 76
9.21 RespondLabourActivity 76
9.22 RespondCostExpense 77
9.23 RespondUser 77
9.24 RespondPlanningGroup 78
9.25 RespondLabourRate 78
9.26 RespondSymptom 79
9.27 RespondCause 79
9.28 RespondPriority 80
9.29 RespondWorkGroup 80
9.30 RespondModel 81
9.31 RespondFleet 81
9.32 RespondCatalogueProfile 82
9.33 ShowSymptom 82
9.34 ShowCause 83
9.35 ShowWorkGroup 83

Document History

Version	Date	Description	Author
1.0	1-Feb-2018	Initial Document	Darryl Smith
1.1	7-Feb-2018	Added Data Structure	Moni Baruah
2.0.0	5-Sep-2018	Reformat/Rename	Grant Johnson
2.0.1	10-Jan-2019	Update Service References	Andre Britz
2.0.2	19-Nov-2020	Added new functions: GetModel GetCostCentre GetSupplier GetCurrency GetOrganisation GetCostBearer GetSourceOfSupply GetPartType **BREAKING CHANGE**: The CostBearerCode attribute of the result of GetCustomer() now returns the Cost Bearer Code, not the Cost Bearer Description	Gary Lu
2.2.5	22-Jul-2022	Added new functions: GetAssetPlanningType ProcessCostCentre GetEquipmentClass GetEquipmentGroup ProcessEquipmentClass ProcessEquipmentGroup ProcessUnitOfMeasure GetManufacturer ProcessManufacturer GetLabourActivity ProcessLabourActivity ProcessCostExpense ProcessLabourActivity ProcessUser ProcessPlanningGroup ProcessLabourRate ProcessNotificationType ProcessSymptom ProcessCause ProcessPriority ProcessWorkGroup	Wayne Simpkins

Version	Date	Description	Author
2.3	18-Jul-2023	Add new functions: ProcessFleet ProcessModel Formatting and miscellaneous corrections.	Wayne Simpkins
8.25	11-Sep-2023	Corrected the unique identifier field on the labour activity function. Clarified sitecode tag usage in the work group function.	Wayne Simpkins
8.26	01-Nov-2023	Documented support for ASYNC processing. Added ReferenceProcessModelInsertMode and ReferenceProcessFleetInsertMode Added ProcessCatalogueProfile().	Wayne Simpkins
8.27	01-Jun-2024	8.27	Wayne Simpkins
8.28	01-Oct-2024	Added support for OAuth2 authentication. Add more supported functions for ASYNC processing.	Wayne Simpkins
8.28.2	10-Apr-2025	Added GetSymptom, GetCause and GetWorkGroup.	Wayne Simpkins
9.0	17-Jul-2025	All inbound integration functions now support ASYNC processing Moved details of synchronous/asynchronous processing and authentication options to the central overview document.	Wayne Simpkins

Version Amendments

The following modifications were made to this document since 1.00.

Item	Description
8.1.3	Added data structure to ProcessCustomer
8.2.3	Added data structure to CancelCustomer
8.3.3	Added data structure to GetCustomer
9.1.1	Added data structure to RespondCustomer
9.2.1	Added data structure to ShowCustomer
5.2	Update the Service Addresses
4	Added new Pre-requisites from Model to Global Part Type
5.1	Added 8 new functions from GetModel to GetPartType
6.3-6.10	Added field descriptions for 8 new functions

Item	Description
8.4-8.11	Added 8 new functions
9.1.1, 9.2.1	Changed figure number
9.3-9.10	Added 8 new response formats

1 Business Background

The Reference service provides functions to manage the AMT configuration items and code lists.

2 Considerations and Assumptions

Customer

The price group of a customer determines the pricing used in standard jobs. This, in turn, determines the pricing used when creating quotes in AMT.

3 Decision Points and Configuration Options

The following AMT configuration settings will affect the behaviour of these interfaces, so the implementer will need to know these settings.

AMT Configuration Setting	Description
StandardJobExpenseAllocation	This setting determines if Standard Job Expense Allocations are being used. When enabled, the validation of expense element is affected for ProcessLabourActivities. Refer to business rules for ProcessLabourActivities.
ReferenceProcessFleetInsertMode	Controls the behaviour when the Reference Adapter ProcessFleet() method is called. For a setting of 0 (the default), if the fleet code does not exist, create it, and if the fleet code does exist, update it. A setting of 1 will only create new codes. If the integration message contains codes that already exist in AMT, the adapter will return a warning that the code already exists in AMT and has not been modified. The warning will also be recorded in IMPORT_ERROR.
ReferenceProcessModelInsertMode	Controls the behaviour when the Reference Adapter ProcessModel() method is called. A setting of 0 (the default) will not alter existing ProcessModel processing logic. That is, if the model code does not exist, create it. If the model code does exist, update it. A setting of 1 will only create new codes. If the integration message contains codes that already exist in AMT, the adapter will return a warning that the code already exists in AMT and has not been modified. The warning will also be recorded in IMPORT_ERROR.

4 Prerequisites

The following AMT configuration items must be compared prior to using these integration endpoints:

- Employee (Account Manager)
- Employee (Sales Responsibility)
- Cost Bearer
- Parts Accounting Customer Class
- Price Group
- Model
- Manufacturer
- Model Family (Equipment Group)
- Cost Centre
- Supplier
- Organisation
- Currency
- Source of Supply
- Part Type
- Global Part Type

5 Integration Patterns

5.1 Supported Integration Patterns

This integration provides support for the following functions:

AMT Configuration Setting	Description
ProcessCustomer	Add a new customer to AMT, or update an existing customer if it already exists
CancelCustomer	Update the Customer Flag and Delete flag
GetCustomer	List all customers matching the given search criteria
GetModel	List all models matching the given search criteria
GetCostCentre	List all cost centres matching the given search criteria
GetSupplier	List all suppliers matching the given search criteria
GetCurrency	List all currencies matching the given search criteria
GetOrganisation	List all organisations matching the given search criteria
GetCostBearer	List all cost bearers matching the given search criteria
GetSourceOfSupply	List all sources of supplies matching the given search criteria
GetPartType	List all part types matching the given search criteria
GetAssetPlanningType	List all asset planning types matching the given search criteria
ProcessCostCentre	Add a new cost centre to AMT, or update an existing cost centre if it already exists
GetEquipmentClass	List all equipment classes matching the given search criteria
GetEquipmentGroup	List all equipment groups matching the given search criteria
ProcessEquipmentClass	This is defined in the interface, but has not yet been implemented. Adds a new equipment class to AMT, or updates an existing equipment class if it already exists
ProcessEquipmentGroup	Add a new equipment group to AMT, or update an existing equipment group if it already exists
ProcessUnitOfMeasure	Add a new UOM to AMT, or update an existing UOM if it already exists
GetManufacturer	List all manufacturers matching the given search criteria
ProcessManufacturer	Add new manufacturer codes to AMT, or update existing manufacturer details if they already exist
GetLabourActivity	List all labour activities matching the given search criteria
ProcessCostExpense	Add a new cost expense to AMT, or update an existing cost expense if it already exists
ProcessLabourActivity	Add a new labour activity to AMT, or update an existing labour activity if it already exists
ProcessUser	Add a new user to AMT, or update an existing user if it already exists
ProcessPlanningGroup	Add a new planning group to AMT, or update an existing planning group if it already exists
ProcessLabourRate	Add a new labour rate to AMT, or update an existing labour rate if it already exists

AMT Configuration Setting	Description
ProcessNotificationType	Add a new notification type to AMT, or update an existing notification type if it already exists
ProcessSymptom	Add a new symptom to AMT, or update an existing symptom if it already exists
ProcessCause	Add a new cause to AMT, or update an existing cause if it already exists
ProcessPriority	Add a new priority to AMT, or update an existing priority if it already exists
ProcessWorkGroup	Add a new work group to AMT, or update an existing work group if it already exists
ProcessModel	Add a new model code to AMT, or update an existing model code's details if it already exists
ProcessFleet	Add a new fleet to AMT, or update existing fleet details if they already exist
ProcessCatalogueProfile	Add a new catalogue profile to AMT, or update an existing catalogue profile.
GetSymptom	List all symptom codes matching the given search criteria
GetCause	List all cause codes matching the given search criteria
GetWorkGroup	List all work group codes matching the given search criteria

5.2 Integration Service Address

More details regarding the general features of the integration service can be found in the Service Overview documentation. In order to use this service, the following endpoints are available for various authentication scenarios. These may not all be available, depending on the deployment configurations at a specific site.

Basic authentication	Domain, username and password provided when establishing the connection
https://<Server>:<port>/ReferenceIntegrationService/ReferenceIntegration/BasicHttpBinding_Https_Basic	
http://<Server>:<port>/ReferenceIntegrationService/ReferenceIntegration/BasicHttpBinding_Http_Basic	

Windows authentication	The Windows credentials of the current Windows account are used to establish the connection. This is the default method if no binding is specified in the URL.
https://<Server>:<port>/ReferenceIntegrationService/ReferenceIntegration/	
http://<Server>:<port>/ReferenceIntegrationService/ReferenceIntegration/	

OAUTH2 authentication	Client authentication is used to retrieve an OAUTH2 access token. The token is passed in the SOAP header when calling the AMT EPF Adapters.
https://<Server>:<port>/ReferenceIntegrationService/ReferenceIntegration/BasicHttpBinding_Https_Token	
http://<Server>:<port>/ReferenceIntegrationService/ReferenceIntegration/BasicHttpBinding_Http_Token	

<Server> is the fully qualified name of the server hosting the service.

Note that Windows authentication is being deprecated.

5.3 Synchronous Transaction Patterns

Synchronous integration should align with the transaction pattern as shown in Figure 1 below.




Figure 1 Synchronous Transactions

6 Field Descriptions

The fields in the following tables are used for this integration. The data types for each field are described in the relevant XML schema definition.

6.1 Customer Identification

CustomerNumber is used to identify a customer.

Field Name	Description	Sample Values
CustomerNumber	Used to identify a customer record.	123456

6.2 Customer

Field Name	Description	Sample Values
CustomerName	How the customer is to be named in AMT.	ABC Mining Australia
BusinessEmailAddress	Email address of the business contact for the customer.	roger@abcmining.com
BusinessFaxNumber	Fax number of the business contact for the customer.	(+1)12345678
BusinessName	Name of the business contact for the customer.	Roger Federer
BusinessPhoneNumber	Phone number of the business contact for the customer.	(+1)12345678
CostBearerCode	The configured AMT cost bearer code for the customer.	Contract
AccountManagerEmployeeNumber	The AMT employee who is the account manager for the customer.	Rafael Nadal
Classification	A way to group customers in AMT.	Coal Mining
Country	Country of the customer.	United Kingdom
County	County of the customer.	Surrey
GroupingA	A way to group customers in AMT.	Grp A
GroupingB	A way to group customers in AMT.	Grp B
GroupingC	A way to group customers in AMT.	Grp C
GroupingD	A way to group customers in AMT.	Grp D
GroupingE	A way to group customers in AMT.	Grp E
Industry	The industry of the customer.	Mining
InvoicingIndicator	Invoicing method for the customer.	ABC123
Location	Location of the customer.	East Surrey
PostCode	Post code of the customer.	1234
PrimaryDivision	The primary division of the customer.	Finance
SalesZoneLevel1	A way to group customers.	Zone 1
SalesZoneLevel2	A way to group customers.	Zone 2

Field Name	Description	Sample Values
Size	Size of the customer.	Very large
StoreNumber	Store number of the customer.	Store 7
DealerDepartment	Department within a dealer that deals with the customer.	Contracts
FaxNumber	Fax number of the customer.	(+1)12345678
GroupCustomer	The group customer of the customer.	ABC Mining Global
HealthRelationship	The health relationship with the customer.	SOS analysis only
Notes	Notes for the customer.	This is a really good customer.
PACC	A way to group customers.	PACC1
ParentCustomerName	The parent customer of the customer.	ABC Mining Australasia
PartsClass	A way to group customers.	Large
PhoneNumber	The phone number of the customer.	(+1)12345678
PostalStateCode	The postal state of the customer.	NSW
PostalStreet	The postal street of the customer.	123 Macquarie St
PostalSuburb	The postal suburb of the customer.	Woolloomooloo
PrimaryIndustryCode	The primary industry code of the customer.	Thermal Coal Mining
SalesResponsibilityEmployeeNumber	The AMT employee responsible for sales to the customer.	Andy Murray
PurchasingProfile	The purchasing profile of the customer.	Lucrative
RelationshipProfile	The relationship profile of the customer.	Very Healthy
StateCode	The state of the customer.	NSW
StreetAddress	The street address of the customer.	123 Macquarie St
Suburb	The suburb of the customer.	Woolloomooloo
CSACustomerIndicator	Indicates whether the customer is a Customer Support Agreement (CSA) customer.	1
PSMIndicator	Indicates whether the customer is used in the Product Support Marketing (PSM) module of AMT.	0
PriceGroupCode	The configured AMT price group code of the customer.	DEFAULT
OrganisationCode	The configured AMT organisation of the customer.	Org1

6.3 Model

Field Name	Description	Sample Values
ModelId	AMT unique System Id of the model. This field is only applicable in the ShowModel response to a GetModel request. It is not relevant to the ProcessModel function.	1
ModelCode	The model code.	793C
ModelDescription	The model description.	12H
ManufacturerName	Name of the manufacturer of the model.	Caterpillar
ModelFamilyCode	The code of the model family (Equipment Group) to which the model belongs.	797

6.4 Cost Centre

Field Name	Description	Sample Values
CostCentreId	AMT unique System Id of the cost centre.	1
CostCentreCode	The cost centre code.	RENT
CostCentreDescription	The cost centre description.	RENTAL
OrganisationCode	The code of the organisation to which the cost centre belongs.	ORG
CBD	Indicator for whether the cost centre is intended for Component Based Depreciation (which is different to the newer Capital Asset Depreciation). Not yet implemented in ShowCostCentre.	0 or 1
CCActivityCode	The cost centre's activity code or description, which is used for reporting in the budget and forecasting module. Not yet implemented in ShowCostCentre.	GRINDING
CCLocation	The cost centre's location code or description, which is used for reporting in the budget and forecasting module. Not yet implemented in ShowCostCentre.	MILL
CCResponsibility	The cost centre's responsibility code or description, which is used for reporting in the budget and forecasting module. Not yet implemented in ShowCostCentre.	MAINT

6.5 Supplier

Field Name	Description	Sample Values
DefaultRecord	Indicates whether or not the supplier is the default supplier in AMT	0 or 1

6.6 Currency

Field Name	Description	Sample Values
CurrencyId	AMT unique System Id of the currency.	1
CurrencyCode	The code for the currency.	AUD
Description	The currency description.	Australian Dollars
Symbol	The currency symbol.	$
DefaultLabourRate	Configured default labour rate of the currency.	18.3
PrimaryCurrencyIndicator	Indicates whether or not the currency is the primary currency in AMT.	0 or 1

6.7 Organisation

Field Name	Description	Sample Values
OrganisationId	AMT unique System Id of the organisation.	1
OrganisationCode	The code for the organisation.	ORG
OrganisationName	Name of the organisation.	Organisation 1
DefaultRecord	Indicates whether or not the organisation is the default in AMT.	0 or 1

6.8 Cost Bearer

Field Name	Description	Sample Values
CostBearerId	AMT unique System Id of the cost bearer.	1
CostBearerCode	The cost bearer code.	CC
CostBearerName	A cost bearer name.	Contract
DefaultRecord	Indicates whether or not the cost bearer is the default in AMT.	0 or 1
Capital	Indicates whether or not the cost bearer is capital.	0 or 1

6.9 Source of Supply

Field Name	Description	Sample Values
SourceOfSupplyId	AMT unique System Id of the source of supply.	1
SourceOfSupplyCode	The source of supply code.	CAT
SourceOfSupplyDescription	The source of supply description.	Caterpillar

6.10 Part Type

Field Name	Description	Sample Values
PartTypeId	AMT unique System Id of the part type.	1
PartTypeCode	The code for the part type.	CAT
PartTypeDescription	The part type description.	Caterpillar
DefaultRecord	Indicates whether or not the part type is the default in AMT.	0 or 1
GlobalPartTypeCode	The code of the global part type to which the part type belongs.	CAT
FluidType	Indicates whether or not the part type is fluid.	0 or 1

6.11 Notification Type

Field Name	Description	Sample Values
NotificationTypeCode	The code for the notification type.	M1
NotificationTypeDesc	The description of the notification type.	Maintenance request
DefaultRecord	Indicates if this is the default notification code.	0 or 1
Inactive	Indicates if this notification code is no longer active.	0 or 1

6.12 Asset Planning Type

Field Name	Description	Sample Values
AssetPlanningTypeId	AMT unique Id of the asset planning type.	1
AssetPlanningTypeCode	The asset planning type code.	None, Advanced
DefaultRecord	Indicates if this is the default code.	0 or 1

6.13 Equipment Class

Field Name	Description	Sample Values
EquipmentClassCode	AMT unique code for the equipment class.	MO
EquipmentClassDescription	Description of the equipment class.	Mobile
DefaultRecord	Indicates whether this equipment class is the default equipment class.	0 or 1

6.14 Equipment Group

Field Name	Description	Sample Values
EquipmentClassCode	AMT unique code for the equipment class.	MO
EquipmentGroupCode	AMT unique code for the equipment group.	WT
EquipmentGroupDescription	Description of the equipment group.	Water Truck
DefaultRecord	Indicates whether this equipment group is the default equipment group.	0 or 1

6.15 Unit Of Measure

Field Name	Description	Sample Values
ShortDescription	This is the unique code for the AMT UOM	KM
LongDescription	Description of the UOM	Kilometres
ExternalUOM	UOM code used by external systems. This may be the same as the short description.	KMS
DefaultRecord	Indicates if this UOM is the default UOM,	0 or 1
OperatingHours	Flag to indicate UOM is operating hours.	0 or 1
RevenueRate	Revenue rate for the UOM.	

6.16 Manufacturer

Field Name	Description	Sample Values
Manufacturer	Code/Name of the manufacturer. This is the unique identifier for the manufacturer in AMT.	ABB
ManufacturerDesc	Description of the manufacturer.	Power Systems
ManufacturerCode	Export Code – Short version of the manufacturer code.	AB

6.17 Labour Activity

Field Name	Description	Sample Values
ActivityCode	AMT code for labour activity.	ELEC
LabourActvity	Unique Name of the labour activity.	Electrician
ExpenseElementCode	Expense element code for labour activity.	00010042
Inactive	Indicates if the labour activity is inactive. Not yet implemented in ShowLabourActivity.	0 or 1

6.18 Cost Expense

Field Name	Description	Sample Values
CostExpenseCode	Unique AMT code for Expense Element.	666
CostExpenseDesc	Description of expense element.	Fuel Expense
DepreciationExpense	Indicates if for use in depreciation.	0 or 1
Ownership	Indicates if for use in ownership cost.	0 or 1
GlobalCostExpense	AMT Global Expense Element code.	Default
CBDExpense	Indicates if for Component Based Depreciation (different to Capital Depreciation).	0 or 1
PartsDefault	Indicates if the default expense element for parts.	0 or 1
LabourDefault	Indicates if the default expense element for labour.	0 or 1
MiscDefault	Indicates if the default expense element for miscellaneous.	0 or 1
Inactive	Indicates if Inactive.	0 or 1

6.19 User

Field Name	Description	Sample Values
OrganisationCode	The configured AMT organisation of the user.	DEFAULT
DefaultPasswordHash	Deprecated. Use Password.	
LoginName	The AMT login name for the user.	PSHAE01
RealName	The real name of the AMT user.	Peter Shae
Group	Permission Group in AMT to define user access to AMT functions.	Planners
PlanningGroup	Collection of AMT planning group codes for this user.	Mobile
Language	Language for code for the user in AMT.	English

Field Name	Description	Sample Values
EmailAddress	Email address of the user.	
Terminated	Indicator for whether the user has been terminated.	0 or 1
CostCentresAll	Indicates if the user has access to all cost centres. A value of 1 indicates access to all cost centres.	0 or 1
CostCentres	Collection of Cost Centre codes the user has access to. Only considered when CostCentresAll is false.	
AllEquipment	Indicates if the user has access to all AMT Equipment.	0 or 1
Branches	Collection of branch codes that restricts the user to only the nominated branches. Only considered when AllEquipment is false.	
Sites	Collection of site names that restricts the user to only the nominated sites. Only considered when AllEquipment is false.	Plant Hire
WorkOrderMaximumAuthority	The maximum value of a work order that the user can authorise.	100000
QuoteAuthorisationEnabled	Indicates whether this user has access to authorise quotes.	0 or 1
QuoteMaximumAuthority	Maximum value of quotes the user can authorise.	75000
QuoteMaximumDiscount	Maximum discount percent the user can give on a quote.	5.5
BudgetStatusAccessNone	Indicates if the user has access to budget status codes.	0 or 1
BudgetStatusAccess	A collection of budget status codes the user has access to.	
MessageAdministrator	Indicates if the user is a message group administrator.	0 or 1
Password	User's password.	

6.20 Planning Group

Field Name	Description	Sample Values
Code	AMT unique code for the planning group.	WASH
Description	Description of the planning group.	Wash plant group
MessageGroupCode	AMT message group for the planning group.	FP1
OrganisationCode	The configured AMT Organisation of the customer.	DEFAULT

6.21 Labour Rate

Field Name	Description	Sample Values
BranchCode	The code of the branch to apply for this labour rate.	1
LabourActivity	AMT code for labour activity.	ELEC
CurrencyCode	Code for the currency of the labour rate	USD
PayTypeCode	Code for the Pay Type of the labour rate.	Normal, Overtime
LabourRatePerHour	The hourly rate of the labour activity in the branch.	124.50

6.22 Symptom

Field Name	Description	Sample Values
SymptomCode	Unique AMT code for the symptom.	LEAK
SymptomDesc	Description of the symptom.	Leaking fluids
DefaultRecord	Indicates if the system default symptom code.	1 or 0
StrategyDefault	Indicates if the default symptom code for strategies.	1 or 0

6.23 Cause

Field Name	Description	Sample Values
CauseCode	Unique AMT code for the cause.	ABUSE
CauseDesc	Description of the cause.	Operator abuse of machinery
DefaultRecord	Indicates if the system default cause code..	1 or 0
StrategyDefault	Indicates if the default cause code for strategies.	1 or 0

6.24 Priority

Field Name	Description	Sample Values
PriorityCode	Unique AMT code for the priority.	P1
PriorityDesc	Description of the priority.	Critical Priority 1
DefaultRecord	Indicates if the system default priority code.	1 or 0
SortOrder	Sort order of priority codes to display in AMT drop-down.	1, 2, 3

6.25 Work Group

Field Name	Description	Sample Values
SiteCode	Name of the AMT Site for the work group. Note that the site code is not mandatory in AMT, so this value is the **name** of the site, and not the code of the site.	MINE
WorkGroupCode	Unique code for the Work Group in AMT.	FITTER
WorkGroupDesc	Description of the work group.	Mobile fitters
DefaultRecord	Indicates if the default work group code for the site.	0 or 1
Expired	Indicates whether the work group is no longer used.	0 or 1
TargetAllocation	Target planning allocation percentage for resource balancing.	80

6.26 Fleet

Field Name	Description	Sample Values
FleetCode	Unique code for the Fleet in AMT.	HAUL
SiteCode	Name of the AMT Site to which the fleet belongs.	Plant Hire
PricingGroupCode	Price group to use for equipment in this fleet.	DEFAULT
AvailablityCode	Code for the availability formula. Valid values are PA for Physical Availability and MA for Mechanical Availability.	PA, MA
ServiceInterval	Standard interval between services. This is used in the service accuracy report.	250
Tolerance	The percentage tolerance used to determine which services were performed within acceptable tolerance of the standard service interval.	10
EnableForecastingAvailability	Used to enable availability forecasting for the fleet.	0 for disabled and 1 for enabled
AnnualSchedulingHours	Annual scheduled hours for an equipment.	8760 (365 days @ 24 hours)
SchedulingEfficiency	A measurement of how efficient the planning process is on site. The higher the percentage, the fewer downtime events because all strategy work for a month is planned together.	80%
AvailabilityYear1	The percentage availability for an equipment in year 1.	95
AvailabilityYear2	The percentage availability for an equipment in year 2.	95
AvailabilityYear3	The percentage availability for an equipment in year 3.	95

Field Name	Description	Sample Values
AvailabilityYear4	The percentage availability for an equipment in year 4.	95
AvailabilityYear5	The percentage availability for an equipment in year 5.	95
AvailabilityYear6	The percentage availability for an equipment in year 6.	95
AvailabilityYear7	The percentage availability for an equipment in year 7.	95
AvailabilityYear8	The percentage availability for an equipment in year 8.	95
AvailabilityYear9	The percentage availability for an equipment in year 9.	95
AvailabilityYear10	The percentage availability for an equipment in years 10 onwards.	95
DefaultRecord	Indicates if this is the default fleet in AMT.	0 indicates false and 1 indicates true.

6.27 Catalogue Profile

Field Name	Description	Sample Values
Code	Code of the Catalogue Profile.	PM_UTT
Description	Description of the Catalogue Profile.	DEFAULT
Inactive	Indicates if the catalogue profile is active (0) or inactive (1).	0, 1

7 Error Handling

The following valid errors are returned from this interface.

Error Condition	Description
The provided document has an unrecognised format. Various XML format errors are returned	Check the format of the schema document against those provided. Errors can be related to well-formed XML issues, or failure to validate the document against the XSD.
The provided value for <ElementCode> does not have the correct datatype	Check datatypes of elements, especially date formats. Note that date and datetime conventions are used.
Mandatory element <ElementName> not provided	An expected XML element has not been provided.
Mandatory attribute <AttributeName> not provided	An expected XML attribute has not been provided.
The provided code for <ElementCode> does not have a corresponding AMT configuration item	AMT makes extensive use of pre-configured code lists. Relevant codes must be preconfigured prior to use of the interface.
A customer update has been requested, but no corresponding customer has been found with: CustomerNumber: <CustomerNumber>	This results when the external system tries to update a customer that does not exist in AMT yet.

The following valid warnings are returned from this interface. These affected items will still be processed.

Warning Condition	Description
Element AccountManagerEmployeeNumber has been provided but will be ignored	The employee referenced has not been marked as an account manager in AMT. The customer will be updated/created, but this field will not be used.
Element SalesResponsibilityEmployeeNumber has been provided but will be ignored	The employee referenced has not been marked as an account manager in AMT. The customer will be updated/created, but this field will not be used.

8 Integration Functions

Only fields with specific rules have been listed. All other fields should conform to the datatype rules as defined in the schema definition files and are optional.

8.1 ProcessCustomer

This interface is used to add new customers to AMT or update existing customers in AMT.

8.1.1 Business Rules

Field Name	Business Rules	Optional/ Required
CustomerNumber	This field is required and is used to determine if the customer already exists in AMT.	R
CustomerName		R
CostBearerCode	The value provided should match a configured **Cost Bearer** within AMT.	O
AccountManagerEmployeeNumber	The Employee number must be marked as **Account Manager** in the AMT Employee table; otherwise, the provided value is not used, and a warning is returned	O
SalesResponsibilityEmployeeNumber	The Employee number must be marked as **Sales Responsibility** in the AMT Employee table; otherwise, the provided value is not used, and a warning is returned	O
PriceGroupCode	The value provided should match a configured **Price Group** within AMT If no value is provided, the default Price Group of the Organisation will be used	O
OrganisationCode	If this field is not provided when creating a new customer, the default Organisation is used This field is ignored for existing customers	O
CSACustomerIndicator	Only the following values are accepted **0** – Does not have a Customer Support Agreement (CSA) **1** – Has a CSA	O
PSMIndicator	Only the following values are accepted **0** – Is not used in the Product Support Marketing (PSM) **1** – Is used in the Product Support Marketing (PSM)	O

8.1.2 Processing Rules

1. One or more customers can be included in the same message.
2. Each customer is processed individually. Failure of a single customer load is reported, and processing continues.
3. If the customer does not exist:
    a. The customer is created as a new customer.

   b. Any value against a provided optional tag is used.
   c. If an optional tag is not provided, the value is not set in AMT unless a specific business rule exists to manage this case.
4. If the customer does exist:
   a. The customer will be updated with new provided values.
   b. Any value against a provided tag will be overwritten.
   c. If no tag is provided, the existing values will remain as-is.
5. Customers can be duplicated - the customer processed last will take precedence.
6. **RespondCustomer** is returned upon completion of processing.

8.1.3 Data Structure




Figure 2 ProcessCustomer

8.2 CancelCustomer

This interface is used to remove customers from AMT. Rather than deleting the customer within AMT, the Customer Flag Delete flag is set to True.

8.2.1 Business Rules

Field Name	Business Rules	Optional/ Required
CustomerNumber	This field is used to uniquely identify a customer within AMT.	R

8.2.2 Processing Rules

1. One or more customers can be included in the same message.
2. Each customer is cancelled individually. Failure of a single customer is reported, and processing continues.
3. Customers can be duplicated within the message.
4. If the customer does exist, then the Customer Delete Flag is set to True.
5. If the customer does not exist in AMT, no further action is taken.
6. **RespondCustomer** is returned upon completion of the process.

8.2.3 Data Structure




Figure 3 CancelCustomer

8.3 GetCustomer

This interface is used to retrieve a list of customers from AMT.

8.3.1 Business Rules

Field Name	Business Rules	Optional/ Required
CustomerName	A wildcard match of the provided data will be done by AMT	O
CustomerNumber	A wildcard match of the provided data will be done by AMT	O
ParentCustomerName	A wildcard match of the provided data will be done by AMT	O

8.3.2 Data Structure




Figure 4 GetCustomer

8.4 GetModel

8.4.1 Business Rules

Field Name	Business Rules	Optional/ Required
ModelCode	A wildcard match of the provided data will be done by AMT	O
ManufacturerName	A wildcard match of the provided data will be done by AMT	O
ModelFamilyCode	A wildcard match of the provided data will be done by AMT	O

8.4.2 Processing Rules

1. Any provided fields will be matched with the existing model in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowModel** is returned upon completion of the process.

8.4.3 Data Structure




Figure 5 GetModel

8.5 GetCostCentre

This interface is used to retrieve a list of cost centres from AMT.

8.5.1 Business Rules

Field Name	Business Rules	Optional/ Required
CostCentreCode	A wildcard match of the provided data will be done by AMT	O
OrganisationCode	A wildcard match of the provided data will be done by AMT	O

8.5.2 Processing Rules

1. Any provided fields will be matched with the existing cost centre in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowCostCentre** is returned upon completion of the process

8.5.3 Data Structure




Figure 6 GetCostCentre

8.6 GetSupplier

This interface is used to retrieve a list of suppliers from AMT.

8.6.1 Business Rules

Field Names	Business Rules	Optional/ Required
SupplierCode	A wildcard match of the provided data will be done by AMT	O
BranchCode	A wildcard match of the provided data will be done by AMT	O
SiteCode	A wildcard match of the provided data will be done by AMT	O
RegionCode	A wildcard match of the provided data will be done by AMT	O
OrganisationCode	A wildcard match of the provided data will be done by AMT	O

8.6.2 Processing Rules

1. Any provided fields will be matched with the existing supplier in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowSupplier** is returned upon completion of the process.

8.6.3 Data Structure




Figure 7 GetSupplier

8.7 GetCurrency

This interface is used to retrieve a list of currencies from AMT.

8.7.1 Business Rules

Field Names	Business Rules	Optional/ Required
CurrencyCode	A wildcard match of the provided data will be done by AMT	O
CurrencyDescription	A wildcard match of the provided data will be done by AMT	O

8.7.1 Processing Rules

1. Any provided fields will be matched with existing currency in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND
4. **ShowCurrency** is returned upon completion of the process

8.7.2 Data Structure




Figure 8 GetCurrency

8.8 GetOrganisation

This interface is used to retrieve a list of organisations from AMT.

8.8.1 Business Rules

Field Names	Business Rules	Optional/ Required
OrganisationCode	A wildcard match of the provided data will be done by AMT	O
OrganisationName	A wildcard match of the provided data will be done by AMT	O

8.8.2 Processing Rules

1. Any provided fields will be matched with an existing organisation in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowOrganisation** is returned upon completion of the process.

8.8.3 Data Structure




Figure 9 GetOrganisation

8.9 GetCostBearer

This interface is used to retrieve a list of cost bearers from AMT.

8.9.1 Business Rules

Field Names	Business Rules	Optional/ Required
CostBearerCode	A wildcard match of the provided data will be done by AMT	O
CostBearerName	A wildcard match of the provided data will be done by AMT	O

8.9.2 Processing Rules

1. Any provided fields will be matched with the existing cost bearer in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowCostBearer** is returned upon completion of the process.

8.9.3 Data Structure




Figure 10 GetCostBearer

8.10 GetSourceOfSupply

This interface is used to retrieve a list of Source of Supply codes and descriptions from AMT.

8.10.1 Business Rules

Field Names	Business Rules	Optional/ Required
SourceOfSupplyCode	A wildcard match of the provided data will be done by AMT	O
SourceOfSupplyDescription	A wildcard match of the provided data will be done by AMT	O

8.10.2 Processing Rules

1. Any provided fields will be matched with an existing source of supply in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowSourceOfSupply** is returned upon completion of the process.

8.10.3 Data Structure




Figure 11 GetSourceOfSupply

8.11 GetPartType

This interface is used to retrieve a list of part types from AMT.

8.11.1 Business Rules

Field Names	Business Rules	Optional/ Required
PartTypeCode	A wildcard match of the provided data will be done by AMT	O
PartTypeDescription	A wildcard match of the provided data will be done by AMT	O
GlobalPartTypeCode	A wildcard match of the provided data will be done by AMT	O

8.11.2 Processing Rules

1. Any provided fields will be matched with the existing part type in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowPartType** is returned upon completion of the process

8.11.3 Data Structure




Figure 12 GetPartType

8.12 ProcessNotificationType

This interface is used to add new notification types to AMT or update existing notification types in AMT.

8.12.1 Business Rules

Field Names	Business Rules	Optional/ Required
NotificationTypeCode	This field is required and is used to determine if the notification type already exists in AMT.	R
NotificationTypeDescription		R
DefaultRecord	Only the following values are accepted: **0** – Is not the default notification type in AMT **1** – Is the default notification type in AMT	O
Inactive	Only the following values are accepted: **0** – The notification type is active in AMT **1** – The notification type is inactive in AMT	O

8.12.2 Processing Rules

1. One or more notification types can be included in the same message.
2. Each notification type is processed individually. Failure of a single notification load is reported, and processing continues.
3. **RespondNotificationType** is returned upon completion of processing.

8.12.3 Data Structure




Figure 13 ProcessNotificationType

8.13 GetAssetPlanningType

This interface is used to retrieve a list of asset planning types from AMT.

8.13.1 Business Rules

Field Names	Business Rules	Optional/ Required
AssetPlanningTypeCode	A wildcard match of the provided data will be done by AMT	O

8.13.2 Processing Rules

1. Any provided fields will be matched with existing planning type codes in AMT.
2. All items within a list element are considered as a logical OR.
3. **ShowAssetPlanningType** is returned upon completion of the process.

8.13.3 Data Structure




Figure 14 GetAssetPlanningType

8.14 ProcessCostCentre

This interface is used to add new notification types to AMT or update existing notification types in AMT.

8.14.1 Business Rules

Field Names	Business Rules	Optional/ Required
CostcentreID	This is not used if provided. The ID is an internal AMT ID and is maintained by AMT.	CostcentreID
CostCentreCode	This field is required and is used to determine if the Cost Centre Code already exists in AM.	CostCentreCode
CostCentreDescription		CostCentreDescription
OrganisationCode	Must be a valid AMT organisation Code If this field is not provided when creating a new customer, then the default Organisation is used.	OrganisationCode

Field Names	Business Rules	Optional/ Required
CBD	Only the following values are accepted **0** – Cost Centre is not for use with CBD **1** – Cost Centre is for use with CBD	CBD

8.14.2 Processing Rules

1. One or more cost centres can be included in the same message.
2. Each cost centre is processed individually. Failure of a single cost centre load is reported, and processing continues.
3. **RespondCostCentre** is returned upon completion of processing.

8.14.3 Data Structure




Figure 15 ProcessCostCentre

8.15 GetEquipmentClass

This interface is used to retrieve a list of equipment classes from AMT.

8.15.1 Business Rules

Field Names	Business Rules	Optional/ Required
EquipmentClassCode	Must be a valid AMT Equipment Class code	O
EquipmentClassDescription	A wildcard match of the provided data will be done by AMT.	O
Default	Only the following values are accepted **0** – Returns non-default equipment classes **1** – Returns the default equipment class	O

8.15.2 Processing Rules

1. Any provided fields will be matched with existing equipment class codes in AMT.
2. All items within a list element are considered as a logical OR.
3. **ShowEquipmentClass** is returned upon completion of the process

8.15.3 Data Structure




Figure 16 GetEquipmentClass

8.16 GetEquipmentGroup

This interface is used to retrieve a list of equipment groups from AMT.

8.16.1 Business Rules

Field Names	Business Rules	Optional/ Required
EquipmentClassCode	Must be a valid AMT Equipment Class code.	O
EquipmentGroupCode	Must be a valid AMT equipment group.	O
EquipmentGroupDescription	A wildcard match of the provided data will be done by AMT.	O
Default	Only the following values are accepted **0** – Returns non--default equipment groups **1** – Returns the default equipment group	O

8.16.2 Processing Rules

1. Any provided fields will be matched with existing equipment groups in AMT.
2. All items within a list element are considered as a logical OR.
3. **ShowEquipmentGroup** is returned upon completion of the process.

8.16.3 Data Structure




Figure 17 GetEquipmentGroup

8.17 ProcessEquipmentClass

This interface is defined in the adapter XSD, but has yet to be implemented.

8.18 ProcessEquipmentGroup

This interface is used to add equipment groups or update existing equipment groups in AMT.

8.18.1 Business Rules

It is necessary to create equipment class codes in AMT before creating Equipment group codes.

Technical fields, which can form part of the Equipment Group configuration in AMT, are currently excluded from the adapter.

Field Names	Business Rules	Optional/ Required
EquipmentClassCode	Must be a valid AMT Equipment Group.	R
EquipmentGroupCode	Must be a valid AMT equipment group. This is used to uniquely identify the Equipment Group in AMT	R
EquipmentGroupDescription		R
Default	Only the following values are accepted **0** – Indicates this is not the default equipment group **1** – Indicates this is the default equipment group	R

8.18.2 Processing Rules

1. One or more equipment groups can be included in the same message.
2. Each equipment group is processed individually. Failure of a single equipment group load is reported, and processing continues.
3. If the equipment group does not exist in AMT, it will be created. If the equipment group does exist, the details will be updated.
4. If there is an existing default equipment group, an error will be returned when setting a different equipment group as the default. It will be necessary to set the existing default equipment to not be the default before setting the new equipment group to the default.
5. **RespondEquipmentGroup** is returned upon completion of processing.

8.18.3 Data Structure




Figure 18 ProcessEquipmentGroup

8.19 ProcessUnitOfMeasure

This interface is used to add units of measure or update existing units of measure in AMT.

8.19.1 Business Rules

Field Names	Business Rules	Optional/ Required
ShortDescription	This is the unit of measure code as seen in AMT. This field is used to uniquely identify the unit of measure in AMT.	R
ExternalUOM	A wildcard match of the provided data will be done by AMT.	R
DefaultRecord	When creating a unit of measure, if no value is provided, a value of 0 is assumed. Only the following values are accepted: **0** – Indicates this is not the default unit of measure **1** – Indicates this is the default unit of measure	O
OperatingHours	Only the following values are accepted: **0** – Indicates this is not operating hours **1** – Indicates this is operating hours If no value is provided, a value of 0 is assumed.	O

8.19.2 Processing Rules

1. One or more units of measure can be included in the same message.
2. Each unit of measure is processed individually. Failure of a single unit of measure load is reported, and processing continues.
3. If the unit of measure does not exist in AMT it will be created. If the unit of measure does exist, the details will be updated.
4. **RespondUnitOfMeasure** is returned upon completion of processing.

8.19.3 Data Structure




Figure 19 ProcessUnitOfMeasure

8.20 GetManufacturer

This list is used to retrieve a list of manufacturers from AMT.

8.20.1 Business Rules

Field Names	Business Rules	Optional/ Required
Manufacturer	Must be a valid AMT Manufacturer code	O
ManufacturerDesc	A case-insensitive wildcard match will be performed.	O
ManufacturerCode	A case-insensitive wildcard match will be performed.	O

8.20.2 Processing Rules

1. Any provided fields will be matched with existing manufacturers in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowManufacturer** is returned upon completion of the process.

8.20.3 Data Structure




Figure 20 **GetManufacturer**

8.21 ProcessManufacturer

This interface is used to add manufacturers or update existing manufacturers in AMT.

8.21.1 Business Rules

Field Names	Business Rules	Optional/ Required
Manufacturer	Unique Manufacturer code in AMT. This field is used to identify if the manufacturer already exists in AMT.	R
ManufacturerDesc		R
ManufacturerCode		R

8.21.2 Data Structure




Figure 21 ProcessManufacturer

8.22 GetLabourActivity

This interface is used to retrieve a list of labour activities from AMT.

8.22.1 Business Rules

Field Names	Business Rules	Optional/ Required
ActivityCode	Must be a valid Activity Code.	O
LabourActivity	A case-insensitive wildcard match will be performed.	O
ExpenseElementCode	A case-insensitive wildcard match will be performed.	O

8.22.2 Processing Rules

1. Any provided fields will be matched with existing labour activities in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowLabourActivity** is returned upon completion of the process

8.22.3 Data Structure




Figure 22 GetLabourActivity

8.23 ProcessLabourActivity

This interface is used to add labour activities or update existing labour activities in AMT.

8.23.1 Business Rules

Field Names	Business Rules	Optional/ Required
ActivityCode	Labour activity code in AMT.	R
LabourActivity	Unique name of the Labour Activity in AMT. This field is used to identify if the labour activity already exists in AMT.	R
ExpenseElementCode	Must be a valid AMT Expense Element Code If StandardJobExpenseAllocations are enabled, and there is no default expense element defined for labour activities, this field will be mandatory.	O
Inactive	Only the following values are accepted 0 – Indicates this is an active labour activity 1 – Indicates this is an inactive labour activity If no value is provided when creating a labour activity, a value of 0 is assumed.	O

8.23.2 Processing Rules

1. One or more labour activities can be included in the same message.
2. Each labour activity is processed individually. Failure of a single labour activity load is reported, and processing continues.
3. If the labour activity does not exist in AMT, it will be created. If the labour activity does exist, the details will be updated.
4. **RespondLabourActivity** is returned upon completion of processing.

8.23.3 Data Structure




Figure 23 ProcessLabourActivity

8.24 ProcessCostExpense

This interface is used to add expense elements or update existing expense elements.

8.24.1 Business Rules

Field Name	Business Rule	Optional/ Required
CostExpenseCode	Unique expense element code in AMT. This field is used to identify if the expense element already exists in AMT.	R
CostExpenseDesc		R
DepreciationExpense		O
Ownership	Only the following values are accepted: **0** – Indicates the expense element is not for Ownership costs **1** – Indicates the expense element is for Ownership costs If no value is provided when creating a new expense element, a value of 0 is assumed.	O
GlobalCostExpense	Must be a valid AMT Global Expense Element	O
CBDExpense	Only the following values are accepted: **0** – Indicates expense element is not for CBD **1** – Indicates expense element is for CBD If no value is provided when creating a new expense element, a value of 0 is assumed.	O
PartsDefault	Only the following values are accepted: **0** – Indicates this is not the default expense element for parts. **1** – Indicates this is the default expense element for parts. If no value is provided when creating a new expense element, a value of 0 is assumed.	O
LabourDefault	Only the following values are accepted: **0** – Indicates this is not the default expense element for labour **1** – Indicates this is the default expense element for labour If no value is provided when creating a new expense element, a value of 0 is assumed.	O
MiscDefault	Only the following values are accepted: **0** – Indicates this is not the default expense element for misc **1** – Indicates this is the default expense element for misc If no value is provided when creating a new expense element, a value of 0 is assumed	O
Inactive	Only the following values are accepted 0 – Indicates the expense element is active 1 – Indicates the expense element is not active If no value is provided when creating a new expense element, a value of 0 is assumed.	

8.24.2 Processing Rules

1. One or more expense elements can be included in the same message.
2. Each expense element is processed individually. Failure of a single expense element load is reported, and processing continues.
3. If the expense element does not exist in AMT, it will be created. If the expense element does exist, the details will be updated.
4. **RespondCostExpense** is returned upon completion of processing.

8.24.3 Data Structure




Figure 24 ProcessCostExpense

8.25 ProcessUser

This interface is used to add users or update existing users in AMT.

8.25.1 Business Rules

Field Name	Business Rule	Optional/ Required
OrganisationCode	Must be a valid AMT organisation code. If no code is supplied, the default organisation code will be used.	O
LoginName	This is a required field and is the field used to identify whether the user exists in AMT.	R
RealName		R
Group	Must be a valid AMT Group Permission code.	R
PlanningGroup	Must be a valid AMT Planning Group code.	O

Field Name	Business Rule	Optional/ Required
Language	Must be a valid AMT Language Type code.	R
Terminated	Only the following values are accepted: **0** - Indicates the user is active **1** – Indicates the user is terminated	O
CostCentresAll	Only the following values are accepted: **0** – Indicates the user does not have access to all cost centres. It will be necessary to populate CostCentres when this is 0. **1** – Indicates the user does have access to all cost centres.	O
CostCentres	Must be a valid AMT Cost Center code: Multiple cost centres can be sent in the message by repeating the tags. • Is a required field when CostCentresAll is **0** • Is ignored if CostCentresAll is **1**	O
AllEquipment	Only the following values are accepted: **0** – Indicates the user does not have access to all equipment. It will be necessary to specify either **Branches** or **Sites** when this is 0. **1** – Indicates the user does have access to all equipment.	O
Branches	Only applicable when AllEquipment is **0**. If specifying branch codes, it is not possible to specify Sites. Must be a valid AMT Branch code.. Multiple branches can be sent in the message by repeating the tag.	O
Sites	Only applicable when AllEquipment is **0**. If specifying Site codes, it is not possible to specify Branches. Must be a valid AMT Site name. Multiple sites can be sent in the message by repeating the tags.	O
QuoteAuthorisationEnabled	Only the following values are accepted: 0 – indicates the user is not enabled for quote authorisation 1 – Indicates the user is enabled for quote authorisation	O
BudgetStatusAccessNone	Only the following values are accepted: **0** – Indicates th\e user has access to Budget Status codes **1** – Indicates the user has no access to Budget Status It will be necessary to specify BudgetStatusAccess when this is set to **0**	O
BudgetStatusAccess	Only applicable when BudgetStatusAccessNone is 0. Must be a valid AMT Budget Status Code. Multiple codes can be sent in the message by repeating the tags.	O
MessageAdministator	Only the following values are accepted: **0** – Indicates the user is not a message group administrator **1** – Indicates the user is a message group administrator	O

8.25.2 Processing Rules

1. One or more users can be included in the same message.
2. Each user is processed individually. Failure of a user load is reported, and processing continues.
3. If the user does not exist in AMT, it will be created. If the user does exist, the details will be updated.
4. **RespondUser** is returned upon completion of processing.

8.25.3 Data Structure




Figure 25 ProcessUser

8.26 ProcessPlanningGroup

This interface is used to add planning groups or update existing planning groups in AMT.

8.26.1 Business Rules

Field Name	Business Rule	Optional/ Required
Code	This is a required field and is the field used to identify whether the planning group exists in AMT.	R
Description		R
MessageGroupCode	Must be a valid AMT Message Group.	O
OrganisationCode	Must be a valid AMT Organisation Code. If no value is supplied when creating a new Planning Group, the default organisation code will be used.	O

8.26.2 Processing Rules

1. One or more planning groups can be included in the same message.
2. Each planning group is processed individually. Failure of a planning group load is reported, and processing continues.
3. If the planning group does not exist in AMT, it will be created. If the planning group does exist, the details will be updated.
4. **RespondPlanningGroup** is returned upon completion of processing.

8.26.3 Data Structure




Figure 26 ProcessPlanningGroup

8.27 ProcessLabourRate

This interface is used to add labour rates or update existing labour rates in AMT.

8.27.1 Business Rules

Field Name	Business Rule	Optional/ Required
BranchCode	Must be a valid AMT Branch Code.	R
LabourActivity	Must be a valid AMT Labour Activity code.	R
CurrencyCode	Must be a valid AMT Currency Code.	R
PayTypeCode	Must be a valid AMT Pay Type Code.	R

8.27.2 Processing Rules

1. One or more labour rates can be included in the same message.
2. Each labour rate is processed individually. Failure of a labour rate load is reported, and processing continues.
3. If the labour rate does not exist in AMT, it will be created. If the labour rate does exist, the details will be updated.
4. **RespondLabourRate** is returned upon completion of processing.

8.27.3 Data Structure




Figure 27 ProcessLabourRate

8.28 ProcessSymptom

This interface is used to add symptom codes or update existing symptom codes in AMT.

8.28.1 Business Rules

Field Name	Business Rule	Optional/ Required
SymptomCode	This is a required field and is the field used to identify whether the symptom code exists in AMT.	R
SymptomDesc		R
DefaultRecord	Only the following values are accepted: **0** – Indicates the symptom code is not the system default **1** – Indicates the symptom code is the system default If no value is provided when creating a new symptom code, a value of 0 is assumed.	O
StrategyDefault	Only the following values are accepted: **0** – Indicates the symptom code is not the strategy default **1** – Indicates the symptom code is the strategy default If no value is provided when creating a new symptom code, a value of 0 is assumed.	O

8.28.2 Processing Rules

1. One or more symptoms can be included in the same message.
2. Each symptom is processed individually. Failure of a symptom load is reported, and processing continues.
3. If the symptom does not exist in AMT, it will be created. If the symptom does exist, the details will be updated.
4. **RespondSymptom** is returned upon completion of processing.

8.28.3 Data Structure




Figure 28 ProcessSymptom

8.29 ProcessCause

This interface is used to add cause codes or update existing cause codes in AMT.

8.29.1 Business Rules

Field Name	Business Rule	Optional/ Required
CauseCode	This is a required field and is the field used to identify whether the cause code exists in AMT.	R
CauseDesc		R
DefaultRecord	Only the following values are accepted: **0** – Indicates the cause code is not the system default. **1** – Indicates the cause code is the system default If no value is provided when creating a new cause code, a value of 0 is assumed.	O
StrategyDefault	Only the following values are accepted: **0** – Indicates the cause code is not the strategy default **1** – Indicates the cause code is the strategy code If no value is provided when creating a new cause code, a value of 0 is assumed.	O

8.29.2 Processing Rules

1. One or more causes can be included in the same message.
2. Each cause is processed individually. Failure of a cause load is reported, and processing continues.
3. If the cause does not exist in AMT, it will be created. If the cause does exist, the details will be updated.
4. **RespondCause** is returned upon completion of processing.

8.29.3 Data Structure




Figure 29 ProcessCause

8.30 ProcessPriority

This interface is used to add priority codes or update existing priority codes in AMT.

8.30.1 Business Rules

This interface is used to add priority codes or update existing priority codes in AMT.

Field Name	Business Rule	Optional/ Required
PriorityCode	This is a required field and is the field used to identify whether the cause code exists in AMT.	R
DefaultRecord	Only the following values are accepted: **0** – Indicates the priority code is not the system default **1** – Indicates the priority code is the system default If no value is provided when creating a new cause code, a value of 0 is assumed.	O
StrategyDefault	Only the following values are accepted: **0** – Indicates the cause code is not the strategy default **1** – Indicates the cause code is the strategy default If no value is provided when creating a new cause code, a value of 0 is assumed.	O

8.30.2 Processing Rules

1. One or more priorities can be included in the same message.
2. Each priority is processed individually. Failure of a priority load is reported, and processing continues.
3. If the priority does not exist in AMT, it will be created. If the priority does exist, the details will be updated.
4. **RespondPriority** is returned upon completion of processing.

8.30.3 Data Structure




Figure 30 ProcessPriority

8.31 ProcessWorkGroup

This interface is used to add work groups or update existing work groups in AMT.

8.31.1 Business Rules

Field Name	Business Rule	Optional/ Required
SiteCode	Must be a valid site name in AMT (use the name of the site, not the code of the site).	R
WorkGroupCode	This is a required field and is the field used to identify whether the work group code exists for the site in AMT.	R
WorkGroupDesc		R
DefaultRecord	Only the following values are accepted: 0 – Indicates the work group is not the default for this site 1 – Indicates the work group is the default for this site If no value is provided when creating a new work group, a value of 0 is assumed.	O
Expired	Only the following values are accepted: 0 – Indicates the work group is not expired for this site 1 – Indicates the work group has expired for this site If no value is provided when creating a new work group, a value of 0 is assumed.	O
TargetAllocation		R

8.31.2 Processing Rules

1. One or more work groups can be included in the same message.
2. Each work group is processed individually. The failure of a work group load is reported, and processing continues.
3. If the work group does not exist for the site in AMT, it will be created. If the work group does exist for the site, the details will be updated.
4. **RespondWorkGroup** is returned upon completion of processing.

8.31.3 Data Structure




Figure 31 ProcessWorkGroup

8.32 ProcessModel

This interface is used to add Models to AMT, or update existing Models in AMT.

8.32.1 Business Rules

Field Name	Business Rule	Optional/ Required
ModelId	ModelID is not used in any processing for the ProcessModel Function.	O
ModelCode	This is a required field and is the field used to identify whether the Model Code exists in AMT.	R
ModelDescription	Free format text. This is a required field when creating a new Model.	O
ManufacturerName	Must be a valid Manufacturer Name in AMT. Required when creating a new Model.	O
ModelFamilyCode	Must be a valid Model Family Code (Equipment Group) in AMT. Required when creating a new Model.	O

8.32.2 Processing Rules

1. One or more Models can be included in the same message.
2. Each Model is processed individually. Failure of a Model load is reported, and processing continues.
3. If ReferenceProcessModelInsertMode is 0:
   - If the Model does not exist in AMT, it will be created.
   - If the Model does exist, the details will be updated.

   If the ReferenceProcessModelInsertMode is 1:
   - If the Model does not exist in AMT, it will be created.
   - If the Model does exist, the details will not be updated. A warning will be returned.
4. **RespondModel** is returned upon completion of processing.

8.32.3 Data Structure




Figure 32 ProcessModel

8.33 ProcessFleet

This interface is used to add Fleets or update existing Fleets in AMT.

8.33.1 Business Rules

Field Name	Business Rule	Optional/ Required
FleetCode	This is a required field and is the field used to identify whether the Fleet Code exists in AMT.	R
SiteCode	Must be a valid Site name in AMT. Required when creating a new Fleet.	O

Field Name	Business Rule	Optional/ Required
PricingGroupCode	Must be a valid Price Group Code in AMT. Required when creating a new Fleet. If AMT configuration is hiding the PricingGroupCode in AMT, use a value of 'DEFAULT' in the message.	O
AvailabilityCode	Must be a valid Availability Code in AMT. Required when creating a new Fleet. Valid values are: PA – Indicates Physical Availability MA – Indicates Mechanical Availability If the AMT configuration is hiding the Availability Type code in AMT, use a value of 'PA' in the message.	O
ServiceInterval	Must be a valid number greater than 0. Required when creating a new Fleet.	O
Tolerance	Must be a valid number greater than 0. Required when creating a new Fleet.	O
EnableForecastingAvailability	Only the following values are accepted: 0 – Do not enable forecasting availability. 1 – Enable forecasting availability. If no value is provided when creating a fleet, a value of 0 is assumed.	O
AnnualSchedulingHours	Must be a numeric value greater than or equal to 0.	O
SchedulingEfficiency	Must be a numeric value between 0 and 100.	O
AvailabilityYear1	Must be a numeric value between 0 and 100.	O
AvailabilityYear2	Must be a numeric value between 0 and 100.	O
AvailabilityYear3	Must be a numeric value between 0 and 100.	O
AvailabilityYear4	Must be a numeric value between 0 and 100.	O
AvailabilityYear5	Must be a numeric value between 0 and 100.	O
AvailabilityYear6	Must be a numeric value between 0 and 100.	O
AvailabilityYear7	Must be a numeric value between 0 and 100.	O
AvailabilityYear8	Must be a numeric value between 0 and 100.	O
AvailabilityYear9	Must be a numeric value between 0 and 100.	O
AvailabilityYear10	Must be a numeric value between 0 and 100.	O
DefaultRecord	Only the following values are accepted: 0 – Indicates the Fleet is not the default Fleet 1 – Indicates the Fleet is the default Fleet If no value is provided when creating a fleet, a value of 0 is assumed.	O

8.33.2 Processing Rules

1. One or more Fleets can be included in the same message.
2. Each Fleet is processed individually. Failure of a Fleet load is reported, and processing continues.
3. If ReferenceProcessFleetInsertMode = 0
   - If the Fleet does not exist in AMT, it will be created.
   - If the Fleet does exist, the details will be updated.
4. If ReferenceProcessFleetInsertMode = 1
   - If the Fleet does not exist in AMT, it will be created.
   - If the Fleet does exist, the details will not be updated. A warning will be returned.
5. Sending a different site code in the message to the site code on a fleet in AMT will cause the site code for the fleet in AMT to be updated with the new site code in the message.
6. **RespondFleet** is returned upon completion of processing.

8.33.3 Data Structure




Figure 33 ProcessFleet

8.34 ProcessCatalogueProfile

This interface is used to add Catalogue Profiles or update existing Catalogue Profiles in AMT.

8.34.1 Business Rules

Field Name	Business Rule	Optional/ Required
Code	This is a required field, and is the field used to identify whether the Catalogue Profile exists in AMT.	R
Inactive	Only the following values are accepted: 0 – Indicates the Catalogue Profile is Active 1 – Indicates the Catalogue Profile is Inactive If no value is provided when creating a Catalogue Profile, a value of 0 is assumed.	O

8.34.2 Processing Rules

1. One or more Catalogue Profiles can be included in the same message.
2. Each Catalogue Profile is processed individually. Failure of a Catalogue Profile load is reported, and processing continues.
3. If the Catalogue Profile does not exist in AMT, it will be created. If the Catalogue Profile does exist, the details will be updated.
4. **RespondCatalogueProfile** is returned upon completion of processing.

8.34.3 Data Structure




Figure 34 ProcessCatalogueProfile

8.35 GetSymptom

This interface is used to retrieve a list of symptom codes from AMT.

8.35.1 Business Rules

Field Names	Business Rules	Optional/ Required
SymptomCode	Must be a valid Symptom Code.	O
LastModifiedDateUTC	Only Symptom codes modified after this date will be returned in the response message..	O

8.35.2 Processing Rules

1. Any provided fields will be matched with existing Symptom codes in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowSymptom** is returned upon completion of the process.

8.35.3 Data Structure




Figure 35 GetSymptom

8.36 GetCause

This interface is used to retrieve a list of cause codes from AMT.

8.36.1 Business Rules

Field Names	Business Rules	Optional/ Required
CauseCode	Must be a valid Cause Code.	O
LastModifiedDateUTC	Only cause codes modified after this date will be returned in the response message.	O

8.36.2 Processing Rules

1. Any provided fields will be matched with existing Cause codes in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowCause** is returned upon completion of the process.

8.36.3 Data Structure




Figure 36 GetCause

8.37 GetWorkGroup

This interface is used to retrieve a list of work groups from AMT.

8.37.1 Business Rules

Field Names	Business Rules	Optional/ Required
SiteCode	Must be a valid site code.	O
WorkGroupCode	Must be a valid work group code.	O
LastModifiedDateUTC	Only cause codes modified after this date will be returned in the response message	O

8.37.2 Processing Rules

1. Any provided fields will be matched with existing codes in AMT.
2. All items within a list element are considered as a logical OR.
3. Each list is considered as a logical AND.
4. **ShowWorkGroup** is returned upon completion of the process.

8.37.3 Data Structure




Figure 37 GetWokGroup

9 Response Formats

9.1 Respond Customer

This payload is returned in response to the following interfaces:

- ProcessCustomer
- Cancel Customer

9.1.1 Data Structure




Figure 38 RespondCustomer

9.2 ShowCustomer

This payload is returned in response to the following interfaces:

- GetCustomer

9.2.1 Data Structure




Figure 39 ShowCustomer

Note: The Customer data structure is the same as in ProcessCustomer above.

Breaking change

In versions prior to 2.0.10, the CostBearerCode field was populated with the AMT Cost Bearer Description field. In versions 2.0.10 and above, the actual Cost Bearer Code value is returned.

9.3 ShowModel

This payload is returned in response to the following interfaces:

- GetModel

9.3.1 Data Structure




Figure 40 ShowModel

9.4 ShowCostCentre

This payload is returned in response to the following interfaces:

- GetCostCentre

9.4.1 Data Structure




Figure 41 ShowCostCentre

9.5 ShowSupplier

This payload is returned in response to the following interfaces:

- GetSupplier

9.5.1 Data Structure




Figure 42 ShowSupplier

9.6 ShowCurrency

This payload is returned in response to the following interfaces:

- GetCurrency

9.6.1 Data Structure




Figure 43 ShowCurrency

9.7 ShowOrganisation

This payload is returned in response to the following interfaces:

- GetOrganisation

9.7.1 Data Structure




Figure 44 ShowOrganisation

9.8 ShowCostBearer

This payload is returned in response to the following interfaces:

- GetCostBearer

9.8.1 Data Structure




Figure 45 ShowCostBearer

9.9 ShowSourceOfSupply

This payload is returned in response to the following interfaces:

- GetSourceOfSupply

9.9.1 Data Structure




Figure 46 ShowSourceOfSupply

9.10 ShowPartType

This payload is returned in response to the following interfaces:

- GetPartType

9.10.1 Data Structure




Figure 47 ShowPartType

9.11 RespondNotificationType

This payload is returned in response to the following interfaces:

- ProcessNotificationType

9.11.1 Data Structure




Figure 48 RespondNotificationType

9.12 ShowAssetPlanningType

This payload is returned in response to the following interfaces:

- GetAssetPlanningType

9.12.1 Data Structure




Figure 49 ShowAssetPlanningType

9.13 RespondCostCentre

This payload is returned in response to the following interfaces:

- ProcessCostCentre

9.13.1 Data Structure




Figure 50 RespondCostCentre

9.14 ShowEquipmentClass

This payload is returned in response to the following interfaces:

- GetEquipmentClass

9.14.1 Data Structure




Figure 51 ShowEquipmentClass

9.15 ShowEquipmentGroup

This payload is returned in response to the following interfaces:

- GetEquipmentGroup

9.15.1 Data Structure




Figure 52 ShowEquipmentGroup

9.16 RespondEquipmentGroup

This payload is returned in response to the following interfaces:

- ProcessEquipmentGroup

9.16.1 Data Structure




Figure 53 RespondEquipmentGroup

9.17 RespondUnitOfMeasure

This payload is returned in response to the following interfaces:

- ProcessUnitOfMeasure

9.17.1 Data Structure




Figure 54 RespondUnitOfMeasure

9.18 ShowManufacturer

This payload is returned in response to the following interfaces:

- GetManufacturer

9.18.1 Data Structure




Figure 55 ShowManufacturer

9.19 RespondManufacturer

This payload is returned in response to the following interfaces:

- ProcessManufacturer

9.19.1 Data Structure




Figure 56 RespondManufacturer

9.20 ShowLabourActivity

This payload is returned in response to the following interfaces:

- GetLabourActivity

9.20.1 Data Structure




Figure 57 ShowLabourActivity

9.21 RespondLabourActivity

This payload is returned in response to the following interfaces:

- ProcessLabourActivity

9.21.1 Data Structure




Figure 58 RespondLabourActivity

9.22 RespondCostExpense

This payload is returned in response to the following interfaces:

- ProcessCostExpense

9.22.1 Data Structure




Figure 59 RespondCostExpense

9.23 RespondUser

This payload is returned in response to the following interfaces:

- ProcessUser

9.23.1 Data Structure




Figure 60 RespondUser

9.24 RespondPlanningGroup

This payload is returned in response to the following interfaces:

- ProcessPlanningGroup

9.24.1 Data Structure




Figure 61 RespondPlanningGroup

9.25 RespondLabourRate

This payload is returned in response to the following interfaces:

- ProcessLabourRate

9.25.1 Data Structure




Figure 62 RespondLabourRate

9.26 RespondSymptom

This payload is returned in response to the following interfaces:

- ProcessSymptom

9.26.1 Data Structure




Figure 63 RespondSymptom

9.27 RespondCause

This payload is returned in response to the following interfaces:

- ProcessCause

9.27.1 Data Structure




Figure 64 RespondCause

9.28 RespondPriority

This payload is returned in response to the following interfaces:

- ProcessPriority

9.28.1 Data Structure




Figure 65 RespondPriority

9.29 RespondWorkGroup

This payload is returned in response to the following interfaces:

- ProcessWorkGroup

9.29.1 Data Structure




Figure 66 RespondWorkGroup

9.30 RespondModel

This payload is returned in response to the following interfaces:

- ProcessModel

9.30.1 Data Structure




Figure 67 RespondModel

9.31 RespondFleet

This payload is returned in response to the following interfaces:

- ProcessFleet

9.31.1 Data Structure




Figure 68 RespondFleet

9.32 RespondCatalogueProfile

This payload is returned in response to the following interfaces:

- ProcessCatalogueProfile

9.32.1 Data Structure




Figure 69 RespondCatalogueProfile

9.33 ShowSymptom

This payload is returned in response to the following interfaces:

- GetSymptom

9.33.1 Data Structure




Figure 70 ShowSymptom

9.34 ShowCause

This payload is returned in response to the following interfaces:

- GetCause

9.34.1 Data Structure




Figure 71 ShowCause

9.35 ShowWorkGroup

This payload is returned in response to the following interfaces:

- GetWorkGroup

9.35.1 Data Structure




Figure 72 ShowWorkGroup