TopogrElow

TensorFlow API r1.4

tf.contrib.rnn.BasicLSTMCell

Contents

Class BasicLSTMCell

Aliases:

Properties

activity_regularizer

Class BasicLSTMCell

Inherits From: RNNCe11

Aliases:

- Class tf.contrib.rnn.BasicLSTMCell
- Class tf.nn.rnn_cell.BasicLSTMCell

Defined in tensorflow/python/ops/rnn_cell_impl.py.

See the guide: RNN and Cells (contrib) > Core RNN Cells for use with TensorFlow's core RNN methods

Basic LSTM recurrent network cell.

The implementation is based on: http://arxiv.org/abs/1409.2329.

We add forget_bias (default: 1) to the biases of the forget gate in order to reduce the scale of forgetting in the beginning of the training.

It does not allow cell clipping, a projection layer, and does not use peep-hole connections: it is the basic baseline.

For advanced models, please use the full **tf.nn.rnn_cell.LSTMCell** that follows.

Properties

activity_regularizer

Optional regularizer function for the output of this layer.

dtype

graph

input

Retrieves the input tensor(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer.

Returns:

Input tensor or list of input tensors.

Raises:

• AttributeError: if the layer is connected to more than one incoming layers.

Raises:

- RuntimeError: If called in Eager mode.
- AttributeError: If no inbound nodes are found.

input_shape

Retrieves the input shape(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer, or if all inputs have the same shape.

Returns:

Input shape, as an integer shape tuple (or list of shape tuples, one tuple per input tensor).

Raises:

- AttributeError: if the layer has no defined input_shape.
- RuntimeError: if called in Eager mode.

losses

name

non_trainable_variables

non_trainable_weights

output

Retrieves the output tensor(s) of a layer.

Only applicable if the layer has exactly one output, i.e. if it is connected to one incoming layer.

Returns:

Output tensor or list of output tensors.

Raises:

- AttributeError: if the layer is connected to more than one incoming layers.
- RuntimeError: if called in Eager mode.

Retrieves the output shape(s) of a layer.
Only applicable if the layer has one output, or if all outputs have the same shape.
Returns:
Output shape, as an integer shape tuple (or list of shape tuples, one tuple per output tensor).
Raises:
AttributeError: if the layer has no defined output shape.
RuntimeError: if called in Eager mode.
output_size
scope_name
state_size
trainable_variables
trainable_weights
updates
variables
Returns the list of all layer variables/weights.
Returns:
A list of variables.
weights
Returns the list of all layer variables/weights.
Returns:
A list of variables.
Methods
init

output_shape

```
__init__(
   num_units,
   forget_bias=1.0,
   state_is_tuple=True,
   activation=None,
   reuse=None
)
```

Initialize the basic LSTM cell.

Args:

- num_units: int, The number of units in the LSTM cell.
- forget_bias: float, The bias added to forget gates (see above). Must set to **0.0** manually when restoring from CudnnLSTM-trained checkpoints.
- state_is_tuple: If True, accepted and returned states are 2-tuples of the c_state and m_state. If False, they are concatenated along the column axis. The latter behavior will soon be deprecated.
- activation: Activation function of the inner states. Default: tanh.
- reuse: (optional) Python boolean describing whether to reuse variables in an existing scope. If not **True**, and the existing scope already has the given variables, an error is raised.

When restoring from CudnnLSTM-trained checkpoints, must use CudnnCompatibleLSTMCell instead.

__call__

```
__call__(
   inputs,
   state,
   scope=None
)
```

Run this RNN cell on inputs, starting from the given state.

Args:

- inputs: 2-D tensor with shape [batch_size x input_size].
- state: if self.state_size is an integer, this should be a 2-D Tensor with shape [batch_size x self.state_size]. Otherwise, if self.state_size is a tuple of integers, this should be a tuple with shapes [batch_size x s] for s in self.state_size.
- scope: VariableScope for the created subgraph; defaults to class name.

Returns:

A pair containing:

- Output: A 2-D tensor with shape [batch_size x self.output_size].
- New state: Either a single 2-D tensor, or a tuple of tensors matching the arity and shapes of state.

__deepcopy__

```
__deepcopy__(memo)
```

add_loss

```
add_loss(
    losses,
    inputs=None
)
```

Add loss tensor(s), potentially dependent on layer inputs.

Some losses (for instance, activity regularization losses) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs **a** and **b**, some entries in **layer.losses** may be dependent on **a** and some on **b**. This method automatically keeps track of dependencies.

The get_losses_for method allows to retrieve the losses relevant to a specific set of inputs.

Arguments:

- losses: Loss tensor, or list/tuple of tensors.
- inputs: Optional input tensor(s) that the loss(es) depend on. Must match the inputs argument passed to the __call__ method at the time the losses are created. If None is passed, the losses are assumed to be unconditional, and will apply across all dataflows of the layer (e.g. weight regularization losses).

Raises:

• RuntimeError: If called in Eager mode.

add_update

```
add_update(
    updates,
    inputs=None
)
```

Add update op(s), potentially dependent on layer inputs.

Weight updates (for instance, the updates of the moving mean and variance in a BatchNormalization layer) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs **a** and **b**, some entries in **layer.updates** may be dependent on **a** and some on **b**. This method automatically keeps track of dependencies.

The get_updates_for method allows to retrieve the updates relevant to a specific set of inputs.

This call is ignored in Eager mode.

Arguments:

- updates: Update op, or list/tuple of update ops.
- inputs: Optional input tensor(s) that the update(s) depend on. Must match the inputs argument passed to the __call__ method at the time the updates are created. If None is passed, the updates are assumed to be unconditional, and will apply across all dataflows of the layer.

add_variable

```
add_variable(
   name,
   shape,
   dtype=None,
   initializer=None,
   regularizer=None,
   trainable=True,
   constraint=None
)
```

Adds a new variable to the layer, or gets an existing one; returns it.

Arguments:

- name: variable name.
- shape: variable shape.
- dtype: The type of the variable. Defaults to self.dtype or float32.
- initializer: initializer instance (callable).
- regularizer: regularizer instance (callable).
- trainable: whether the variable should be part of the layer's "trainable_variables" (e.g. variables, biases) or "non_trainable_variables" (e.g. BatchNorm mean, stddev).
- constraint : constraint instance (callable).

Returns:

The created variable.

Raises:

• RuntimeError: If called in Eager mode with regularizers.

apply

```
apply(
   inputs,
   *args,
   **kwargs
)
```

Apply the layer on a input.

This simply wraps self.__call__.

Arguments:

- inputs: Input tensor(s).
- *args: additional positional arguments to be passed to self.call.
- **kwargs: additional keyword arguments to be passed to self.call.

Returns:

Output tensor(s).

build

```
build(_)
```

call

```
call(
   inputs,
   state
)
```

Long short-term memory cell (LSTM).

Args:

- inputs: 2-D tensor with shape [batch_size x input_size].
- state: An LSTMStateTuple of state tensors, each shaped [batch_size x self.state_size], if state_is_tuple has been set to True. Otherwise, a Tensor shaped [batch_size x 2 * self.state_size].

Returns:

A pair containing the new hidden state, and the new state (either a LSTMStateTuple or a concatenated state, depending on state_is_tuple).

count_params

```
count_params()
```

Count the total number of scalars composing the weights.

Returns:

An integer count.

Raises:

• ValueError: if the layer isn't yet built (in which case its weights aren't yet defined).

get_input_at

```
get_input_at(node_index)
```

Retrieves the input tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple inputs).

Raises:

• RuntimeError: If called in Eager mode.

get_input_shape_at

```
get_input_shape_at(node_index)
```

Retrieves the input shape(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple inputs).

Raises:

• RuntimeError: If called in Eager mode.

get_losses_for

```
get_losses_for(inputs)
```

Retrieves losses relevant to a specific set of inputs.

Arguments:

• inputs: Input tensor or list/tuple of input tensors. Must match the inputs argument passed to the __call__ method at the time the losses were created. If you pass inputs=None, unconditional losses are returned, such as weight regularization losses.

Returns:

List of loss tensors of the layer that depend on inputs.

Raises:

• RuntimeError: If called in Eager mode.

get_output_at

get_output_at(node_index)

Retrieves the output tensor(s) of a layer at a given node.

Arguments:

node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the
first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple outputs).

Raises:

• RuntimeError: If called in Eager mode.

get_output_shape_at

```
get_output_shape_at(node_index)
```

Retrieves the output shape(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple outputs).

Raises:

• RuntimeError: If called in Eager mode.

get_updates_for

```
get_updates_for(inputs)
```

Retrieves updates relevant to a specific set of inputs.

Arguments:

• inputs: Input tensor or list/tuple of input tensors. Must match the inputs argument passed to the __call__ method at the time the updates were created. If you pass inputs=None, unconditional updates are returned.

Returns:

List of update ops of the layer that depend on inputs.

Raises:

• RuntimeError: If called in Eager mode.

zero_state

```
zero_state(
   batch_size,
   dtype
)
```

Return zero-filled state tensor(s).

Args:

- batch_size: int, float, or unit Tensor representing the batch size.
- dtype: the data type to use for the state.

Returns:

If **state_size** is an int or TensorShape, then the return value is a **N-D** tensor of shape **[batch_size x state_size]** filled with zeros.

If **state_size** is a nested list or tuple, then the return value is a nested list or tuple (of the same structure) of **2-D** tensors with the shapes [**batch_size** x s] for each s in **state_size**.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

