TopogrElow

TensorFlow API r1.4

 $tf.contrib.bayesflow.stochastic_tensor.StochasticTensor$

Contents
Class StochasticTensor
Properties
distribution
dtype

Class StochasticTensor

Inherits From: BaseStochasticTensor

Defined in tensorflow/contrib/bayesflow/python/ops/stochastic_tensor_impl.py.

See the guide: BayesFlow Stochastic Tensors (contrib) > Stochastic Tensor Classes

StochasticTensor is a BaseStochasticTensor backed by a distribution.

Properties

distribution

dtype

graph

name

value_type

Methods

__init__

```
__init__(
    dist,
    name='StochasticTensor',
    dist_value_type=None,
    loss_fn=sge.score_function
)
```

Construct a StochasticTensor.

StochasticTensor is backed by the **dist** distribution and its **value** method will return the same value each time it is called. What **value** is returned is controlled by the **dist_value_type** (defaults to **SampleValue**).

Some distributions' sample functions are not differentiable (e.g. a sample from a discrete distribution like a Bernoulli) and

so to differentiate wrt parameters upstream of the sample requires a gradient estimator like the score function estimator. This is accomplished by passing a differentiable <code>loss_fn</code> to the <code>StochasticTensor</code>, which defaults to a function whose derivative is the score function estimator. Calling <code>stochastic_graph.surrogate_loss(final_losses)</code> will call <code>loss()</code> on every <code>StochasticTensor</code> upstream of final losses.

loss() will return None for **StochasticTensor** s backed by reparameterized distributions; it will also return None if the value type is **MeanValueType** or if **loss_fn=None**.

Args:

- dist: an instance of Distribution.
- name: a name for this StochasticTensor and its ops.
- dist_value_type: a _StochasticValueType, which will determine what the value of this StochasticTensor will be. If not provided, the value type set with the value_type context manager will be used.
- loss_fn: callable that takes (st, st.value(), influenced_loss), where st is this StochasticTensor, and returns a Tensor loss. By default, loss_fn is the score_function, or more precisely, the integral of the score function, such that when the gradient is taken, the score function results. See the stochastic_gradient_estimators module for additional loss functions and baselines.

Raises:

- TypeError: if dist is not an instance of Distribution.
- TypeError: if loss_fn is not callable.

entropy

```
entropy(name='entropy')
```

loss

```
loss(
    final_loss,
    name='Loss'
)
```

mean

```
mean(name='mean')
```

value

```
value(name='value')
```

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

Stay Connected	
Blog	
GitHub	
Twitter	
Support	
Issue Tracker	
Release Notes	
Stack Overflow	
English	
Terms Privacy	