TopogrElow

TensorFlow API r1.4

tf.contrib.rnn.PhasedLSTMCell

Contents

Class PhasedLSTMCell

Properties

activity_regularizer

dtype

Class PhasedLSTMCell

Inherits From: RNNCe11

Defined in tensorflow/contrib/rnn/python/ops/rnn_cell.py.

Phased LSTM recurrent network cell.

https://arxiv.org/pdf/1610.09513v1.pdf

Properties

activity_regularizer

Optional regularizer function for the output of this layer.

dtype

graph

input

Retrieves the input tensor(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer.

Returns:

Input tensor or list of input tensors.

Raises:

• AttributeError: if the layer is connected to more than one incoming layers.

Raises:

• RuntimeError: If called in Eager mode.

• AttributeError: If no inbound nodes are found.

input_shape

Retrieves the input shape(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer, or if all inputs have the same shape.

Returns:

Input shape, as an integer shape tuple (or list of shape tuples, one tuple per input tensor).

Raises:

- AttributeError: if the layer has no defined input_shape.
- RuntimeError: if called in Eager mode.

losses

name

non_trainable_variables

non_trainable_weights

output

Retrieves the output tensor(s) of a layer.

Only applicable if the layer has exactly one output, i.e. if it is connected to one incoming layer.

Returns:

Output tensor or list of output tensors.

Raises:

- AttributeError : if the layer is connected to more than one incoming layers.
- RuntimeError: if called in Eager mode.

output_shape

Retrieves the output shape(s) of a layer.

Only applicable if the layer has one output, or if all outputs have the same shape.

Returns:

Output shape, as an integer shape tuple (or list of shape tuples, one tuple per output tensor).

Raises:

- AttributeError: if the layer has no defined output shape.
- RuntimeError: if called in Eager mode.

output_size

scope_name

state_size

trainable_variables

trainable_weights

updates

variables

Returns the list of all layer variables/weights.

Returns:

A list of variables.

weights

Returns the list of all layer variables/weights.

Returns:

A list of variables.

Methods

__init__

```
__init__(
    num_units,
    use_peepholes=False,
    leak=0.001,
    ratio_on=0.1,
    trainable_ratio_on=True,
    period_init_min=1.0,
    period_init_max=1000.0,
    reuse=None
)
```

Initialize the Phased LSTM cell.

Args:

- num_units: int, The number of units in the Phased LSTM cell.
- use_peepholes: bool, set True to enable peephole connections.
- leak: float or scalar float Tensor with value in [0, 1]. Leak applied during training.
- ratio_on: float or scalar float Tensor with value in [0, 1]. Ratio of the period during which the gates are open.
- trainable_ratio_on: bool, weather ratio_on is trainable.
- period_init_min: float or scalar float Tensor. With value > 0. Minimum value of the initialized period. The period values are initialized by drawing from the distribution: e^U(log(period_init_min), log(period_init_max)) Where U(.,.) is the uniform distribution.
- period_init_max: float or scalar float Tensor. With value > period_init_min. Maximum value of the initialized period.
- reuse: (optional) Python boolean describing whether to reuse variables in an existing scope. If not True, and the existing scope already has the given variables, an error is raised.

__call__

```
__call__(
   inputs,
   state,
   scope=None
)
```

Run this RNN cell on inputs, starting from the given state.

Args:

- inputs: 2-D tensor with shape [batch_size x input_size].
- state: if self.state_size is an integer, this should be a 2-D Tensor with shape [batch_size x self.state_size]. Otherwise, if self.state_size is a tuple of integers, this should be a tuple with shapes [batch_size x s] for s in self.state_size.
- scope: VariableScope for the created subgraph; defaults to class name.

Returns:

A pair containing:

- Output: A 2-D tensor with shape [batch_size x self.output_size].
- New state: Either a single 2-D tensor, or a tuple of tensors matching the arity and shapes of state.

__deepcopy__

```
__deepcopy__(memo)
```

add_loss

```
add_loss(
   losses,
   inputs=None
)
```

Add loss tensor(s), potentially dependent on layer inputs.

Some losses (for instance, activity regularization losses) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs **a** and **b**, some entries in **layer.losses** may be dependent on **a** and some on **b**. This method automatically keeps track of dependencies.

The get_losses_for method allows to retrieve the losses relevant to a specific set of inputs.

Arguments:

- losses: Loss tensor, or list/tuple of tensors.
- inputs: Optional input tensor(s) that the loss(es) depend on. Must match the inputs argument passed to the __call__ method at the time the losses are created. If None is passed, the losses are assumed to be unconditional, and will apply across all dataflows of the layer (e.g. weight regularization losses).

Raises:

• RuntimeError: If called in Eager mode.

add_update

```
add_update(
    updates,
    inputs=None
)
```

Add update op(s), potentially dependent on layer inputs.

Weight updates (for instance, the updates of the moving mean and variance in a BatchNormalization layer) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs **a** and **b**, some entries in **layer.updates** may be dependent on **a** and some on **b**. This method automatically keeps track of dependencies.

The get_updates_for method allows to retrieve the updates relevant to a specific set of inputs.

This call is ignored in Eager mode.

Arguments:

- updates: Update op, or list/tuple of update ops.
- inputs: Optional input tensor(s) that the update(s) depend on. Must match the inputs argument passed to the __call__ method at the time the updates are created. If None is passed, the updates are assumed to be unconditional, and will apply across all dataflows of the layer.

add_variable

```
add_variable(
    name,
    shape,
    dtype=None,
    initializer=None,
    regularizer=None,
    trainable=True,
    constraint=None
)
```

Adds a new variable to the layer, or gets an existing one; returns it.

Arguments:

- name: variable name.
- shape: variable shape.
- dtype: The type of the variable. Defaults to self.dtype or float32.
- initializer : initializer instance (callable).
- regularizer : regularizer instance (callable).
- trainable: whether the variable should be part of the layer's "trainable_variables" (e.g. variables, biases) or "non_trainable_variables" (e.g. BatchNorm mean, stddev).
- constraint : constraint instance (callable).

Returns:

The created variable.

Raises:

• RuntimeError: If called in Eager mode with regularizers.

apply

```
apply(
   inputs,
   *args,
   **kwargs
)
```

Apply the layer on a input.

This simply wraps self.__call__.

Arguments:

- inputs: Input tensor(s).
- *args: additional positional arguments to be passed to self.call.
- **kwargs: additional keyword arguments to be passed to self.call.

Returns:

Output tensor(s).

build

```
build(_)
```

call

```
call(
   inputs,
   state
)
```

Phased LSTM Cell.

Args:

- inputs: A tuple of 2 Tensor. The first Tensor has shape [batch, 1], and type float32 or float64. It stores the time. The second Tensor has shape [batch, features_size], and type float32. It stores the features.
- state: rnn_cell_impl.LSTMStateTuple, state from previous timestep.

Returns:

A tuple containing: - A Tensor of float32, and shape [batch_size, num_units], representing the output of the cell. - A rnn_cell_impl.LSTMStateTuple, containing 2 Tensors of float32, shape [batch_size, num_units], representing the new state and the output.

count_params

```
count_params()
```

Count the total number of scalars composing the weights.

Returns:

An integer count.

Raises:

• ValueError: if the layer isn't yet built (in which case its weights aren't yet defined).

get_input_at

```
get_input_at(node_index)
```

Retrieves the input tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple inputs).

Raises:

• RuntimeError: If called in Eager mode.

get_input_shape_at

```
get_input_shape_at(node_index)
```

Retrieves the input shape(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple inputs).

Raises:

• RuntimeError: If called in Eager mode.

get_losses_for

```
{\tt get\_losses\_for(inputs)}
```

Retrieves losses relevant to a specific set of inputs.

Arguments:

inputs: Input tensor or list/tuple of input tensors. Must match the inputs argument passed to the __call__
method at the time the losses were created. If you pass inputs=None, unconditional losses are returned, such as
weight regularization losses.

Returns:

List of loss tensors of the layer that depend on inputs.

Raises:

• RuntimeError: If called in Eager mode.

get_output_at

```
get_output_at(node_index)
```

Retrieves the output tensor(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple outputs).

Raises:

• RuntimeError: If called in Eager mode.

get_output_shape_at

```
get_output_shape_at(node_index)
```

Retrieves the output shape(s) of a layer at a given node.

Arguments:

• node_index: Integer, index of the node from which to retrieve the attribute. E.g. node_index=0 will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple outputs).

Raises:

• RuntimeError: If called in Eager mode.

get_updates_for

```
get_updates_for(inputs)
```

Retrieves updates relevant to a specific set of inputs.

Arguments:

• inputs: Input tensor or list/tuple of input tensors. Must match the inputs argument passed to the __call__ method at the time the updates were created. If you pass inputs=None, unconditional updates are returned.

Returns:

List of update ops of the layer that depend on inputs.

Raises:

• RuntimeError: If called in Eager mode.

zero_state

```
zero_state(
   batch_size,
   dtype
)
```

Return zero-filled state tensor(s).

Args:

- batch_size: int, float, or unit Tensor representing the batch size.
- dtype: the data type to use for the state.

Returns:

If **state_size** is an int or TensorShape, then the return value is a **N-D** tensor of shape **[batch_size x state_size]** filled with zeros

If **state_size** is a nested list or tuple, then the return value is a nested list or tuple (of the same structure) of **2-D** tensors with the shapes [**batch_size** x s] for each s in **state_size**.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

