TopogrElow

TensorFlow API r1.4

tf.contrib.layers.conv3d_transpose

Contents
Aliases:

Aliases:

- tf.contrib.layers.conv3d_transpose
- tf.contrib.layers.convolution3d_transpose

```
conv3d_transpose(
   inputs,
   num_outputs,
   kernel_size,
    stride=1,
    padding='SAME',
    data_format=DATA_FORMAT_NDHWC,
    activation_fn=tf.nn.relu,
    normalizer_fn=None,
    normalizer_params=None,
    weights_initializer=initializers.xavier_initializer(),
    weights_regularizer=None,
    biases_initializer=tf.zeros_initializer(),
    biases_regularizer=None,
    reuse=None,
    variables_collections=None,
    outputs_collections=None,
    trainable=True,
    scope=None
)
```

Defined in tensorflow/contrib/layers/python/layers/layers.py.

Adds a convolution3d_transpose with an optional batch normalization layer.

The function creates a variable called **weights**, representing the kernel, that is convolved with the input. If **batch_norm_params** is **None**, a second variable called 'biases' is added to the result of the operation.

Args:

- inputs: A 5-D Tensor of type float and shape [batch, depth, height, width, in_channels] for NDHWC data format or [batch, in_channels, depth, height, width] for NCDHW data format.
- num_outputs: Integer, the number of output filters.
- kernel_size: A list of length 3 holding the [kernel_depth, kernel_height, kernel_width] of the filters. Can be an int if both values are the same.
- stride: A list of length 3: [stride_depth, stride_height, stride_width]. Can be an int if both strides are the same. Note that presently both strides must have the same value.
- padding: One of 'VALID' or 'SAME'.
- data_format: A string. NDHWC (default) and NCDHW are supported.
- activation_fn: Activation function. The default value is a ReLU function. Explicitly set it to None to skip it and

maintain a linear activation.

- normalizer_fn: Normalization function to use instead of biases. If normalizer_fn is provided then
 biases_initializer and biases_regularizer are ignored and biases are not created nor added. default set to
 None for no normalizer function
- normalizer_params: Normalization function parameters.
- weights_initializer: An initializer for the weights.
- weights_regularizer: Optional regularizer for the weights.
- biases_initializer: An initializer for the biases. If None skip biases.
- biases_regularizer: Optional regularizer for the biases.
- reuse: Whether or not the layer and its variables should be reused. To be able to reuse the layer scope must be
 given.
- variables_collections: Optional list of collections for all the variables or a dictionary containing a different list of collection per variable.
- outputs_collections: Collection to add the outputs.
- trainable: Whether or not the variables should be trainable or not.
- scope : Optional scope for variable_scope.

Returns:

A tensor representing the output of the operation.

Raises:

- ValueError: If 'kernel_size' is not a list of length 3.
- ValueError: If data_format is neither NDHWC nor NCDHW.
- ValueError: If C dimension of inputs is None.

Except as otherwise noted, the content of this page is licensed under the Creative Commons Attribution 3.0 License, and code samples are licensed under the Apache 2.0 License. For details, see our Site Policies. Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.



English

Terms | Privacy