TopogrElow

TensorFlow API r1.4

tf.contrib.framework.load_embedding_initializer

```
load_embedding_initializer(
    ckpt_path,
    embedding_tensor_name,
    new_vocab_size,
    embedding_dim,
    old_vocab_file,
    new_vocab_file,
    num_oov_buckets=0,
    initializer=None,
    max_rows_in_memory=-1
)
```

Defined in tensorflow/python/training/checkpoint_ops.py.

Returns a variable initializer for loading pre-trained embeddings.

Wrapper around **load_and_remap_matrix_initializer()** specialized for loading embedding weights and remapping according to the provided vocab files. See docs for **load_and_remap_matrix_initializer()** for more details.

NOTE: Only for use with div-partitioned variables / vocabularies.

Args:

- ckpt_path: Path to the TensorFlow checkpoint (version 2, TensorBundle) from which the old matrix Tensor will be
- embedding_tensor_name: Name of the 2-D Tensor to load from checkpoint.
- new_vocab_size: Number of entries in the new vocab.
- embedding_dim: int specifying the dimension of the embedding vectors from the checkpoint. Must match the number of columns in the old embedding matrix.
- old_vocab_file: A scalar Tensor of type string containing the path to the old vocabulary file.
- new_vocab_file: A scalar Tensor of type string containing the path to the new vocabulary file.
- num_oov_buckets: int specifying the number of out-of-vocabulary buckets to use. Must be >= 0.
- initializer: Initializer function that accepts a 1-D tensor as the arg to specify the shape of the returned tensor. If None, defaults to using truncated_normal_initializer().
- max_rows_in_memory: int specifying the maximum number of rows to load from the checkpoint at once. If less
 than or equal to 0, the entire matrix will be loaded into memory. Setting this arg trades increased disk reads for lower
 memory usage.

Returns:

A variable initializer function.

Stay Connected	
Blog	
GitHub	
Twitter	
Support	
Issue Tracker	
Release Notes	
Stack Overflow	
English	
Terms Privacy	