Sockets · The Julia Language

Standard Library / Sockets







Sockets

Sockets.Sockets - Module

Support for sockets. Provides IPAddr and subtypes, TCPSocket, and UDPSocket.

Sockets.connect — Method

connect([host], port::Integer) -> TCPSocket

Connect to the host host on port port.

Sockets.connect — Method

connect(path::AbstractString) -> PipeEndpoint

Connect to the named pipe / UNIX domain socket at path.

Sockets.listen - Method

listen([addr,]port::Integer; backlog::Integer=BACKLOG_DEFAULT) -> TCPServer

Listen on port on the address specified by addr. By default this listens on localhost only. To listen on all interfaces pass IPv4(0) or IPv6(0) as appropriate. backlog determines how many connections can be pending (not having called accept) before the server will begin to reject them. The default value of backlog is 511.

Sockets.listen - Method

```
listen(path::AbstractString) -> PipeServer
```

Create and listen on a named pipe / UNIX domain socket.

Sockets.getaddrinfo-Function

```
getaddrinfo(host::AbstractString, IPAddr=IPv4) -> IPAddr
```

Gets the first IP address of the host of the specified IPAddr type. Uses the operating system's underlying getaddrinfo implementation, which may do a DNS lookup.

Sockets.getipaddr — Function

```
getipaddr() -> IPAddr
```

Get an IP address of the local machine, preferring IPv4 over IPv6. Throws if no addresses are available.

```
getipaddr(addr_type::Type{T}) where T<:IPAddr -> T
```

Get an IP address of the local machine of the specified type. Throws if no addresses of the specified type are available.

This function is a backwards-compatibility wrapper around getipaddrs. New applications should use getipaddrs instead.

Examples

```
julia> getipaddr()
ip"192.168.1.28"

julia> getipaddr(IPv6)
ip"fe80::9731:35af:e1c5:6e49"
```

See also: getipaddrs

Sockets.getipaddrs — Function

```
getipaddrs(addr_type::Type{T}=IPAddr; loopback::Bool=false) where T<:IPAddr ->
```

Get the IP addresses of the local machine.

Setting the optional addr_type parameter to IPv4 or IPv6 causes only addresses of that type to be returned.

The loopback keyword argument dictates whether loopback addresses (e.g. ip 127.0.0.1, ip"::1") are included.



● Julia 1.2

This function is available as of Julia 1.2.

Examples

```
julia> getipaddrs()
5-element Array{IPAddr,1}:
 ip"198.51.100.17"
ip"203.0.113.2"
 ip"2001:db8:8:4:445e:5fff:fe5d:5500"
 ip"2001:db8:8:4:c164:402e:7e3c:3668"
 ip"fe80::445e:5fff:fe5d:5500"
julia> getipaddrs(IPv6)
3-element Array{IPv6,1}:
 ip"2001:db8:8:4:445e:5fff:fe5d:5500"
 ip"2001:db8:8:4:c164:402e:7e3c:3668"
 ip"fe80::445e:5fff:fe5d:5500"
```

Sockets.islinklocaladdr — Function

```
islinklocaladdr(addr::IPAddr)
```

See also: islinklocaladdr, split(ENV["SSH_CONNECTION"], '')[3]

Tests if an IP address is a link-local address. Link-local addresses are not guaranteed to be unique beyond their network segment, therefore routers do not forward them. Link-local addresses are from the address blocks 169.254.0.0/16 or fe80::/10.

Example

```
filter(!islinklocaladdr, getipaddrs())
```

Sockets.getalladdrinfo — Function

```
getalladdrinfo(host::AbstractString) -> Vector{IPAddr}
```

Gets all of the IP addresses of the host. Uses the operating system's underlying getaddrinfo implementation, which may do a DNS lookup.

Example

```
julia> getalladdrinfo("google.com")
2-element Array{IPAddr,1}:
   ip"172.217.6.174"
   ip"2607:f8b0:4000:804::200e"
```

Sockets.DNSError — Type

```
DNSError
```

The type of exception thrown when an error occurs in DNS lookup. The host field indicates the host URL string. The code field indicates the error code based on libuv.

Sockets.getnameinfo — Function

```
getnameinfo(host::IPAddr) -> String
```

Performs a reverse-lookup for IP address to return a hostname and service using the operating system's underlying getnameinfo implementation.

Examples

```
julia> getnameinfo(Sockets.IPv4("8.8.8.8"))
"google-public-dns-a.google.com"
```

Sockets.getsockname — Function

```
getsockname(sock::Union{TCPServer, TCPSocket}) -> (IPAddr, UInt16)
```

Get the IP address and port that the given socket is bound to.

Sockets.getpeername — Function

```
getpeername(sock::TCPSocket) -> (IPAddr, UInt16)
```

Get the IP address and port of the remote endpoint that the given socket is connected to. Valid only for connected TCP sockets.

Sockets.IPAddr — Type

IPAddr

Abstract supertype for IP addresses. IPv4 and IPv6 are subtypes of this.

Sockets.IPv4 — Type

```
IPv4(host::Integer) -> IPv4
```

Returns an IPv4 object from ip address host formatted as an Integer.

Examples

```
julia> IPv4(3223256218)
```

```
ip"192.30.252.154"
```

```
Sockets.IPv6 — Type
```

```
IPv6(host::Integer) -> IPv6
```

Returns an IPv6 object from ip address host formatted as an Integer.

Examples

```
julia> IPv6(3223256218)
ip"::c01e:fc9a"
```

Sockets.@ip_str - Macro

```
@ip_str str -> IPAddr
```

Parse str as an IP address.

Examples

```
julia> ip"127.0.0.1"
ip"127.0.0.1"

julia> @ip_str "2001:db8:0:0:0:2:1"
ip"2001:db8::2:1"
```

Sockets.TCPSocket - Type

```
TCPSocket(; delay=true)
```

Open a TCP socket using libuv. If delay is true, libuv delays creation of the socket's file descriptor till the first bind call. TCPSocket has various fields to denote the state of the socket as well as its send/receive buffers.

```
Sockets.UDPSocket — Type
```

```
UDPSocket()
```

Open a UDP socket using libuv. UDPSocket has various fields to denote the state of the socket.

Sockets.accept — Function

```
accept(server[, client])
```

Accepts a connection on the given server and returns a connection to the client. An uninitialized client stream may be provided, in which case it will be used instead of creating a new stream.

Sockets.listenany — Function

```
listenany([host::IPAddr,] port_hint) -> (UInt16, TCPServer)
```

Create a TCPServer on any port, using hint as a starting point. Returns a tuple of the actual port that the server was created on and the server itself.

Base.bind — Function

```
\verb|bind(socket::Union{UDPSocket, TCPSocket}|, \verb|host::IPAddr, port::Integer; ipv6only|| \\
```

Bind socket to the given host:port. Note that 0.0.0.0 will listen on all devices.

- The ipv6only parameter disables dual stack mode. If ipv6only=true, only an IPv6 stack is created.
- If reuseaddr=true, multiple threads or processes can bind to the same address without error if they all set reuseaddr=true, but only the last to bind will receive any traffic.

```
bind(chnl::Channel, task::Task)
```

Associate the lifetime of chn1 with a task. Channel chn1 is automatically closed when the task terminates. Any uncaught exception in the task is propagated to all waiters on chn1.

The chn1 object can be explicitly closed independent of task termination. Terminating tasks have no effect on already closed Channel objects.

When a channel is bound to multiple tasks, the first task to terminate will close the channel. When multiple channels are bound to the same task, termination of the task will close all of the bound channels.

Examples

```
julia> c = Channel(0);

julia> task = @async (put!(c, 1); error("foo"));

julia> bind(c, task);

julia> take!(c)
1

julia> put!(c, 1);
ERROR: TaskFailedException:
foo
Stacktrace:
[...]
```

Sockets.send - Function

```
send(socket::UDPSocket, host::IPAddr, port::Integer, msg)
```

Send msg over socket to host:port.

Sockets.recv — Function

```
recv(socket::UDPSocket)
```

Read a UDP packet from the specified socket, and return the bytes received. This call blocks.

Sockets.recvfrom — Function

```
recvfrom(socket::UDPSocket) -> (host_port, data)
```

Read a UDP packet from the specified socket, returning a tuple of (host_port, data), where host_port will be an InetAddr{IPv4} or InetAddr{IPv6}, as appropriate.

• Julia 1.3

Prior to Julia version 1.3, the first returned value was an address (IPAddr). In version 1.3 it was changed to an InetAddr.

Sockets.setopt — Function

```
setopt(sock::UDPSocket; multicast_loop=nothing, multicast_ttl=nothing, enable_b
```

Set UDP socket options.

- multicast_loop: loopback for multicast packets (default: true).
- multicast_ttl: TTL for multicast packets (default: nothing).
- enable_broadcast: flag must be set to true if socket will be used for broadcast messages, or

else the UDP system will return an access error (default: false).

• ttl:Time-to-live of packets sent on the socket (default: nothing).

Sockets.nagle — Function

nagle(socket::Union{TCPServer, TCPSocket}, enable::Bool)

Enables or disables Nagle's algorithm on a given TCP server or socket.

Sockets.quickack — Function

quickack(socket::Union{TCPServer, TCPSocket}, enable::Bool)

On Linux systems, the TCP_QUICKACK is disabled or enabled on socket.

« Shared Arrays Sparse Arrays »

Powered by Documenter.jl and the Julia Programming Language.