```
例5-7 一个morphline配置文件
SOLR LOCATOR: {
 collection : usingFlumeCollection
  zkHost: "com.usingflume.solrZk:2181/solr"
}
morphlines : [
  {
                id : usingFlumeMorphline
    importCommands : ["org.kitesdk.**", "org.apache.solr.**"]
    # Convert the event into a UTF-8 encoded string
commands : [
                {
                       readClob {
                          charset : UTF-8
                       }
                }
    # Generate a UUID that can be used for the Solr unique key field
      generateUUID {
          field: id
      }
    }
    # Load the record into Solr
      loadSolr: {
          solrLocator : ${SOLR LOCATOR}
      }
    }
         ]
  }
1
```

Morphline Solr Sink 启动 morphline 会话,从 Channel 中读取事件,并将它们转换为记录,事件主体设置为\_attachment\_body 字段。然后 Sink 依次传递事件到 morphline。每条记录传递给 readClob 命令,用来读取主体,并将它转换为 UTF-8 字符串,再将该字符串设置为 message 字段的值。

generateUUID 生成 UUID,并将它设置为 id 字段的值,为 Solr 使用的唯一键(前面讨论过)。然后为了索引事件通过 loadSolr 命令加载到 Solr 索引。为了扩展 loadSolr 命令也允许加载数据到 SolrCloud 集群。

128