

Trade one account. **The rest follow.**

STRATUH Copier mirrors trades from your **master** account to your **follower** accounts, live, inside the Vest page. It runs in your own logged-in browser, acts only on your trades, and only while **armed**.

You trade the master

Place, manage and close trades on Vest exactly as you normally do.



The copier sees the order

It watches your master's order requests in the page, then fires matching orders.



Followers mirror it

Open

Add

Reduce

Stop / TP

Close

Cancel

01 INSTALL

- 1 Add **Tampermonkey** from your browser's store (Chrome Web Store, Edge Add-ons or Firefox Add-ons). In Chrome, Edge or Brave: `chrome://extensions` > Tampermonkey > Details > turn on **Allow User Scripts**.
- 2 Install from `github.com/xAmped/Vest-Copier` (it then auto-updates), or paste `vest-copier.user.js` into a new Tampermonkey script.
- 3 Open or refresh **next.vestmarkets.com** — the panel appears on the chart, left.
New versions show as a bar in the panel: click Install. Settings are kept.

02 SET UP & ARM

- 1 Your accounts load automatically (click `u` to reload). A green dot means the account can trade.
- 2 Click `M` on your master, then `FLW` on each follower.
Strict 1:1 needs matching size & type. For mixed sizes, turn on Cap-to-fit first.
- 3 Set the leverage you'll use on Vest for the session.
- 4 Click `ARM`. The first time, accept the one-time agreement.
Everyone flat, or already in the same trade (it's adopted).
- 5 Trade the master normally. Every copy is logged.
- 6 Click `DISARM` when you're done. It stops copying; it doesn't close positions.

Trade tab: follows Vest's market. Margin and risk bars, a price ladder in points, risk or max sizing, limits from a chart click, and in a trade Breakeven, Close and add chips. Changed leverage or market? **Disarm and arm again.**

03 SIZING

DEFAULT Strict 1:1

Followers copy the master's exact size. Same size & type only.

SETTINGS > CAP-TO-FIT Sized to each account

Sized to its own equity. Same stop, same % risk.

```
follower size =
  master size × follower equity ÷ master equity
// e.g. 25k master 10.00 · 5k follower 1.90
```

04 OPTIONS & SAFETY

Fast mode	Fires follower entries the instant you send yours, before the master confirms.
Auto-flatten	Closes followers left in a trade without the master.
Flatten All	Closes all positions and orders on every loaded account. Instant, no confirmation. Stays armed.
Fill check	Names any account that didn't fill, master included.
Not copied	Refused orders; closes Vest forces (breach, liquidation).
Records	<code>P&L</code> totals · <code>CSV</code> log · <code>Diag</code> report (token-free, safe to send).
Status	Bottom right. Amber after a Vest update: click it to run the site check, then accept.

05 GOOD HABITS

- ✓ **Start tiny.** Test one small trade across all accounts first.
- ✓ **Stay flat** between sessions and disarm when not trading.
- ✓ **Leave headroom.** Don't run the master at 100% margin in strict 1:1.
- ✓ **Size for the worst case:** a loss on every account at once.
- ✓ **Disarm** before any manual trade you don't want copied.
- ✓ **Something off?** Click `Diag` and send the file.

06 TROUBLESHOOTING

No panel? Turn on **Allow User Scripts**, then refresh Vest.

Can't pick a follower? It's a different size or type. Turn on Cap-to-fit, or match accounts.

Won't arm? The log names the account and the reason.