



AutoAdventurer

Complete Manual

Quest automation, travel, Rage, Boost, events, configuration, logging, and troubleshooting
Version 2.0.0 | Tashi

AutoAdventurer is the active-gameplay module in Tashi's Full Automation Suite. It coordinates quest objectives, dimension travel, character requirements, Rage Mode, movement abilities, Bonus helpers, and boss fights.

This manual covers configuration version 35. New users should begin with the User Guide.

Reference Chapters

- 1 Installation and Upgrading
- 2 Quick Start and Controls
- 3 Quest Automation
- 4 Automatic Rage
- 5 Auto Movement & Combat
- 6 Travel, Events, and Safety
- 7 Bonus, Slider, and Boss Features
- 8 Configuration Reference
- 9 Logging Reference
- 10 Troubleshooting

Module Responsibilities

- AutoAdventurer selects and performs kill quests, travels between dimensions, switches compatible characters, and controls Rage/Boost helpers.
- AutoProgression handles purchases, normal Ascension, craftables, materials, eggs, and completed-quest claiming.
- AutoClimber controls Ascending Heights routes, enemies, and rewards.
- AutoBonusRunner controls supported Bonus Stage routes, jumping, recovery, sphere requirements, rewards, and retry.

The mods can be used independently or together.

Default Controls

Key	Action
P	Toggle Quest Automation
K	Toggle Automatic Rage
J	Immediately end the current Rage Mode
L	Toggle Auto Movement & Combat

Automatic Rage and Quest Automation start disabled. Auto Movement & Combat starts enabled by default and can still be toggled with L. Slider Skip and Auto Boss are controlled directly by configuration and default to enabled.

Safety Principles

- Quest decisions use internal IDs and game objects instead of localized text.
- Reward priority is applied only after a quest is proven executable.

- Native Portal cooldowns and destination restrictions are never bypassed.
- Only the manual J action force-ends Rage Mode.
- IL2CPP quest, enemy, map, character, and Portal objects are not retained across scene changes.
- Events, boxes, keys, portals, and special scenes take priority over travel.

Support Development

If these mods save you time, you can support continued development through [PayPal](#).

Installation and Upgrading

Recommended Installation

- 1 Install and initialize Idle Slayer Mod Manager.
- 2 Install Idle Slayer Mods Core.
- 3 Import the AutoAdventurer ZIP without extracting it.
- 4 Enable AutoAdventurer and start the game.

Manual Installation

Place `AutoAdventurer.dll` in:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\Mods\
```

Do not place the DLL directly in the Steam game directory. A custom Mod Manager installation must use its own `ModLoader\Mods` directory.

Configuration File

The first launch creates:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\UserData\AutoAdventurer.cfg
```

Edit the file while the game is closed, save it, and restart the game.

Upgrading

- Replace the old DLL or import the new ZIP.
- Keep `AutoAdventurer.cfg` to preserve personal settings.
- The mod migrates renamed or removed settings when its schema changes.
- Do not manually edit `Configuration Version`.

Requirements

- Idle Slayer
- MelonLoader 0.7.1 or newer
- Idle Slayer Mods Core
- Idle Slayer Mod Manager (recommended on Windows)

Quick Start and Controls

Recommended Start

- 1 Enter a normal running dimension.
- 2 Press K to enable Automatic Rage.
- 3 Auto Movement & Combat starts enabled by default; press L whenever you want to disable or re-enable it.
- 4 Press P to enable Quest Automation.
- 5 If AutoProgression is installed, keep completed-quest claiming enabled so follow-up quests can unlock automatically.

Key Behavior

P — Quest Automation

- Starts a new completion-statistics session when enabled.
- Prints session totals and abnormal tasks when disabled.
- Clears the session task lock and abnormal exclusion list when disabled.

K — Automatic Rage

- Enables or disables future automatic Rage activations.
- Disabling it does not end a Rage execution already in progress.

J — Immediate Rage Stop

- This is the only AutoAdventurer path that force-ends Rage Mode.
- Keys, time limits, and travel preparation wait for Rage to end naturally.

L — Auto Movement & Combat

- Enables or disables minimum-height jumping, automatic arrows, and the selected movement ability according to their configuration switches.
- Requests an immediate supported Boost/Wind Dash activation when enabled and safe.
- Follows the player's selected Boost or Wind Dash ability.
- Runs only in the central Runner/Rage scene.

Independent Features

The following settings default to enabled and do not depend on P, K, or L:

- Skip Bonus Start Slider
- Auto Boss

Menus and Scenes

Ordinary menus over the central Runner/Rage scene do not pause character or quest automation. Villages, minigames, boss maps, story scenes, and true GameState changes use their own pause or specialized behavior.

Quest Automation

Press P to enable or disable Quest Automation. Only kill quests that are proven executable are considered.

Eligibility Validation

A quest must pass every relevant check before ranking:

- 1 It is active, incomplete, valid, and unclaimed.
- 2 Its quest type is supported.
- 3 Its target enemy or category can be resolved from internal game objects.
- 4 A required evolution is unlocked; a later descendant in the same evolution chain can satisfy an earlier-stage requirement.
- 5 A required character is unlocked.
- 6 A valid target map currently contains a matching enemy.
- 7 If travel is required, the destination is a normal Map currently offered by the native Portal.

An impossible task cannot win because of its reward.

Supported Objectives

- Exact enemy kills
- Exact enemy evolution stages
- Elemental or native enemy-type kills
- Flyers
- Giants
- Arrow kills
- Resolvable Rage kills
- Resolvable Wind Dash kills
- Character-specific kills for unlocked characters

Ignored Objectives

- Unresolvable generic targets such as `AnyEnemy`
- Boxes, collections, and other non-kill objectives
- Tasks requiring an unavailable character
- Locked exact evolution stages that the current stage cannot satisfy
- Targets limited to Bonus, boss, village, story, or other non-Portal maps
- Destinations absent from the current native Portal list
- Weekly Quests, for both execution and completion statistics

Reward Priority

Priority is applied only after full eligibility validation:

Priority	Reward
Top	Unlocks additional quest levels (IncreaseQuestsLevel)
High	Unlocks equipment, characters, minions, giants, NPCs, Stones of Time, Ascension upgrades, loadouts, or another explicit content system
Normal	Gives a numeric improvement or no unlock reward

Within the same priority, the quest with the smallest total kill requirement is selected. Exact ties keep game-list order.

CpS, Coins, Souls, Rage, Boost, Wind Dash, drop-rate, damage, and offline numeric improvements remain Normal priority.

Quest Locking

- The lock combines internal ID, runtime type, target, character, and goal.
- A selected quest remains locked instead of changing every scan.
- Daily identity includes additional runtime data because multiple Daily slots can share the same base ID.
- Manually rerolled Daily quests are detected as removed or replaced.
- Scene interruptions retain a valid task lock.

Time Limits and Abnormal Tasks

- Maximum Quest Time Minutes defaults to 5 minutes.
- When it expires, the current task is excluded while alternatives are tested.
- If no alternative exists, the target is validated again; a valid task may continue with refreshed timers.
- A separate watchdog checks progress every 5 minutes.
- Invalid or non-progressing tasks enter the current P session's abnormal list and are excluded from later scans.
- Disabling P prints and resets the abnormal list.

Character Tasks

- Only unlocked required characters are accepted.
- Automatic Rage refresh is suppressed while a character correction is needed.
- An active Rage execution ends naturally before switching.
- Any outfit belonging to the required base character is accepted.
- The previous character is not restored after completion.

Arrow Tasks

Generic arrow-kill tasks suppress new automatic Rage activations so ordinary bow kills can continue. A Rage execution already running still ends naturally.

Elemental Dark Divinities

Auto `Align Elemental Divinities` defaults to `true` and runs only while `P` is enabled. An explicit elemental kill task may switch among a set of elemental Dark Divinities that the player already activated. This helper does not select, lock, or increase the priority of that task.

Silver Random Box task handling is a separate global feature documented in the configuration reference. It does not depend on Quest Automation or `P`.

Completion Statistics

- Counters reset each time `P` is enabled.
- Daily and normal completions are counted separately.
- Weekly completions are excluded.
- A task must be positively observed as completed or successfully claimed while the session is active.
- Claims initiated by `AutoProgression` or another path can be observed.
- Disabling `P` prints the final total.
- In-game notifications can be disabled without disabling logs.

No Executable Quest

The mod reads the same live Souls score used by the Portal star display and selects the highest-scoring currently available dimension. A tie prefers the current map to avoid unnecessary travel. Quest scanning continues there.

Automatic Rage

Press K to toggle Automatic Rage. Press J to immediately end the current Rage execution.

Activation Cycle

- Readiness is checked every 12 seconds by default.
- Rage can be refreshed while an execution is already active.
- Refreshes do not restart the current cycle's maximum-duration timer.
- At the configured limit, refreshes stop and the execution ends naturally.
- The default maximum is 120 seconds; 0 disables the limit.

Post-Rage Protection

After Rage ends, the map is protected for 5 seconds by default. During this window the mod:

- Does not restart Rage.
- Prioritizes a fresh quest scan.
- Checks keys, boxes, events, minigame items, and portals.
- Revalidates a planned destination before opening a Portal.

This shared delay prevents a new Rage or Portal from starting before delayed world objects have appeared.

Natural and Forced End Behavior

- Pressing K off stops future activations but does not end the current Rage.
- Reaching the duration limit stops refreshes and waits naturally.
- Detecting a Chest Hunt Key stops refreshes and waits naturally.
- Quest travel stops refreshes and waits naturally.
- Only the manual J key force-ends the current execution.

Blockers

- Chest Hunt Key
- Existing Portal, door, or interactive entrance
- Special Random Box
- Ascending Heights or Grapple Run trigger items
- Unsupported scenes and map transitions
- Quest travel, character correction, or arrow-task suppression
- Post-Rage protection

Scene Stabilization

After returning from a village, minigame, story scene, or Portal transition, the central Runner/Rage scene must remain stable for 2 seconds before Automatic Rage resumes.

Auto Movement & Combat

Auto Movement & Combat starts enabled by default. Press L to disable or re-enable it.

Jumping and Arrow Attacks

- Minimum-height jumping and automatic arrow attacks can be enabled independently in the configuration.
- Arrow frequency supports Light, Medium, High, Extra High, and Ultra.
- All movement and combat helpers run only in the central Runner/Rage scene.

Selected Ability

- The mod reads `AbilitiesManager.selectedAbility` before activation.
- Switching between Boost and Wind Dash is followed automatically.
- The two abilities are not treated as independent cooldowns.
- Ability objects are re-resolved after Ascension and scene reconstruction.

Cooldown and Delay

- Activation waits until the selected ability cooldown reaches zero.
- Ability activation uses a fixed internal 0.2-second delay after cooldown reaches zero. This safety timing is intentionally not exposed in the configuration file.
- Wind Dash pauses while a Chest Hunt Key is active on the map, preventing it from outrunning the key. Normal Boost is unaffected.
- Before horizontal Random Box tracking is unlocked, both Boost and Wind Dash pause while the box-catching helper is targeting an active box. Its jump lead adapts to the observed approach speed so existing speed bonuses do not invalidate the intercept timing.
- Enabling with L requests immediate activation, but all scene, unlock, and safety conditions still apply.
- The authoritative cooldown is synchronized immediately after activation to prevent duplicate calls in one ready window.

Grounded Wind Dash

Wind Dash Require Grounded defaults to enabled:

- When ready, Wind Dash is checked every frame until the player is grounded.
- It activates immediately after ground contact without a second delay.
- This reduces the chance of passing above portals, keys, gems, or elite enemies.

Disable the setting to allow automatic airborne Wind Dash.

Minigames and Reward Sections

Bonus stages, reward sections, and other minigames are excluded. AutoAdventurer does not inject jumps, arrows, Boost, or Wind Dash into those scenes.

Scene Stabilization

Auto Movement & Combat waits 0.5 seconds after returning to the central gameplay scene.

Travel, Events, and Safety

Travel Sequence

- 1 Select and lock an executable quest.
- 2 Stay if the current map can complete it.
- 3 Validate a destination from the native Portal list if travel is required.
- 4 Acquire a travel lock and suppress new automatic Rage activations.
- 5 Let any active Rage execution end naturally.
- 6 Wait through post-Rage protection.
- 7 Revalidate the quest, map, Portal button, cooldown, and world blockers.
- 8 Spawn the Portal and wait for entry.
- 9 Re-scan after arrival and scene stabilization.

Portal Requirements

- Native Portal cooldown is zero.
- The native Portal button is visible, enabled, and interactable.
- No active Portal already exists.
- The target appears in `GetAvailableMaps(false)`.
- The target is a normal Map, not a Bonus, boss, village, or story map.
- AutoAdventurer never resets or bypasses Portal cooldown.

Minimum Dimension Stay

After automatic arrival, the mod remains in that dimension for at least 10 minutes by default before another automatic departure. This prevents repeated movement among several valid maps.

Map Events

Travel pauses for supported map-bound events including:

- Horde
- Extreme Coins
- Lucky Coins
- Gemstone Rush
- Frenzy
- Dual Randomness

The task lock is retained, while travel-related Rage suppression is released so Rage can serve the event. Task and Portal conditions are re-evaluated after the event.

Detection combines the game's `IsActive()` state, remaining time, and event lifecycle callbacks. A briefly missing Unity object cannot immediately end an event: the last timer and consecutive-miss confirmation protect travel.

Random Boxes

Normal, Silver, Golden, and Special Random Boxes pause travel from the moment their live object appears. After the box clears, the mod checks whether it created an event, minigame entrance, or another world transition. Boxes remain quiet in repeated debug logs; confirmed events log their type.

Keys and Minigame Items

- A Chest Hunt Key stops new Rage refreshes.
- Ascending Heights and Grapple Run trigger items block conflicting Rage/travel preparation.
- Quest scanning freezes inside special scenes and resumes from fresh objects after returning.

Travel Timeout

If arrival is not detected within 60 seconds, the Portal request is released safely and the task can be retried. Possible causes include a missed Portal, an interrupted scene, or a transition that did not complete. A valid task lock is not discarded merely because the travel request timed out.

Bonus, Slider, and Boss Features

Bonus Start Slider

Skip Bonus Start Slider defaults to enabled.

- It runs independently from the Runner/Rage action guard.
- It waits until PopupSlider is visible and fully initialized.
- It invokes confirmation exactly once for each visible slider.
- A later slider can be handled only after the previous one disappears.

Movement Automation in Bonus Content

Automatic jumps, arrows, Boost, and Wind Dash are restricted to the central Runner/Rage scene. Bonus stages, reward sections, and other minigames are excluded so AutoAdventurer does not interfere with their own movement logic.

Auto Boss

Auto Boss defaults to enabled. In a supported boss scene it:

- Resolves the active boss controller.
- Limits boss health to 1 when it is higher.
- Advances required boss dialogue.
- Uses the game's direct arrow action for the finishing attack.
- Avoids a generic contextual action that can become a jump in boss mode.
- Handles the supported result close action.

Disabling the setting leaves boss health, dialogue, and combat untouched.

Quest Automation Interaction

Quest scanning and Portal travel freeze in boss maps, Bonus stages, Chest Hunt, Ascending Heights, and other special scenes. After returning to a stable Runner/Rage scene, the locked task is resolved again from current objects.

Configuration Reference

Configuration file:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\UserData\AutoAdventurer.cfg
```

AutoAdventurer

Setting	Default	Description
Configuration Version	35	Internal migration version; do not edit
Debug Mode	false	All detailed diagnostics, including Quest Automation; user actions, warnings, and errors always log

Automatic Rage

Setting	Default	Description
Toggle Key	K	Toggle Automatic Rage
Stop Key	J	Force-end the current Rage execution
Activation Check Interval Seconds	12	Rage activation and refresh interval
Maximum Rage Duration Seconds	20	Maximum automatic cycle; 0 disables the limit
Post Rage Protection Seconds	8	Shared delay for quests, boxes, events, entrances, travel, and the next Rage

Gameplay

Setting	Default	Description
Skip Bonus Start Slider	true	Confirm supported minigame start sliders
Auto Boss	true	Set boss to 1 HP, advance dialogue, and finish the fight

Auto Movement & Combat

Setting	Default	Description
Enable On Startup	true	Enable movement and combat automation when the game starts
Toggle Key	L	Toggle Auto Movement & Combat
Auto Jump	true	Repeatedly request the shortest possible jump in the central Runner/Rage scene
Auto Shoot Arrows	true	Request arrow attacks while movement automation is enabled
Arrow Attack Frequency	Medium	Light (1/s), Medium (3/s), High (8/s), Extra High (15/s), or Ultra (every rendered frame)
Wind Dash Require Grounded	true	Require ground contact for automatic Wind Dash

Quest Automation

Setting	Default	Description
Toggle Key	P	Toggle quest selection and guided travel
Show Completion Notifications	true	Show in-game session totals; logs remain enabled
Auto Align Elemental Divinities	true	While P is enabled, every five seconds align to the first active elemental task in the live list, correcting manual changes and activating an available affordable element when none is active; this never changes task priority or replaces the current lock
Minimum Dimension Stay Minutes	10	Minimum stay after automatic arrival; actual travel is also limited by Portal cooldown and availability
Maximum Quest Time Minutes	5	Maximum time on one locked task; 0 disables the limit

Silver Box Automation

These global settings run every five seconds after the game loads and do not depend on P or any other hotkey.

Setting	Default	Description
Enabled	true	Master switch for this section; when disabled, both rules are inactive and Silver Bank remains under manual control
Auto Release Silver Box Lock	true	Force Silver Bank off whenever an active normal task requires Silver Random Boxes

Setting	Default	Description
Permanent Release Above Divinity Points	0	Disable Silver Bank above this normalized available-point threshold and enable it again at or below the threshold when affordable; 0 disables threshold control without forcing either state

Example

```
[AutoAdventurer]
"Configuration Version" = 35
"Debug Mode" = false

["Automatic Rage"]
"Toggle Key" = "K"
"Stop Key" = "J"
"Activation Check Interval Seconds" = 12.0
"Maximum Rage Duration Seconds" = 20.0
"Post Rage Protection Seconds" = 8.0

[Gameplay]
"Skip Bonus Start Slider" = true
"Auto Boss" = true

["Silver Box Automation"]
"Enabled" = true
"Auto Release Silver Box Lock" = true
"Permanent Release Above Divinity Points" = 0.0

["Auto Movement & Combat"]
"Enable On Startup" = true
"Toggle Key" = "L"
"Auto Jump" = true
"Auto Shoot Arrows" = true
"Arrow Attack Frequency" = "Medium"
"Wind Dash Require Grounded" = true

["Quest Automation"]
"Toggle Key" = "P"
"Show Completion Notifications" = true
"Auto Align Elemental Divinities" = true
"Minimum Dimension Stay Minutes" = 10.0
"Maximum Quest Time Minutes" = 5.0
```

The movement ability activation delay is an internal 0.2-second safety value and is intentionally not written to the configuration file.

Logging Reference

Log Categories

User Log

Important actions appear without a special debug marker:

```
[AutoAdventurer] Automatic Rage enabled.  
[AutoAdventurer] Quest travel arrived: map=map_factory.  
[AutoAdventurer] Quest completed: ... Session total: ...
```

Main Debug

Enable [AutoAdventurer] Debug Mode:

```
[AutoAdventurer] [Debug][Movement] Ability triggered: selected=WindDash; cooldown=...  
[AutoAdventurer] [Debug][Rage] Automatic Rage blocker detected: Portal ...
```

Detailed messages are grouped by subsystem:

Category	Purpose
Config	Parsed numeric settings and migration results
Runtime	Runtime lifecycle and scene readiness
Movement	Jump, arrow, Boost, Wind Dash, and box-targeting decisions
Rage	Rage readiness, execution, refresh, and blockers
Quest	Quest discovery, selection, locks, travel, and progress
Element	Elemental quest and Dark Divinity alignment
SilverBox	Silver Bank and Silver Random Box task control
Boss	Boss health and result-screen automation
Gameplay	Other global gameplay helpers

Quest and all other diagnostics use the single main Debug Mode setting:

```
[AutoAdventurer] [Debug][Quest] Quest selected: ...
```

Exact repeated Debug messages are emitted at most once every 10 seconds. Warnings and errors use a 30-second duplicate window. When logging resumes, the message includes the number of identical repeats that were suppressed.

Safely caught exceptions produce one concise error line in every mode. The full managed/native exception detail is emitted only when Debug Mode is enabled under [Debug][Exception].

Quest Selection Fields

Field	Meaning
quest	Localized name and internal ID
questType	Internal quest type
objective	Original target ID
matchedEnemy	Current enemy stage selected for the objective
currentMap	Current dimension
targetMap	Planned dimension
mapState	On target or travel required
progress	Current and required amount
remainingKills	Remaining count
unlockReward	Reward Upgrade name and ID
rewardBenefit	Internal reward effect ID
rewardPriority	Top, High, or Normal
requiredCharacter	Required character ID
automaticRageSuppressed	Whether quest state currently blocks new Rage

Common Messages

Travel lock acquired

A destination was selected. New Rage is suppressed while safe travel is prepared.

waiting for Rage Mode to end naturally

Rage is still running and will not be force-ended.

Post-Rage protection scheduled

The mod is waiting for delayed boxes, events, entrances, or a fresh task scan.

Map event detected

Dimension travel is paused and Rage may serve the event.

Quest travel ... timed out

Arrival was not detected within 60 seconds. The request was released safely and can be retried.

automaticRageSuppressed=False

The quest is not blocking Rage. This does not mean the K toggle is enabled. Use the latest Automatic Rage enabled/disabled message.

Garbled Localized Names

Console encoding can display localized quest names incorrectly. Automation does not depend on those strings; internal quest, target, map, and reward IDs remain usable for diagnosis.

Troubleshooting

Automatic Rage Does Not Activate

Check in order:

- 1 The latest toggle message says `Automatic Rage enabled`.
 - 2 No key, Portal, minigame item, or Special Random Box is blocking it.
 - 3 The 2-second post-scene stabilization has completed.
 - 4 No travel, character correction, or arrow task suppresses it.
 - 5 Rage cooldown is ready.
 - 6 The current maximum-duration cycle is not waiting to end naturally.
- `automaticRageSuppressed=False` does not prove that the K toggle is enabled.

Auto Movement & Combat Does Not Activate

- 1 Confirm `Auto Movement & Combat enabled` is the latest toggle state.
- 2 Confirm the selected Boost or Wind Dash is unlocked.
- 3 Wait for ground contact if grounded Wind Dash is enabled.
- 4 Confirm the game is in the central Runner/Rage scene; minigames are excluded.
- 5 After Ascension, wait for the 5-second safety suspension and ability stability checks.

Quest Automation Does Not Travel

Quest Debug may show that the mod is waiting for:

- Native Portal cooldown
- An interactable Portal button
- Rage to end naturally
- Post-Rage protection
- A box, event, key, or entrance
- Minimum dimension-stay time
- A stable supported scene
- A destination in the native Portal list

Quest Selection Looks Wrong

Inspect:

```
rewardPriority=  
remainingKills=  
matchedEnemy=  
targetMap=
```

Ranking is `Top > High > Normal`, then smallest total kill requirement. A task already locked is not replaced merely because a new task appears.

Completion Does Not Advance to the Next Quest

- AutoAdventurer does not claim completed quests.
- Confirm the game or AutoProgression claimed the task.
- The quest list is refreshed only through the safe closed-panel path.
- A manually rerolled Daily is recognized on a later scan.

Portal Timeout

Quest travel ... timed out means arrival was not detected within 60 seconds. The old request is released and can retry. One occasional timeout is normally recoverable; repeated timeouts require the full surrounding log.

Travel Occurred During an Event

Provide log lines containing:

- Map event detected/ended
- Travel lock acquired
- opened a portal
- Event remaining time

Event end requires the last observed timer and consecutive missing checks; one failed Unity lookup must not end the guard.

Freeze or Crash

- 1 Preserve the full MelonLoader log.
- 2 Note the GameState, map, Rage state, and whether a Portal, menu, boss, or Ascension had just occurred.
- 3 Use P, K, and L separately to isolate Quest, Rage, and Boost behavior.
- 4 Never replace the DLL while the game is running.
- 5 Confirm compatible MelonLoader and Idle Slayer Mods Core versions.

What to Include in a Bug Report

- Time of the problem
- Full log file, not only the last error
- Current map and special scene
- Whether P, K, and L were enabled
- Relevant configuration section
- Reproduction steps

Default log directory:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\MelonLoader\Logs\
```