



AutoAdventurer

User Guide

Installation, quick start, controls, and everyday use
Version 2.0.0 | Tashi

AutoAdventurer automates active gameplay in Idle Slayer: quest selection, dimension travel, Rage Mode, Boost/Wind Dash, Bonus helpers, and boss fights.

This guide is written for players who want to install the mod and start using it without reading implementation details. For every setting and diagnostic rule, see the Complete Manual.

What AutoAdventurer Does

- Finds kill quests that your current save can actually complete.
- Prioritizes quests that unlock more quests or other new content.
- Travels to a valid unlocked dimension when the target is elsewhere.
- Automatically uses Rage Mode, Boost, or Wind Dash when enabled.
- Waits safely around keys, boxes, map events, portals, and scene transitions.
- Supports compatible character-specific, arrow, elemental, flyer, giant, and evolved-enemy quests.
- Can skip supported Bonus start sliders and automatically finish boss fights.
- Tracks quests completed during each Quest Automation session.

AutoAdventurer does not claim completed quests. Use the game or AutoProgression to claim them.

Installation

Idle Slayer Mod Manager (recommended)

- 1 Install and initialize Idle Slayer Mod Manager.
- 2 Install Idle Slayer Mods Core.
- 3 Import the AutoAdventurer ZIP without extracting it.
- 4 Enable AutoAdventurer and start the game.

Manual installation

Place AutoAdventurer.dll in:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\Mods\
```

Default Keys

Key	Action
P	Enable or disable Quest Automation
K	Enable or disable Automatic Rage
J	Immediately end the current Rage Mode
L	Enable or disable Auto Movement & Combat

The keys can be changed in AutoAdventurer.cfg.

Recommended First Setup

- 1 Enter a normal running dimension.
- 2 Press K to enable Automatic Rage.

- 3 Auto Movement & Combat starts enabled; press L only if you want to disable or re-enable it.
- 4 Press P to enable Quest Automation.
- 5 Keep completed-quest claiming enabled in AutoProgression if you use both mods.

Automatic Rage and Quest Automation start disabled. Auto Movement & Combat starts enabled by default. Auto Boss and Bonus Slider Skip are configuration-controlled and are also enabled by default.

How Quest Automation Chooses a Task

AutoAdventurer first removes tasks that cannot currently be completed. A task must have a supported kill objective, an unlocked enemy or evolution, an available required character, and a valid normal Portal destination.

Only then does it compare reward priority:

- 1 Top — unlocks additional quest levels.
- 2 High — unlocks equipment, characters, minions, giants, NPCs, loadouts, or another new system.
- 3 Normal — gives a numeric upgrade or no unlock reward.

Within the same priority, the quest with the smallest total kill requirement is selected. Once selected, the task remains locked until it completes, becomes invalid, is replaced, or reaches its configured time limit.

Why the Mod Sometimes Waits

Waiting is usually an intentional safety rule. AutoAdventurer may be waiting for:

- Rage Mode to end naturally.
- The post-Rage protection period.
- The normal Portal cooldown.
- A map event or Random Box outcome.
- A Chest Hunt Key, minigame item, door, or existing Portal.
- A scene transition to finish.
- Wind Dash to reach the ground.
- The minimum stay time after automatic dimension travel.

Except for the manual J key, the mod never force-ends Rage Mode.

Automatic Rage

- Press K once to enable it and again to disable it.
- Disabling it stops future activations but lets the current Rage end naturally.
- Press J only when you intentionally want to end the current Rage immediately.
- Keys, travel preparation, and configured duration limits stop Rage refreshes and wait for the execution to finish naturally.

Auto Movement & Combat

- Press L to enable or disable the complete movement/combat helper.
- Automatic minimum-height jumps and arrow attacks follow their configuration switches and run only in the central Runner/Rage scene.

- The mod follows whichever supported movement ability the player selected.
- Wind Dash can wait for ground contact before activating.
- Bonus stages and other minigames are excluded.

Bonus and Boss Features

- Skip Bonus Start Slider confirms supported timing sliders once they are ready.
- Auto Boss advances supported boss dialogue, reduces the boss to 1 HP, and performs the finishing arrow attack.
- Both features can be disabled independently in the configuration file.

Configuration File

Launch the game once to create:

```
%LOCALAPPDATA%\IdleSlayerModManager\ModLoader\UserData\AutoAdventurer.cfg
```

Useful defaults:

Setting	Default
Rage activation check	12 seconds
Maximum automatic Rage cycle	20 seconds
Post-Rage protection	8 seconds
Movement ability activation delay	0.2 seconds (internal)
Wind Dash requires ground	Enabled
Minimum automatic dimension stay	10 minutes
Maximum time on one quest	5 minutes

See the Configuration Reference for every option.

Quick Troubleshooting

Rage is not activating

Check the log for the last Automatic Rage enabled/disabled message. A quest line containing automaticRageSuppressed=False only means that the quest is not blocking Rage; it does not mean the K toggle is enabled.

Boost or Wind Dash is not activating

Confirm that Auto Movement & Combat is enabled, the selected ability is unlocked, its cooldown is ready, and Wind Dash has reached the ground if required.

Quest Automation is not travelling

It may be waiting for the Portal cooldown, Rage, an event, a box, a scene transition, the minimum stay timer, or an interactable Portal button.

A Portal request timed out

The mod did not detect arrival within 60 seconds. It releases the request safely and can retry the locked task. An occasional timeout is recoverable.

For detailed diagnosis, see Troubleshooting and Logging.

Full Automation Suite

- AutoAdventurer handles active gameplay and quest objectives.
- AutoProgression handles purchases, Ascension, craftables, materials, eggs, and quest claiming.
- AutoClimber handles Ascending Heights routes, rewards, and compatible quest enemies.
- AutoBonusRunner handles supported Bonus Stage routes, recovery, sphere requirements, rewards, and retry.

Each mod works independently. Together, they cover complementary parts of a fully automated Idle Slayer setup.

Support Development

If these mods save you time, you can support continued development through [PayPal](#).