

SURFACE

by MONARO

V0.9.8.1 BETA

USER MANUAL

A shaping processor for drums, hi-hats first: noise, saturation, bit crushing and transient shaping in a reorderable chain, framed by two equalisers and level-matched output.



Contents

1	Introduction	3
	About Surface	3
	System requirements	3

2	Quick start	4
	Installation	4
	Activation and trial	4
	Inserting Surface in your DAW	4
	First five minutes	4

3	Using Surface	5
	Overview	5
	Signal flow	6
	Knobs, sliders and faders	6
	The module chain	6
	Live displays	7

4	Modules	8
	Noise	8
	Saturation	9
	Crusher	10
	Transient	11

5	EQ In and EQ Out	12
----------	-------------------------	-----------

6	Levels: I/O, Auto Gain, Intensity	14
----------	--	-----------

7	Presets, A/B and bypass	14
----------	--------------------------------	-----------

8	Interface settings	15
----------	---------------------------	-----------

9	Technical notes	16
----------	------------------------	-----------

10	License and support	16
-----------	----------------------------	-----------

11	Acknowledgements	17
-----------	-------------------------	-----------

Key combinations are written for macOS first. On Windows, **Cmd** is **Ctrl** and **Option** is **Alt**.
Names of on-screen controls, menus and buttons are set like **this**.

1 Introduction

About Surface

Most of what makes a hi-hat sit in a mix happens in the first few milliseconds and in the texture of its tail: how hard the stick lands, how much air and grit there is around it, how quickly it dies away.

Surface is built around exactly those things. Instead of a general-purpose channel strip it gives you four shaping modules that each change one aspect of a hit, and keeps the result level-matched so you hear the shape, not the volume. It works on any percussive material (snare, shakers, room tracks, drum buses), but its defaults, ranges and detection are tuned for hats and cymbals.

What is in it

■ Noise

White, pink or cassette hiss that follows each hit's envelope, for air and texture.

■ Saturation

Tube (even harmonics first) or Tape (odd harmonics first), oversampled with linear-phase filters.

■ Crusher

Sample-rate and bit-depth reduction from one Amount control, with a tone filter.

■ Transient

Per-hit attack and decay shaping with look-ahead, level-independent detection.

EQ In and EQ Out

Up to five bands each (cuts, shelves, bells, tilt) over a live analyser.

Reorderable chain

Drag the four modules into any order.

Auto Gain

Matches output loudness to input hit by hit, for honest before / after comparisons.

Intensity

One control that scales every module towards neutral at once.

Workflow

Live displays for every module, A/B slots, presets, two themes and five interface sizes.

System requirements

PLATFORM	FORMATS	REQUIREMENTS
macOS	VST3, Audio Unit	macOS 11 Big Sur or later; Apple silicon and Intel (universal binary)
Windows	VST3	Windows 10 or 11, 64-bit host

Surface needs an internet connection once to activate (or to start the trial). After that it runs offline; see License and support. Pro Tools is not supported yet (no AAX version).

2 Quick start

Install, activate, insert Surface on a track and make your first changes.

Installation

macOS

1. Open `Surface-Beta_Installer.pkg`. Because the beta installer is not yet notarised, macOS may block it the first time: open System Settings > Privacy & Security and click Open Anyway.
2. Choose the formats you want (VST3, Audio Unit) and follow the installer. The plugins go to `/Library/Audio/Plug-Ins/VST3` and `/Library/Audio/Plug-Ins/Components`.
3. Restart your DAW and let it rescan plug-ins if it asks.

To uninstall on Windows, use Settings > Apps ("Surface (MONARO)"). On macOS, delete `Surface.vst3` and `Surface.component` from the folders above.

Integrity check Release builds check their own signature; a modified copy shows "This copy of Surface has been modified". Only download Surface from the official release page.

Windows

1. Run `Surface-Beta_Installer.exe` and confirm the administrator prompt. The beta installer is not yet code-signed, so Windows SmartScreen may warn the first time: click More info, then Run anyway.
2. Follow the installer. Surface is installed to `C:\Program Files\Common Files\VST3`, the standard VST3 folder every host scans.
3. Restart your DAW and let it rescan plug-ins if it asks.

Activation and trial

Without a license or trial, Surface passes audio through unchanged and shows the activation sheet when you open it. **License key**: paste or type the key and click Activate; a key can be active on two computers at a time. **Free trial**: click Start free trial for seven days of the full plugin; the status bar counts down the remaining time. To check or move your license later, open the menu (top right) and choose License....

Inserting Surface in your DAW

Surface is an insert effect, mono or stereo. Put it directly on the hi-hat (or drum) track, before any bus processing.

HOST	WHERE TO FIND IT
Logic Pro	Audio FX slot > Audio Units > MONARO > Surface
Ableton Live	Browser > Plug-Ins > VST3 (or Audio Units) > MONARO > Surface; drag onto the track
Cubase / Nuendo	Inserts slot > MONARO > Surface
Studio One	Browser > Effects > MONARO > Surface; drag onto the channel
Reaper	FX button > VST3 (or AU) > Surface (MONARO)
FL Studio	Mixer insert slot > Select > Surface; rescan in Plugin Manager if it is missing
Bitwig Studio	Device browser > MONARO > Surface


First five minutes

1. Loop a section with the hats soloed. Leave **Auto Gain** on (it is on by default): every change you make is level-matched, so louder never fools you into "better".
2. Switch on **Transient** by clicking the dot in its header. Turn Attack up for more stick, down to soften; turn Release down to tighten an open hat.
3. Switch on **Saturation**, try Tube and Tape, and raise Drive until the hats get denser without getting harsh.
4. Add **Noise** at a low Level for air between hits; pick the colour with the arrows on the display.
5. Use **EQ Out** to place the result: a low cut, a little shelf at the top.
6. Compare with **Bypass** (power icon, top right), then pull **Intensity** back until the effect is just right in the mix.

3 Using Surface

Overview

The whole of Surface is on one screen: the display on top shows the selected page, the chain below holds the controls, the header holds the global actions.



Display legend and options

Click a layer to hide it; the chips set speed or resolution.

Live display

The live view of the selected page.

A/B and Copy

Two complete settings slots; Copy duplicates the current one into the other.

Preset browser

Arrows step through presets; the name opens the preset menu.

Type

The module's variant (noise colour, saturation type).

Intensity

Scales every module towards neutral.

Bypass

Smooth bypass of the whole plugin.

Menu

Tooltips, interface size, theme, manual, license, About.

I/O drawer

Shows or hides the In / Out faders, Delta, Link and Auto Gain.

In / Out faders and meters

Input and output gain with peak meters.

EQ In, EQ Out

Thumbnails of the two EQs; click one to edit it in the display.

Module chain

The four modules in processing order; drag a header to reorder.

Module on / off

The dot in each header.


Delta, Link and Auto Gain

See Levels.

Status bar


The version, the trial countdown, short confirmations such as a saved preset; a link when a newer version is available.

Signal flow



- The four modules run in the order shown in the chain; the default order is Noise, Saturation, Crusher, Transient.
- Auto Gain compares the signal after IN gain with the signal after EQ Out, so it undoes the loudness change of the processing only. Your In and Out settings stay as you set them.
- Bypass cross-fades from the processed output to the dry input, delay-compensated, so it never clicks or flams.

Knobs, sliders and faders



Surface keeps numbers out of sight while you listen. A control shows its value only while you move it. The same gestures work on every knob, slider and fader:

Adjust

Drag up / down (knobs, faders) or left / right (sliders), or use the mouse wheel. Hold **Shift** to fine-tune.

Reset to default

Double-click, or **Option**-click (Windows: **Alt**-click).

Type a value


Cmd-click (Windows: **Ctrl**-click) or right-click. **Enter** applies, **Esc** cancels. Units are optional: **-3**, **-3 dB** and **-3dB** all work.

Keyboard

After tabbing to a control: arrows step 1 % (with **Shift** 0.1 %), **Page Up** / **Page Down** 10 %, **Home** resets.

In the EQ band panel, double-clicking a value opens it for typing; **Option** / **Alt**-click resets. Hover over any control with Show tooltips enabled in the menu for a one-line reminder.

The module chain



EQ In on the left, the four modules in processing order, EQ Out on the right.

Select

Click anywhere on a module's column: its display opens above.

Switch on / off

Click the dot in its header. Off modules turn grey but keep their settings; switching fades in and out.

Reorder

Drag a module's header left or right. A bar shows where it will land. The order is saved with the session, presets and A/B slots.

Order matters. Saturating after the noise colours the noise too; crushing before the transient shaper gives the shaper grittier edges to work on; putting Transient first shapes the dry hit before anything else thickens it.

Live displays

Every page has its own live display, fed by the audio while the editor is open (closed editors cost nothing). Click a legend entry (Input, Added, Output, Pre, Post) to hide or show that layer.

Level displays (Noise, Transient)

The input as a grey body, the result as an outline in the module's colour; the gap between them is what the module does. The chip switches between Slow (2 to 16 s) and Fast (0.25 to 2 s). Wheel or pinch zooms time, **Option** / **Alt** + wheel zooms level, double-click resets.

Spectrum displays (Saturation, Crusher)

The input in grey and, in colour, what the module added. Speed sets how quickly it follows, Res its frequency resolution. Drag the frequency scale to zoom and pan.

EQ In / Out



The curve over a pre / post analyser; see EQ In and EQ Out.

4 Modules

Four shaping modules, each changing one aspect of a hit.

Noise

Adds noise that rises and falls with every hit, like extra air or a tape bed that only breathes when the hats play. An envelope follower tracks the input; the noise is shaped by it, so the level is relative to the hit, not absolute.



CONTROL	RANGE	DEFAULT	
Type	White, Pink, Cassette I, Cassette II	White	Colour of the noise (arrows on the display). Cassette I is a clean, bright tape hiss; Cassette II darker and more worn. Both drift very slightly in level and brightness, like a real deck.
Level	-80 ... +18 dB	-12 dB	Noise level relative to the hit. 0 dB (knob centre) is as loud as the hit.
Tone	0 ... 100	50	Tilts the noise dark (left) or bright (right).
Attack	0.1 ... 50 ms	1.0 ms	How fast the noise follows the start of a hit.
Release	5 ... 500 ms	60 ms	How long the noise hangs on after the hit. Longer values fill the gaps between hits.
Width	0 ... 100 %	50 %	Stereo spread, from mono to fully decorrelated. The level stays the same at any width.

Tip A short Release with a fast Attack adds “sizzle” glued to each hit; a long Release with Cassette noise builds a lo-fi bed under a programmed pattern.

■ Saturation

Adds harmonics and rounds peaks. Quiet parts pass through unchanged at any Drive, so Saturation thickens and densifies without changing the tonal balance of the low-level signal. The display shows the input spectrum in grey and, in orange, only what Saturation added: raise Drive and the orange layer grows; change Character and its harmonic balance shifts.





CONTROL	RANGE	DEFAULT	
Type	Tube, Tape	Tube	Tube: even harmonics lead (2nd above 3rd); warm, full, slightly lopsided. Tape: odd harmonics lead (3rd strongest) with a smaller 2nd and a rich upper series; denser and brighter.
Drive	0 ... 36 dB	6 dB	How hard the signal hits the curve.
Character	0 ... 100 %	30 %	Tube: amount of asymmetry, i.e. how much 2nd harmonic. Tape: how much earlier the top end saturates than the rest, like a tape recorder's emphasis.
Mix	0 ... 100 %	100 %	Blend of saturated and clean signal. Both paths are time-aligned, so blending never combs.

The module runs at twice the host sample rate with linear-phase filters: no aliasing harshness, and no phase shift. Below about 200 Hz only the clean signal passes, so the low end of a drum bus stays tight while the top saturates.

Level Because Saturation compresses peaks, a heavily driven signal is quieter at its peaks; Auto Gain makes up for it.

■ Crusher

Digital degradation: sample-rate reduction (aliasing, metallic “ring”) and bit-depth reduction (grain, quantisation noise). Amount sets how deep both go; Rate / Bits sets the balance between them. The purple layer on the display is what the reduction added to the input.





CONTROL	RANGE	DEFAULT	
Amount	0 ... 100 %	50 %	Overall depth of the reduction.
Rate / Bits	Rate 100 ... Both ... Bits 100	Both	Balance between the two: left only reduces the sample rate, right only the bit depth, centre does both fully.
Filter	LP 100 ... Off ... HP 100	Off	One-knob tone filter after the crusher: left darkens (low-pass), right thins (high-pass).

The low end below the crossover stays clean (a phase-matched split), so crushing a full drum loop keeps its weight.

By design Crusher runs at the host rate on purpose: the aliasing is the sound.

■ Transient

Shapes each hit individually. Surface detects every onset independently of level, so quiet ghost notes are treated like accents, and applies a gain envelope to it. On the display the grey body is the input, the blue outline the shaped output: more Attack lifts the outline above the start of each hit, a negative Release pulls its tail in.




CONTROL	RANGE	DEFAULT	
Attack	-100 ... +100 %	0 %	Positive: more punch on each hit. Negative: softer hits.
Release	-100 ... +100 %	0 %	Positive: the hit rings longer. Negative: shorter, tighter tails. It adapts to the length of the hits, so it feels the same on a closed and an open hat.

A constant 0.5 ms look-ahead lets it shape even the very first edge of the hit. Rolls and rattles do not retrigger the shaper, and both channels are linked, so the stereo image never shifts.

Timing The look-ahead latency is the same whether the module is on or off, so switching it never moves the timing.

5 EQ In and EQ Out

Two equalisers frame the modules. **EQ In** prepares the signal before it is shaped (for example, cut the low end so Saturation does not work on bleed); **EQ Out** places the result in the mix. Each has up to five bands and its own on / off dot; click the thumbnail at either end of the chain to edit it in the display.



Q follows the convention of most equalisers: Q 1 is a plain (Butterworth) cut and a bell of about two octaves, so the same numbers give the same curves as in other EQs. The bands follow their analog prototypes all the way up to the top of the spectrum, without the high-frequency squeeze of a standard digital EQ, and with minimum phase. The analyser shows the signal before (Pre) and after (Post) the EQ; Speed and Res set its ballistics and resolution.

Band types

TYPE	SETTINGS
Low Cut / High Cut	Frequency, slope 6, 12, 18 or 24 dB/oct, resonance (the height of its point)
Low Shelf / High Shelf	Frequency, gain ± 18 dB, Q
Bell	Frequency, gain ± 18 dB, Q 0.1 ... 18
Tilt	Centre frequency and gain: tilts the whole spectrum around it

Creating and editing bands

Create

Click an empty spot (far left creates a low cut, far right a high cut, elsewhere a bell). Hovering previews the band.
Click-and-drag on the curve creates a band and moves it.

Move

Drag a point: frequency and gain (cuts: resonance).
Option-drag locks to one axis, **Shift** is fine.

Q and slope

Cmd-drag, or the wheel over a point (cuts: slope). **Cmd**
+ wheel changes gain.

Select

Click a point; **Cmd**-click adds; **Shift**-click selects a range; drag on the background to lasso; **Cmd** **A** selects all, **Esc** none.

Bypass a band

Option-click its point.

Change shape

Cmd **Option**-click cycles the type; **Option** **Shift**-click cycles the slope.

Exact values

Double-click a point to type its frequency. With one band selected, the band panel under it shows all its values.

Context menu

Right-click a point: bypass, shape, copy, delete. Right-click the background: paste.

Delete and nudge


Select and press **Delete**; arrow keys nudge the selection.

Zoom

Drag the frequency scale up / down to zoom, left / right to pan; pinch or **Cmd** + wheel over the background;
Option + wheel zooms the dB scale; double-click the scale resets.

On Windows use **Ctrl** for **Cmd** and **Alt** for **Option**.

6 Levels: I/O, Auto Gain, Intensity



I/O drawer

The I/O button (top right) slides out two faders with peak meters, and the Delta, Link and Auto Gain switches. The meters show peak level in dBFS with a short peak hold; the hold mark turns orange above 0 dBFS.

CONTROL	RANGE	DEFAULT	
In	–24 ... +24 dB	0 dB	Gain into the processing. Driving the input harder makes Saturation and Crusher work harder and changes what the Noise envelope follows.
Out	–24 ... +24 dB	0 dB	Final output gain.
Delta	On / Off	Off	Plays only what Surface changes: the output minus the latency-aligned input (after In gain), level-matched when Auto Gain is on. Out gain still applies. Not stored in presets or A/B slots.
Link	On / Off	Off	Out follows In inversely (output gain = Out – In), so you can push the input into the modules without changing the output level. The Out fader then shows the gain that actually reaches the output. Automation-safe.
Auto Gain	On / Off	On	Matches output loudness to input loudness.

Auto Gain

Auto Gain measures each hit (from one onset to the next) before and after the processing and corrects the level from the next hit on. It never moves inside a hit, so it cannot pump or reshape your transients; after any change the level is right from the next hit. On sustained material without clear hits it updates every 1.5 seconds. For a fresh instance a safety guard keeps the first hits from jumping out while the first measurement is taken.

When to turn it off When you want Saturation or Transient to make the track louder on purpose, or when the next plugin in the chain depends on the absolute level.

Intensity

Intensity (header) scales every module from neutral (0 %) to exactly as set (100 %, default). It is not a dry/wet mix: only each module's main knob is reduced (Noise Level, Saturation Drive, Crusher Amount, Transient Attack and Release), so the character, mix and filter settings stay as you set them and there is no phase combing between a dry and a processed copy. Below 10 % Saturation eases fully to neutral. Use it to dial the whole sound in and out of the mix with one control, or automate it for sections.

7 Presets, A/B and bypass

Presets

Browse

The arrows next to the preset name step to the previous / next preset.

Preset menu

Click the name: Init (all defaults), your presets grouped by folder, Save As..., and Options.

Default

Options > Save as Default makes the current settings the startup state for new instances (badged in the menu); Reset Default returns to the factory start.

Import

Options > Import accepts `.surfacepreset` files or a `.zip` of them; folders inside the archive are recreated.

Presets store every setting including the module order. They are plain files (`*.surfacepreset`), so you can copy, share and organise them in sub-folders. They live in `~/Library/Audio/Presets/MONARO/Surface` (macOS) and

`Documents\MONARO\Surface` (Windows).

A/B

A and B are two complete settings slots, including the module order (Bypass and Delta are not part of a slot). Click the other letter to switch. Copy copies the current slot into the other one, so you can branch off a variation and compare it with the original. Both slots are saved with your session.

Bypass

The power icon bypasses the whole plugin with a short cross-fade. The dry path is delay-compensated, so bypassing never shifts timing. While bypassed, the interface turns monochrome. Bypass is also available to your host as a parameter.

8 Interface settings

All in the menu, top right:

Show tooltips	Short hints when hovering over controls.
Interface size	50, 75, 100, 125 or 150 %. Remembered with the session.
Theme	Graphite or Chalk.
User manual	Opens this document.
License...	Shows the license holder; activate or deactivate this computer.
About	Version and copyright.

9 Technical notes

Latency

Surface reports a constant latency to the host, which compensates it automatically.

SOURCE	LATENCY	REASON
Saturation	97 samples	Linear-phase oversampling filters
Transient	0.5 ms	Look-ahead
Total at 44.1 kHz	≈ 2.7 ms	
Total at 48 kHz	≈ 2.5 ms	

The latency is the same whether modules are on or off and in any order, so switching and reordering never move the timing. For live monitoring through Surface, keep it in mind.

Transparency

With every module off, Surface is bit-transparent apart from the reported delay. A module switched on at neutral settings does not change the frequency response or phase of a quiet signal (within ± 0.05 dB up to 21 kHz at 44.1 kHz). There is no global oversampling and no dry/wet mixing at the plugin level, both deliberate choices to avoid comb filtering.

10 License and support

Your license

Two computers

One license can be active on two computers at a time. To move it, open License... on the old computer and choose Deactivate, then activate on the new one.

Offline use

After activation Surface works offline. It renews its activation in the background when online; it keeps working for at least 45 days without a connection.

Trial

The trial runs for seven days on one computer and is not tied to a key. When it ends, Surface passes audio through unchanged until you activate a license.

Troubleshooting

PROBLEM	SOLUTION
Not in the plugin list	Rescan plug-ins in your host. On macOS check that the formats were selected in the installer. Make sure the host scans the standard VST3 folder.
“This copy has been modified”	Run the installer from the official release page again.
Activation fails	Check the internet connection and the key (copy and paste it). “Limit reached” means two computers are already active: deactivate one.
Level jumps when comparing	Make sure Auto Gain is on; it settles from the next hit after a change.

Support

For help, bug reports and license questions, contact MONARO through the channel you received your license or beta invitation from. Please include your operating system, host and version, and the Surface version shown in About.

11 Acknowledgements

Surface is designed and developed by MONARO. Thanks to everyone who tested the betas and shaped this plugin with their feedback.

Third-party components. JUCE framework, © Raw Material Software Limited, used under its license. Monocypher (cryptography for licensing and integrity), by Loup Vaillant, BSD-2-Clause / CC0. Archivo typeface by Omnibus-Type, SIL Open Font License 1.1.

Trademarks. VST is a registered trademark of Steinberg Media Technologies GmbH. Audio Units, Logic Pro and macOS are trademarks of Apple Inc. All other product names are trademarks of their respective owners and are used only to describe compatibility.

© 2026 MONARO. All rights reserved. This manual describes Surface 0.9.8.1 beta; features and details may change before the final release.