SURFACE by MONARO

V1.0

USER MANUAL

A shaping processor for drums: noise, saturation, bit crushing and transient shaping in a reorderable chain, framed by two equalisers and level-matched output.



© 2026 MONARO

Contents

1 Introduction 3
- About Surface 3
- System requirements 3

2 Quick start 4
- Installation 4
- Activation and trial 4
- Inserting Surface in your DAW 4
- First five minutes 4

3 Using Surface 5
- Overview 5
- Signal flow 6
- Knobs, sliders and faders 6
- The module chain 6
- Live displays 7

4 Modules 8
- Noise 8
- Saturation 9
- Crusher 10
- Transient 11

5 EQ In and EQ Out 12

6 Levels: I/O, Auto Gain, Intensity 14

7 Presets and bypass 15

8 Interface settings 15

9 Technical notes 16

10 License and support 16

11 Acknowledgements 17

Key combinations are written for macOS first. On Windows, `Cmd` is `Ctrl` and `Option` is `Alt`.
Names of on-screen controls, menus and buttons are set like this.

1 Introduction

About Surface

Most of what makes a drum sit in a mix happens in the first few milliseconds and in the texture of its tail: how hard the stick lands, how much air and grit there is around the hit, how quickly it dies away.

Surface has four shaping modules, each changing one aspect of a hit, and matches the output level to the input so that a change in shape is not heard as a change in level. It is made for drums and percussion as a whole: hi-hats and cymbals, snares and rimshots, claps, shakers and percussion loops, room tracks and drum buses. Its detection follows every hit, from a ghost note to an accent.

What is in it

- **Noise**
  White, pink or cassette hiss that follows each hit's envelope, for air and texture.
- **Saturation**
  Tube (even harmonics first) or Tape (odd harmonics first), oversampled with linear-phase filters.
- **Crusher**
  Sample-rate and bit-depth reduction from one Amount control, with a tone filter.
- **Transient**
  Per-hit attack and decay shaping with look-ahead, level-independent detection.

EQ In and EQ Out
Up to five bands each (cuts, shelves, bells, tilt) over a live analyser.

Reorderable chain
Drag the four modules into any order.

Auto Gain
Matches output loudness to input with one steady gain, for fair before / after comparisons.

Intensity
One control that scales every module towards neutral at once.

Workflow
Live displays for every module, factory and user presets, two themes and five interface sizes.

System requirements

PLATFORM	FORMATS	REQUIREMENTS
macOS	VST3, Audio Unit	macOS 11 Big Sur or later; Apple silicon and Intel (universal binary)
Windows	VST3	Windows 10 or 11, 64-bit host

Surface needs an internet connection once to activate (or to start the trial). After that it runs offline; see License and support. Pro Tools is not supported yet (no AAX version).

2 Quick start

Installation

macOS

1. Open `Surface_Installer.pkg`. Because the installer is not yet notarised, macOS may block it the first time: open System Settings > Privacy & Security and click Open Anyway.
2. Choose the formats you want (VST3, Audio Unit) and follow the installer. The plug-ins go to `/Library/Audio/Plug-Ins/VST3` and `/Library/Audio/Plug-Ins/Components`.
3. Restart your DAW and let it rescan plug-ins if it asks.

Windows

1. Run `Surface_Installer.exe` and confirm the administrator prompt. The installer is not yet code-signed, so Windows SmartScreen may warn the first time: click More info, then Run anyway.
2. Follow the installer. Surface is installed to `C:\Program Files\Common Files\VST3`, the standard VST3 folder every host scans.
3. Restart your DAW and let it rescan plug-ins if it asks.

To uninstall on Windows, use Settings > Apps (“Surface (MONARO)”). On macOS, delete `Surface.vst3` and `Surface.component` from the folders above.

Integrity check Release builds check their own signature; a modified copy shows “This copy of Surface has been modified”. Only download Surface from the official release page.

Activation and trial

Without a license or trial, Surface passes audio through unchanged and shows the activation sheet when you open it. **License key:** paste or type the key and click Activate. **Trial:** click Start a 7-day trial under the key field for seven days of the full plug-in; the status bar counts down the remaining time. To check or move your license later, open the menu (top right) and choose License....

Inserting Surface in your DAW

Surface is an insert effect, mono or stereo. Put it directly on a drum or percussion track (hats, snare, clap, a percussion loop) or on a drum bus.

HOST	WHERE TO FIND IT
Logic Pro	Audio FX slot > Audio Units > MONARO > Surface
Ableton Live	Browser > Plug-Ins > VST3 (or Audio Units) > MONARO > Surface; drag onto the track
Cubase / Nuendo	Inserts slot > MONARO > Surface
Studio One	Browser > Effects > MONARO > Surface; drag onto the channel
Reaper	FX button > VST3 (or AU) > Surface (MONARO)
FL Studio	Mixer insert slot > Select > Surface; rescan in Plugin Manager if it is missing
Bitwig Studio	Device browser > MONARO > Surface


First five minutes

1. Loop a section with the drum soloed: a hat, a snare, a clap. Leave **Auto Gain** on (it is on by default): every change you make is level-matched, so louder never fools you into “better”.
2. Switch on **Transient** with the slide switch in its header. Turn Attack up for more stick, down to soften; turn Release down to tighten a ringing snare or open hat.
3. Switch on **Saturation**, try Tube and Tape, and raise Drive until the hits get denser without getting harsh.
4. Add **Noise** at a low Level for air between hits; pick the colour with the tabs at the top of the display.
5. Use **EQ Out** to place the result: a low cut, a little shelf at the top.
6. Compare with **Bypass** (power icon, top right), then pull **Intensity** back until the effect is just right in the mix.

3 Using Surface

Overview

The whole of Surface is on one screen: the display on top shows the selected page, the chain below holds the controls, the header holds the global actions.



Legend and View

Click a layer to hide it; the View chip sets how the display draws.

Live display

The live view of the selected page.

Preset field

Arrows step through presets; click the name for the list.

Type

The module's variant (noise colour, saturation type).

Intensity

Scales every module towards neutral.

Bypass

The power icon: bypasses the whole plug-in with a cross-fade.

Menu

Hints, interface size, theme, manual, license, About; an update when one is available.

I/O drawer

Shows or hides the In / Out faders, Delta, Link and Auto Gain.

In / Out faders and meters

Input and output gain with peak meters.

EQ In, EQ Out

Thumbnails of the two EQs; click one to edit it in the display.

Module chain

The four modules in processing order; drag a header to reorder.

Module on / off

The slide switch at the right of each module header.


Delta, Link and Auto Gain

See Levels.

Status bar

The version, the hint for the control under the mouse, the trial countdown or license state, and a link when a newer version is available.

Signal flow



- The four modules run in the order shown in the chain; the default order is Noise, Saturation, Crusher, Transient.
- Auto Gain compares the signal after In gain with the signal after EQ Out, so it undoes the loudness change of the processing only. Your In and Out settings stay as you set them.
- Bypass cross-fades from the processed output to the dry input, delay-compensated, so it never clicks or flams.

Knobs, sliders and faders



A control shows its value only while you move it. The same gestures work on every knob, slider and fader:

Adjust

Drag up / down (knobs, faders) or left / right (sliders), or use the mouse wheel. Hold Shift to fine-tune.

Reset to default

Cmd-click or Option-click (Windows: Ctrl- or Alt-click).

Type a value

Double-click. Enter applies, Esc cancels. Units are optional: `-3`, `-3 dB` and `-3dB` all work; frequencies take `1.2k`, Crusher's Filter `LP 30`, `HP 30` or `Off`, Rate / Bits `Both`, `R70` or `B70`.

Right-click


Your DAW's own menu for that parameter (show automation, MIDI learn and so on). Where the host has none (Audio Units), a right-click types a value.

Keyboard

On a knob or slider (click it or tab to it): arrows step 1 % (with Shift 0.1 %), Page Up / Page Down 10 %, Home resets.

The In and Out faders move 6 dB per wheel notch. In the EQ band panel, double-clicking a value opens it for typing; Option / Alt-click resets. With Show hints on (menu, on by default), the line at the bottom of the window explains the control under the mouse. Keys 1 to 6 open the pages in chain order, from EQ In to EQ Out.

The module chain



EQ In on the left, the four modules in processing order, EQ Out on the right.

Header

Each module has its name and a slide switch at the right (on: thumb right, in the module's colour). The coloured line under the name lights while the module is on.

Select

Click the name or the module's surface: its page opens in the display.

Switch on / off

Only the switch toggles the module. Off modules sink and their controls fade, but keep their settings; switching fades in and out.

Reorder

Drag a module's header left or right; the neighbours slide aside to make room, and the module stays within the module section. Esc while dragging puts it back. The order is saved with the session and presets.

Saturating after the noise colours the noise too; crushing before the transient shaper gives the shaper grittier edges to work on; putting Transient first shapes the dry hit before anything else thickens it.

Live displays

Every page has its own live display, fed by the audio while the editor is open (the displays stop when the editor is closed). Click a legend entry (Input, Added, Output, Pre, Post) to hide or show that layer. The View chip next to the legend opens the display's options.

Level displays (Noise, Transient)

The input is a grey body. What the module adds is filled in its colour, what it removes is hatched, and the edge of the result is drawn in the same colour. View switches between Static (bars standing still, in time with the song; the wheel shows 1/4, 1/2, 1, 2 or 4 bars) and Dynamic (scrolling; the wheel or a pinch zooms 0.25 to 16 s); Reset zoom returns to the default length. The level scale is fixed, so heights compare across hits; Option / Alt + wheel moves its floor (−84 to −18 dB, default −54 dB), double-click resets. The view you chose last opens next time, in any session (it is not part of a preset).

Page title and kind

The page title sits at the right of the display's top row, dimmed while the module is off. Noise and Saturation choose their kind there (White / Pink / Cassette / Old Cassette; Tube / Tape) with tabs centred in that row: click, or use the mouse wheel over them, one kind per notch.

Spectrum displays (Saturation, Crusher)

The input in grey and, in colour, what the module added. In View, Speed (Fast, Medium, Slow) sets how quickly it follows and Resolution (Low, Medium, High) its detail. The wheel or a pinch zooms the frequency range, Option / Alt + wheel the level range; drag to pan while zoomed or drag the frequency scale; double-click resets.


EQ In / Out


The curve over a pre / post analyser; see EQ In and EQ Out.

4 Modules

Noise

Adds noise that rises and falls with every hit. An envelope follower tracks the input and shapes the noise, so Level is relative to the hit.






CONTROL	RANGE	DEFAULT	
Type	White, Pink, Cassette, Old Cassette	White	Colour of the noise (tabs at the top of the display). Cassette is the steady hiss of a blank Type I tape; Old Cassette a fifty-year-old tape, fuller in the lows with a little more air on top. Both are real recordings, cleaned of clicks and hum.
Level	−80 … +18 dB	−12 dB	Noise level relative to the hit. At 0 dB (knob centre) the noise is as loud as the hit.
Tone	−12 … +12 dB	0 dB	Tilts the noise around 800 Hz: left darker, right brighter. Only the colour changes, the loudness stays.
Attack	0.1 … 50 ms	1.0 ms	How fast the noise comes in. Longer values round off its start, so the hit's own attack comes through first and the noise follows it.
Release	−100 … +100 %	0 %	The noise follows the hit's level. At 0 it lasts exactly as long as the hit; to the left it is shorter, to the right it rings on past the hit, up to one second, and fades out completely by then.
Width	0 … 100 %	50 %	Stereo spread, from mono to fully decorrelated. The level stays the same at any width.

Tip A low Release with a fast Attack adds “sizzle” glued to each hit; a high Release with Cassette noise builds a lo-fi bed under a programmed pattern.

Saturation

Adds harmonics and rounds peaks. Quiet parts pass through unchanged at any Drive, so Saturation thickens the hit without changing the tonal balance of the low-level signal. The display shows the input spectrum in grey and, in orange, only what Saturation added: raise Drive and the orange layer grows; change Character and its harmonic balance shifts.






CONTROL	RANGE	DEFAULT	
Type	Tube, Tape	Tube	**Tube**: even harmonics lead (2nd above 3rd); warm, full, slightly lopsided. **Tape**: odd harmonics lead (3rd strongest) with a smaller 2nd and a rich upper series; denser and brighter.
Drive	0 … 36 dB	6 dB	How hard the signal hits the curve. Higher values add more harmonics.
Character	0 … 100 %	30 %	**Tube**: amount of asymmetry, i.e. how much 2nd harmonic. **Tape**: from new tape (clean until it saturates, firm, odd harmonics) to old tape (bends earlier and softer, warmer 2nd; the top of a loud hit saturates first and loses its edge, a quiet one passes).
Tone	−12 … +12 dB	0 dB	Which part of the sound saturates: up drives the body and keeps the top open and bright, down drives the top so it softens first. Only the saturation moves; the clean balance stays.
Mix	0 … 100 %	100 %	Blend of saturated and clean signal. Both paths are time-aligned, so blending never combs.


The module runs at twice the host sample rate with linear-phase filters and antialiased curves: less aliasing on the top octave and no phase shift. Below about 200 Hz only the clean signal passes, so the low end of a drum bus stays tight while the top saturates.

Level A hit keeps its loudness at any Drive, Character and Tone: the peaks are held and the body comes up, as with driven hardware. Auto Gain matches the rest.

Crusher

Digital degradation: sample-rate reduction (aliasing, metallic “ring”) and bit-depth reduction (grain, quantisation noise). Amount sets how deep both go; Rate / Bits sets the balance between them. The purple layer on the display is what the reduction added to the input.






CONTROL	RANGE	DEFAULT	
Amount	0 … 100 %	50 %	Overall depth of the reduction.
Rate / Bits	Rate 100 … Both … Bits 100	Both	Balance between the two: left only reduces the sample rate, right only the bit depth, centre does both fully.
Filter	LP 100 … Off … HP 100	Off	One-knob tone filter after the crusher, a gentle 6 dB/oct slope: left darkens (low-pass), right thins (high-pass).

The low end below 300 Hz stays clean (a phase-matched split), so crushing a full drum loop keeps its weight.

By design Crusher runs at the host rate on purpose: the aliasing is the sound.

Transient

Shapes each hit individually. Surface detects every onset independently of level, so quiet ghost notes are treated like accents, and applies a gain envelope to it. On the display the grey body is the input, what Transient adds is filled in blue, what it removes is hatched: more Attack fills the start of each hit, a negative Release hatches its tail.






CONTROL	RANGE	DEFAULT	
Attack	−100 … +100 %	0 %	Positive: more punch on each hit. Negative: softer hits.
Release	−100 … +100 %	0 %	Positive: the hit rings longer. Negative: shorter, tighter tails. It adapts to the length of the hits, so it feels the same on a short rimshot and a ringing snare or open hat.

A constant 0.5 ms look-ahead lets it shape even the very first edge of the hit. The rattle of a single hit does not retrigger the shaper, but a clearly louder hit right after a soft pickup or flam gets its own Attack, and with Release turned left a quick second hit inside the first one's tail keeps its level. Both channels are linked, so the stereo image never shifts.

Timing The look-ahead latency is the same whether the module is on or off, so switching it never moves the timing.

5 EQ In and EQ Out

Two equalisers frame the modules. **EQ In** prepares the signal before it is shaped (for example, cut the low end so Saturation does not work on bleed); **EQ Out** places the result in the mix. Each has up to five bands and its own on / off switch; click the thumbnail at either end of the chain to edit it in the display.



Q follows the convention of modern equalisers: Q 1 is a plain (Butterworth) cut and a bell a little over an octave wide, so the same numbers give the same curves as in other EQs. The bands follow their analog prototypes all the way up to the top of the spectrum, without the high-frequency squeeze of a standard digital EQ, and with minimum phase. The analyser shows the signal before (Pre) and after (Post) the EQ; View sets its speed and resolution. Hovering shows the frequency, its note name and the level under the mouse.

Band types

TYPE	SETTINGS
Low Cut / High Cut	Frequency; slope 6, 12, 18, 24, 30, 36, 48, 72 or 96 dB/oct (default 12); resonance (the height of its point)
Low Shelf / High Shelf	Frequency, gain ±18 dB, Q
Bell	Frequency, gain ±18 dB, Q
Tilt	Centre frequency and gain ±18 dB: tilts the whole spectrum around it

Q runs from 0.1 to 18 on every type; a new band starts at Q 1 and, for cuts, 12 dB/oct.

Creating and editing bands

Create

Click an empty spot: at the very edges a cut (below 50 Hz, above 15 kHz), next to them a shelf (up to 120 Hz, from 7 kHz), elsewhere a bell. Hovering previews the band. Click-and-drag on the curve always creates a band and moves it, even with a band selected. Double-clicking the background also adds a band.

Move

Drag a point: frequency and gain. Shift-drag moves it more slowly. Option-drag locks the drag to the axis it starts on. Cmd-drag changes frequency only.

Q and slope

Mouse wheel over a point: Q. On a cut, one notch is one slope step (up steeper, down gentler). Cmd + wheel changes gain, Shift + wheel makes finer steps.

Select

Click a point; Cmd-click adds; Shift-click selects a range; drag on the background to lasso; Cmd A selects all, Esc none.

Bypass a band

Option-click its point.

Change shape

Cmd Option-click cycles the type; Option Shift-click cycles the slope.

Reset and exact values

Double-click a point to reset its gain to 0 dB (on a cut, its Q). Type exact values in the band panel.

Context menu

Right-click a point: bypass or enable, shape, copy, delete. Right-click the background: paste, select all bands, reset zoom.

On Windows use Ctrl for Cmd and Alt for Option.

Delete and nudge

Select and press Delete or Backspace. Arrow keys nudge the selection by 1/12 octave or 0.5 dB (with Shift 1/48 octave or 0.1 dB).

Band panel

The line under the selected band: on / off, shape (the wheel over its icon cycles it), slope for cuts, frequency, gain and Q as numbers to drag or type, the arrows to step to the previous / next band, and delete.


Zoom

Drag the frequency scale up / down to zoom, left / right to pan; pinch or Cmd + wheel over the background; Option + wheel zooms the dB scale; double-click the frequency scale resets the view.

Draw mode

The pencil button at the bottom left of the display switches to draw mode. Sketch a curve and Surface fits bands to it; they replace the bands of that EQ. A part drawn down to −15 dB or lower becomes a cut. The mode ends when you release the mouse; Esc leaves it.

6 Levels: I/O, Auto Gain, Intensity



I/O drawer

The I/O button (top right) slides out two faders with peak meters, and the Delta, Link and Auto Gain switches. The meters show peak level in dBFS and hold the peak for about a second; the hold mark turns red above 0 dBFS. The drawer stays open or closed across sessions.

CONTROL	RANGE	DEFAULT	
In	−24 … +24 dB	0 dB	Gain into the processing. Driving the input harder makes Saturation and Crusher work harder and changes what the Noise envelope follows.
Out	−24 … +24 dB	0 dB	Final output gain.
Delta	On / Off	Off	Plays only what Surface changes: the output minus the latency-aligned input (after In gain), level-matched when Auto Gain is on. Out gain still applies. Not stored in presets.
Link	On / Off	Off	With Link on, the output gain is Out − In: you can push the input into the modules, and moving or automating In does not change the output level. The Out fader shows the gain that reaches the output.
Auto Gain	On / Off	On	Matches output loudness to input loudness.

Auto Gain

Auto Gain applies one gain to the whole signal: a hit recorded 15 dB under the next stays 15 dB under it, so accents and ghost notes keep their ratio. Loudness is judged the way the ear judges it (K-weighted), not by raw peaks.

- **Settings:** the gain follows knob moves and automation within about 20 ms, also while rendering offline.
- **Material:** when only the sound changes (another part of the song), the gain glides to its new value over about a second.
- **Correction:** a slow fine-tuning measured hit by hit and applied only at an onset, never inside a hit, so it cannot pump or reshape transients. On material without clear hits it updates every 1.5 seconds.
- **Limits:** it lifts the level by at most 12 dB. When the processing all but silences the hits (heavy Crusher on very quiet material, a steep high cut) the output stays quieter rather than jumping.

When to turn it off When you want Transient to make the track louder on purpose, or when the next plug-in in the chain depends on the absolute level.

Intensity

Intensity (header) scales every module from neutral (0 %) to exactly as set (100 %, default). It is not a dry/wet mix: only each module's main knob is reduced (Noise Level, Saturation Drive, Crusher Amount, Transient Attack and Release), so the character, mix and filter settings stay as you set them and there is no phase combing between a dry and a processed copy. Below 10 % Saturation eases fully to neutral. Automate it to change the effect between sections.

7 Presets and bypass

Presets

Browse
The arrows next to the preset name step to the previous / next preset.

Preset menu
Click the name: Init (all defaults), the presets grouped by folder, Save As..., and Options.

Factory presets
Six starting points in the Factory folder: hi-hats, an open hat, a clap, percussion and a shaker. They are ordinary preset files: edit, rename or delete them freely; a deleted one does not come back.

Default
Options > Save as Default makes the current settings the startup state for new instances (badged DEFAULT in the menu); Reset Default to Init returns to the factory start.

Import and folder
Options > Import... accepts `.surfacepreset` files or a `.zip` of them; folders inside the archive are recreated. Show Preset Folder opens it in Finder or Explorer.

Presets store every sound setting and the module order; the window size, Bypass and Delta stay as they are in the session. They are plain files (`*.surfacepreset`), so you can copy, share and organise them in sub-folders. They live in `~/Library/Audio/Presets/MONARO/Surface` (macOS) and `Documents\MONARO\Surface` (Windows).

Bypass

The power icon bypasses the whole plug-in with a 20 ms cross-fade. The dry path is delay-compensated, so bypassing never shifts timing. While bypassed, the window darkens and says BYPASSED. Bypass is also available to your host as a parameter.

8 Interface settings

All in the menu, top right:

Update to ...	Only when a newer version is available: opens the update sheet (see below).
Show hints	The line at the bottom of the window says what the control under the mouse does. On by default.
Interface size	50, 75, 100, 125 or 150 %. Remembered with the session.
Theme	Graphite or Chalk; one choice for every session.
User manual	Opens this document.
License...	Shows the license holder; activate or deactivate this computer.
About	Version and copyright.

Updates

Surface checks for a new version when you open it. When there is one, the status bar says so and the update sheet opens once: Download fetches the installer, Skip this version stays quiet until the next one, Remind me later asks again in a day. The sheet links to the release notes.

9 Technical notes

Latency

Surface reports a constant latency to the host, which compensates it automatically.

SOURCE	LATENCY	REASON
Saturation	97 samples	Linear-phase oversampling filters
Transient	0.5 ms	Look-ahead
Total at 44.1 kHz	≈ 2.7 ms	
Total at 48 kHz	≈ 2.5 ms	

The latency is the same whether modules are on or off and in any order, so switching and reordering never move the timing. When you monitor live through Surface, you hear this latency.

Transparency

With every module off, Surface is bit-transparent apart from the reported delay. A module switched on at neutral settings does not change the frequency response or phase of a quiet signal (within ±0.05 dB up to 21 kHz at 44.1 kHz). There is no global oversampling and no dry/wet mixing at the plug-in level, both deliberate choices to avoid comb filtering.

10 License and support

Your license

Computers

A license is active on a set number of computers at a time. To move it, open License… on the old computer and choose Deactivate this computer, then activate on the new one.

Offline use

After activation Surface works offline. It renews its activation in the background when online, and keeps working for 45 days without a connection; after that it asks to connect once.

Trial

The trial runs for seven days on one computer and is not tied to a key. When it ends, Surface passes audio through unchanged until you activate a license.

Troubleshooting

PROBLEM	SOLUTION
Surface is not in my plug-in list	Rescan plug-ins in your host. On macOS check that the formats were selected in the installer. Make sure the host scans the standard VST3 folder.
“This copy has been modified”	Run the installer from the official release page again.
Activation fails	Check the internet connection and the key (copy and paste it). “This key is already active on another computer”: deactivate it there first, or contact us.
“Check the date and time”	The computer’s clock is far off; set it to the correct date and time.
Level jumps when comparing	Make sure Auto Gain is on; it follows a change of settings within about 20 ms.

Support

For help, bug reports and license questions, contact MONARO through the channel you received your license from. Please include your operating system, host and version, and the Surface version shown in About.

11 Acknowledgements

Surface is designed and developed by MONARO. Thanks to everyone who tested the betas.

Recordings. The Cassette and Old Cassette noise are made from recordings by stecman and richwise on Freesound, released under CC0.

Third-party components. JUCE framework, © Raw Material Software Limited, used under its license. Monocypher (cryptography for licensing and integrity), by Loup Vaillant, BSD-2-Clause / CC0. Archivo typeface by Omnibus-Type, SIL Open Font License 1.1.

Trademarks. VST is a registered trademark of Steinberg Media Technologies GmbH. Audio Units, Logic Pro and macOS are trademarks of Apple Inc. All other product names are trademarks of their respective owners and are used only to describe compatibility.

© 2026 MONARO. All rights reserved. This manual describes Surface 1.0.