Oracle® Communications Network Charging and Control

Open Services Development User's and Technical Guide Release 6.0.1

April 2017



Copyright

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

About This Document Document Conventions	
Chapter 1	
System Overview	4
Overview What is Open Services Development?	
Typical OSD Configuration Scenario	
Service Handlers	
Chapter 2	
Getting Started	13
Overview	
Signing on to Open Services Development	
Chapter 3	
Using Open Services Development Scre	ens15
Overview	
Find Screens	
Service Providers	
Operation Sets	
Operations Client ASPs	
Notification Gateway User	
Chapter 4	
Configuration	29
Overview	20
eserv.config Configuration	
acs.conf configuration	
SLEE.config Configuration	
sms.jnlp Configuration	42
Chapter 5	
Background Processes	45
Overview	45
osdInterface	
WSDL Generating Plug-in	
WSDL Regenerator	
Statistics Logged Reports	
Chapter 6	
Troubleshooting	5.2
Overview	

Common Troubleshooting Procedures	53
Chapter 7	
About Installation and Removal	57
Overview	57
Installation and Removal Overview	
Post Install Replication	58
Glossary of Terms	59
Index	65

About This Document

Scope

The scope of this document includes all functionality a user must know in order to effectively operate the Open Services Development application. It does not include detailed design of the service.

Audience

This guide is written primarily for Open Services Development (OSD) administrators. However, the overview sections of the document are useful to anyone requiring an introduction.

Prerequisites

A solid understanding of UNIX and a familiarity with IN concepts are an essential prerequisite for safely using the information contained in this technical guide. Attempting to install, remove, configure or otherwise alter the described system without the appropriate background skills, could cause damage to the system; including temporary or permanent incorrect operation, loss of service, and may render your system beyond recovery.

Although it is not a prerequisite to using this guide, familiarity with the target platform would be an advantage.

This manual describes system tasks that should only be carried out by suitably trained operators.

Related Documents

The following documents are related to this document:

- Advanced Control Services Technical Guide
- Control Plan Editor User's Guide
- Notification Gateway Technical Guide

Document Conventions

Typographical Conventions

The following terms and typographical conventions are used in the Oracle Communications Network Charging and Control (NCC) documentation.

Formatting Convention	Type of Information
Special Bold	Items you must select, such as names of tabs.
	Names of database tables and fields.
Italics	Name of a document, chapter, topic or other publication.
	Emphasis within text.
Button	The name of a button to click or a key to press.
	Example: To close the window, either click Close, or press Esc.
Key+Key	Key combinations for which the user must press and hold down one key and then press another.
	Example: Ctrl+P or Alt+F4.
Monospace	Examples of code or standard output.
Monospace Bold	Text that you must enter.
variable	Used to indicate variables or text that should be replaced with an actual value.
menu option > menu option >	Used to indicate the cascading menu option to be selected.
	Example: Operator Functions > Report Functions
hypertext link	Used to indicate a hypertext link.

Specialized terms and acronyms are defined in the glossary at the end of this guide.

System Overview

Overview

Introduction

This chapter provides a high-level overview of the application. It explains the basic functionality of the system and lists the main components.

It is not intended to advise on any specific Oracle Communications Network Charging and Control (NCC) network or service implications of the product.

In this Chapter

This chapter contains the following topics. What is Open Services Development?......1

What is Open Services Development?

Introduction

Open Services Development (OSD) enables third parties to submit Web Services Description Language (WSDL) files that invoke control plans.


About the Notification Gateway

The NCC Notification Gateway (NGW) receives notifications from Oracle Communications Billing and Revenue Management (BRM Elastic Charging Engine (ECE) and transforms those notifications, via the OSD osdInterface, into messages that NCC can pass to subscribers.

See Notification Gateway Technical Guide for more information about NGW.

Architecture

This diagram shows the OSD architecture within a Oracle Communications Network Charging and Control environment.



Typical OSD Configuration Scenario

Introduction

This example is intended to show the nature of completing an OSD configuration, rather than an exact configuration.

OSD configuration process

Configuration for OSD is an iterative process of:

- 1 Complete Service Provider tab.
- 2 Complete Operation Sets tab.
- 3 Complete Operation tab.

- 4 Complete Client ASP tab.
- If you will be using Notification Gateway to send notifications to subscribers from a third party, set the Notification Gateway username and password.
- Create control plan for each operation.
- Compile control plans.
- 8 Review WSDL through Operation screen (for each control plan).
- **9** Review WSDL through Operation Sets screen for the service supplier.

Example scenario

This scenario uses a control plan that copies data from the incoming Simple Object Access Protocol (SOAP) request to the outgoing SOAP result (this is not very useful but is a good illustration of how the software works).


- This copies from a short integer tag called ShortLO profile field in the incoming session data, which is mapped from the SOAP request, to a tag called ShortOPLO in the outgoing session data, which is mapped to the SOAP result.
- The incoming data is the number 12 in this scenario, see *Incoming SOAP message* (on page 11).
- The data is copied to ShortOPLO and the response returned through an out-going SOAP message. To achieve this:
- The OSD screens are configured as shown. 1
- The control plan is created and compiled.
- The generated WSDL is given to the third party. 3
- The third party uses the WSDL by adding the relevant data, and sending the SOAP message to the OSD interface.
- The OSD interface recognizes what control plan to invoke, see Incoming SOAP message (on page 11)).
- The control plan copies the number and responds to the OSD interface.
- 7 The OSD interface returns a SOAP message to the third party, see Outgoing SOAP message (on page 11)).

Service Providers tab

Here is the Service Providers tab, configured for the scenario.

Notes:


- The UAS port and address configured below must match the VWS eserv.config file triggering section address and port information.
- The InterfaceName must match the configured OSD interface running on the SLC SLEE.



Operation Sets tab

Here is the **Operation Sets** tab, configured for the scenario.


Note: The service to invoke is the capability that will be triggered on the SLC SLEE. For example, if the CCS service loader is used, this field will specify the CCS capability that will be triggered.



Operations tab

Here is the **Operations** tab, configured for the scenario.

Note: The control plan name is populated automatically when this operation is selected for WSDL generation during control plan compilation. The operation should only be enabled after a control plan WSDL has been generated.




Client ASPs tab

Here is the Client ASPs tab, configured for the scenario.

Notes:

- The client ASP name and IP address are the details of the VWS.
- The user name and password information configured must match the triggering operations overrides section of the **eserv.config** file on the VWS.



Control Plan


Here is the control plan for the scenario.



Important: An OSD control plan must contain an Unconditional Terminate or Unconditional Terminate to Pending feature node.

Copy Node Configuration

Here is the Copy node configuration detail for this scenario.



Control plan compilation

When the control plan is compiled, parameters are inserted into the WSDL using the OSD and Copy feature node configuration screens to provide the parameter names:

- "CC_Service_Number" is the number to trigger the control plan which we configured in the ACS Numbers screen
- "ShortLO" is the input which we have to provide in the SOAP message
- "ShortOPLO" is the output which we have to provide in the SOAP message
- "errorCode" is for error messages, so if the functionality is not correct or we have wrong SOAP message the error code will come out in outgoing SOAP messages

The resultant operation segment is generated in three parts:

- soakRequestType
- soakResultType
- soakFaultType

```
<xs:sequence>
    <xs:element name="errorCode" type="xs:int"/>
  </xs:sequence>
</xs:complexType>
```

Operation WSDL

This is the operation generated WSDL code from the control plan compilation.

```
<types>
    <xs:element name="soakRequest" type="soakRequestType"/>
   <xs:element name="soakResult" type="soakResultType"/>
<xs:element name="soakFault" type="soakFaultType"/>
    <xs:complexType name="soakRequestType">
      <xs:sequence>
        <xs:element name="CC Service Number"</pre>
type="xmlns.oracle.com/communications/ncc:NumericString" minOccurs="1"/>
        <xs:element name="ShortLO" type="xmlns.oracle.com/communications/ncc:Short"</pre>
minOccurs="0"/>
      </xs:sequence>
    </xs:complexType>
    <xs:complexType name="soakResultType">
      <xs:sequence>
        <xs:element name="ShortOPLO" type="xmlns.oracle.com/communications/ncc:Short"</pre>
minOccurs="0"/>
      </xs:sequence>
    </xs:complexType>
    <xs:complexType name="soakFaultType">
      <xs:sequence>
        <xs:element name="errorCode" type="xs:int"/>
      </xs:sequence>
    </xs:complexType>
  </types>
  <message name="soakInput">
    <part name="body" element="tns:soakRequest"/>
  <message name="soakOutput">
    <part name="body" element="tns:soakResult"/>
  </message>
  <message name="soakFaultOutput">
    <part name="body" element="tns:soakFault"/>
  </message>
  <portType name="soakPortType">
    <operation name="soakOperation">
      <input message="tns:soakInput"/>
      <output message="tns:soakOutput"/>
      <fault message="tns:soakFaultOutput"/>
    </operation>
  </portType>
  <binding name="soakBinding" type="tns:soakPortType">
    <soap:binding style="document" transport="http://schemas.xmlsoap.org/soap/http"/>
    <operation name="soakOperation">
      <soap:operation soapAction="http://boss-sb-smp/wsdls/OSD/soak/soak"/>
      <input>
        <soap:body use="literal"/>
      </input>
      <output>
        <soap:body use="literal"/>
      </output>
      <fault>
        <soap:body use="literal"/>
      </fault>
    </operation>
  </binding>
```

Operation Set WSDL

This is the full WSDL generated for the operation set.

Note: The "===" lines are not part of the generated file, they mark the start and end lines of the operation WSDL lines.

```
<?xml version="1.0"?>
<definitions name="soak"
  targetNamespace="http://boss-sb-smp/wsdls/OSD/soak.wsdl"
  xmlns:xs="http://www.w3.org/2001/XMLSchema"
  xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/"
  xmlns:tns="http://boss-sb-smp/wsdls/OSD/soak.wsdl"
 xmlns="http://schemas.xmlsoap.org/wsdl/">
  <types>
    <xs:element name="soakRequest" type="soakRequestType"/>
    <xs:element name="soakResult" type="soakResultType"/>
    <xs:element name="soakFault" type="soakFaultType"/>
    <xs:complexType name="soakRequestType">
      <xs:sequence>
        <xs:element name="CC_Service_Number"</pre>
type="xmlns.oracle.com/communications/ncc:NumericString" minOccurs="1"/>
       <xs:element name="ShortLO" type="xmlns.oracle.com/communications/ncc:Short"</pre>
minOccurs="0"/>
      </xs:sequence>
    </xs:complexType>
    <xs:complexType name="soakResultType">
      <xs:sequence>
        <xs:element name="ShortOPLO" type="xmlns.oracle.com/communications/ncc:Short"</pre>
minOccurs="0"/>
      </xs:sequence>
    </xs:complexType>
    <xs:complexType name="soakFaultType">
      <xs:sequence>
        <xs:element name="errorCode" type="xs:int"/>
      </xs:sequence>
    </xs:complexType>
  </types>
  <message name="soakInput">
    <part name="body" element="tns:soakRequest"/>
  </message>
  <message name="soakOutput">
    <part name="body" element="tns:soakResult"/>
  <message name="soakFaultOutput">
    <part name="body" element="tns:soakFault"/>
  </message>
  <portType name="soakPortType">
    <operation name="soakOperation">
      <input message="tns:soakInput"/>
      <output message="tns:soakOutput"/>
      <fault message="tns:soakFaultOutput"/>
    </operation>
  </portType>
  <binding name="soakBinding" type="tns:soakPortType">
    <soap:binding style="document" transport="http://schemas.xmlsoap.org/soap/http"/>
    <operation name="soakOperation">
      <soap:operation soapAction="http://boss-sb-smp/wsdls/OSD/soak/soak"/>
      <input>
        <soap:body use="literal"/>
      </input>
      <output>
        <soap:body use="literal"/>
      </output>
      <fault>
        <soap:body use="literal"/>
      </fault>
    </operation>
```

```
</binding>
========
 <service name="soak">
   <port name="soakPort1" binding="tns:soakBinding">
     <soap:address location="http://eng-host06-z7:6262"/>
   </port>
  </service>
</definitions>
```

Incoming SOAP message

This is the incoming SOAP message used to trigger the control plan.

```
<?xml version="1.0" encoding="UTF-8"?>
<soapenv:Envelope xmlns:soapenv="http://schemas.xmlsoap.org/soap/envelope/"</pre>
xmlns:tags="http://abox-sb-smp/wsdls/OSD/tags.wsdl">
<soapenv:Header/>
  <soapenv:Body>
    <tags:acsTagsRequest xmlns="http://abox-sb-smp/wsdls/OSD/tags.wsdl">
     <!--Optional:-->
      <Short>12</Short>
      <CC Service Number>1234567</CC Service Number>
    </tags:acsTagsRequest>
  </soapenv:Body>
</soapenv:Envelope>
```

Outgoing SOAP message

This is the outgoing SOAP message.

```
<?xml version="1.0"?>
<SOAP-ENV: Envelope
 xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"
  xmlns:xsd="http://www.w3.org/2001/XMLSchema"
 SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding">
  <SOAP-ENV: Body>
    <m:reTestResult xmlns:m="http://abox-sb-smp/wsdls/OSD/reTest.wsdl">
      <ShortOPLO>12</ShortOPLO>
    </m:reTestResult>
  </SOAP-ENV:Body>
</SOAP-ENV:Envelope>
```

Service Handlers

Introduction

Service handlers determine which service is used to invoke a control plan from an OSD WSDL file. Each service handler must match a configured service on the SLC. You associate a service handler with an OSD operation by selecting the service handler from the Service to Invoke list for an operation set in the OSD UI. The list of available services depends on which NCC components are installed on the platform. See *Operations* (on page 22) for more information.

For meanings and uses of the different service handlers, see ACS Technical Guide, CCS Technical Guide, and Notification Gateway Technical Guide.

For information about the mandatory parameters required by the different services, see *Mandatory* Parameters for OSD (on page 45).

OSD service handlers

The following list shows the possible services that you can invoke when you install OSD.

ACS

- ACS_Management
- ACS OSD
- ACS Outgoing
- ACS_Prefix

CCS service handlers

The following list shows the possible Prepaid Charging services that you can invoke through OSD when you install the CCS:

- CCS
- CCS_ROAM
- CCS SM MO
- CCS_SM_MT
- REVERSE_CCS_SM_MT
- CCS DATA
- CCS_MO
- CCS MT
- CCS BPL

NGW Ext Sub service handler

The Notification Gateway uses the Ext_Sub service handler. Ext_Sub handles notifications for external subscribers that are received from the Notification Gateway. The Ext_Sub service maps external balances, such as ECE subscriber balances, to NCC balances. The NCC balances are then used in notification templates referenced by OSD control plans.

See Notification Gateway Technical Guide for information about Ext_Sub service handler configuration.

Getting Started

Overview

Introduction

This chapter explains how to start the Open Services Development (OSD) user interface (UI).

In this chapter

This chapter contains the following topics.

Signing on to Open Services Development

Overview

You access Open Services Development (OSD) by logging into the Service Management System (SMS) and selecting Open Services Development from the Services menu in the Service Management System window. For more information about the SMS user interface, see Service Management System User's Guide.

SMS main screen

Here is an example of the Service Management System main menu showing the Open Services Development menu option.



Using Open Services Development Screens

Overview

Introduction

The Open Services Development (OSD) user interface (UI) enables you to configure how incoming SOAP messages will be handled for any OSD data that is specific to a service provider, that is, one ACS customer. This chapter explains how to configure OSD in the OSD UI.

In this chapter

This chapter contains the following topics.

Find Screens


Introduction

You use the Find screens to locate records in the Operation Sets, Operations and Client ASPs tabs.

While each of these tabs has a different results table, they all use the same mechanism to populate their tables.

Example Find screen

Here is an example find screen with the default results table for the selected service provider.



Using the Find screen

If the **Service Provider** drop down list is present, it can be ignored, unless you are wanting to change provider on all the tabs.

The search text box (**Operation Set Name** in the example) is used to do a search on items beginning with the text typed. For example typing "Weekly" would return all operation sets whose name started with "Weekly".

Note: This search function is case sensitive - "week" would not find anything.

To start the search, click **Search**. All found items replace any previous table contents.

Once the record has been found, click on that table entry and click **Close** to return to the parent tab, which will be populated with the found record details.

Service Providers

Introduction


The Service Providers tab allows you to select a service provider that will have OSD configuration.

Note: Once selected, data for the service provider is propagated to the following tabs:

- Service Providers
- Operation Sets
- Operations

Service Providers tab

Here is an example of the Service Providers tab.



Service Providers fields

This table describes the Service Providers tab fields.

Field	Description
Service Provider	The service provider that an ASP uses for the operation set.
	Note:
	 This will be the same provider for the Service Provider, Operation Sets and Operation tabs.
	 Selection of a different provider changes the screen contents as if Clear had been clicked.
Use Router	Flag to indicate that ASPs using operations belonging to this service provider access OSD through a router such as squid.
	If this flag is selected then the router port and router address are placed in the WSDL file.
	If this flag is not selected then ASPs access OSD on the SLCs directly for these operations. In this case, all the ports and addresses from the SLC ports panel are placed in the WSDL file and the router port and router address are not used.
Router Port	This is a single port in the range 1024 through 65535.
Router Address	Address of the router to use for load sharing.
Protocol	The protocol the ASPs should use to send the SOAP request envelope.

Edit Service Providers

Follow these steps to edit a service provider OSD interaction.

Step Action 1 Select the Service Provider from the drop down list. Note: This is a list of already established service providers (see SMS Main menu > Services > ACS Services > Customers tab. The selected service provider is auto selected in the other tabs. 2 If load sharing is required, select **Use Router** check box, then: Enter the router port in the Router Port field Enter the router address in the Router Address field 3 Select the Protocol to be used: HTTP **HTTPS** Amend the list of SLC ports to receive ASP input from. 4 To add a new port, see Adding SLC ports (on page 18) To change a port, see Editing SLC ports (on page 19)

To delete a port, select the port in the table and click **Remove**

Adding SLC ports

5

5

Follow these steps to add a SLC port.

Click Save

Step Action Click Add. 1 The New Port List Entry screen displays. New Port List Entry Port 1024 Address Interface Name osdInterface Help Cancel Save 2 Enter the new port number in the Port field. You must enter a value in the range 1024 to 65535. Enter the port address in the Address field. You must enter the host name of a SLC 3 running OSD. Enter the interface name in the Interface Name field. You must enter a name that matches 4 the name of a running osdInterface on the SLC, as defined in the SLEE.cfg file. To help improve performance, configure ports for more than one interface.


Click Save.

Editing SLC ports

Follow these steps to edit an existing SLC port list entry.

Step Action 1 Select the port entry that you want to change from the table. 2 Click Edit.

The Edit Port List Entry screen displays.



- 3 (Optional) Enter a different port address in the Address field. You must specify the host name of a SLC running OSD.
- (Optional) Type a different interface name in the Interface Name field. You must enter the 4 name of a running osdInterface on the SLC, as defined in the SLEE.cfg file.
- 5 Click Save.

Operation Sets

Introduction

Operation sets are a collection, for ease of maintainability, of related operations.


The Operation Sets tab is where the selected service provider has all their sets of operations configured.

Each set can have any number of operations (see Operations (on page 22)) and each service provider can have any number of operation sets.

When generated by a control plan compile, all operations for the operation set are inserted into a single WSDL file.

Operation Sets tab

Here is an example of the Operation Sets tab.



Operation Sets fields

This table describes the **Operation Sets** tab fields.

Field	Description
Service Provider	The service provider for this operation set.
	Note:
	This will be the same provider for the Service Provider, Operation Sets and Operation tabs.
	Selection of a different provider changes the screen contents as if Clear had been clicked.
Operation Set	The name of this collection of operations.
Name	Note: There is a special PeriodicCharge set name for use with period charging pro-rating.
WSDL Location	Location of the control plan generated WSDL file for this operation set.
	Note: First part of this is set at installation time in the sms.jnlp file.
WSDL URL	Web URL for the WSDL file.
	Note: This is set at installation time in the sms.jnlp file and in eserv.config -

Field	Description
	wsdlUriBaseName parameter.
Service to Invoke	The service that will be used to invoke the control plan from the WSDL file. This must match a configured service on the SLC to trigger the control plan successfully.
	Note : This list is created at SMS package installation time in a database table. See Service Handlers.
	For meanings and uses of the different service handlers, see ACS Technical Guide, CCS Technical Guide, and Notification Gateway Technical Guide.
Max outstanding Transactions	This is the maximum number of SOAP requests for operations in this operation set that are allowed to be active at any one time.
	Any SOAP requests in excess of this will be rejected with HTTP error 503 (unavailable).

Warning: If either the WSDL location or WSDI URL are modified, then it is up to the user to configure the SMS file system and Apache so that the two are consistent.

Editing Operation Sets


Follow these steps to edit a service provider operation set.

01	A #
Step	Action
1	Select the Service Provider from the drop down list.
	Note:
	 This is a list of already established service providers (see SMS Main menu > Services > ACS Services > Customers tab.
	The selected service provider is auto selected in the other tabs.
2	To set the tab for a new operation set, click Clear.
	To locate an existing operation set for amending, click Find (see <i>Find screens</i> (on page 15)).
	To remove an operation set, click Delete , and then confirm on the Delete Operation Set confirmation dialog.
3	Type the operation set name in the Operation Set Name field.
	Result: The name is inserted into the WSDL file location and URL.
4	Select the Service to Invoke from the drop down list.
	Tip: This should reflect the service the WSDL is going to invoke.
5	Type the maximum allowed outstanding transactions in the Max Outstanding Transactions field.
6	Click Save.

Operations

Operations tab

Here is an example of the Operations tab.



Operations fields

This table describes the **Operations** tab fields.

Field	Description
Service Provider	The service provider for for this operation.
	Note:
	This will be the same provider for the Service Provider, Operation Sets and Operation tabs.
	Selection of a different provider changes the screen contents as if Clear had been clicked.
Operation Name	The name of this operation. This is the name that the control plan uses when generating the WSDL file sub set.
Operation Set	The operation set that this operation will belong to.
	Tip: For periodic charges this must be PeriodicCharge.
Control Plan	The control plan that this WSDL sub set will invoke. This is automatically populated when saving a control plan with this operation name.
Enabled	If an operation is not enabled, the ASP will receive a SOAP fault with error 7 = operation not available.

Editing Operations


Follow these steps to edit a service provider operation.

Step	Action
1	Select the Service Provider from the drop down list.
2	To set the tab for a new operation, click Clear.
	To locate an existing operation for amending, click Find (see <i>Find screens</i> (on page 15)).
	To remove an operation, click Delete , then confirm on the Delete confirmation dialog.
3	Type the operation name in the Operation Name field.
	Result: The name is inserted into the WSDL file location and URL.
4	Select the Operation Set for this operation from the drop down list.
5	Select the Enabled check box.
6	Click Save.
7	Repeat steps 4 to 6 for each operation set that you want to add this operation to.

Client ASPs

Client ASPs tab

Here is an example Client ASPs tab.



Client ASPs fields

This table describes the function of each field.

Field	Description
Client ASP Name	The name of the ASP.
IP Address	The IP address for the ASP.
User Name	The user name for this ASP. The combination of user name and IP address is used to identify the ASP.
Max Tx/Sec	The maximum number of SOAP requests per second this ASP is allowed to send.
	Any SOAP requests in excess of this will be rejected with HTTP error 503 (unavailable).
Max Tx Outstanding	The maximum number of SOAP requests from this ASP that are allowed to be active at any one time.
	Any SOAP requests in excess of this will be rejected with HTTP error 503 (unavailable).
Change Password	The password used to authenticate this ASP.
Confirm Password	This must match Change Password value.

Edit Client ASPs

Follow these steps to edit a client ASP.

Step	Action
1	To amend or delete an ASP, use the Find functionality to locate the required ASP (see <i>Find screens</i> (on page 15)).
2	To add a new ASP, click Clear.
3	Enter the new ASP name in the Client ASP Name field.
4	Enter or change the IP Address.
5	Enter or change the User Name.
6	Enter or change the maximum transaction rate in the Max Tx/Sec field.
7	Enter or change the maximum transaction backlog in the Max Tx Outstanding field.
8	Set the password for the SOAP HTML header in the Change Password and Confirm Password fields.
	Note: Any password will do, but a secure password containing characters and numbers is recommended.
9	Click Save.
	Result: The Add becomes available to do the next step.
10	Maintain the allowed operations for this ASP (see Add Allowed Operations (on page 24)).

Add Allowed Operations

Follow these steps to add an allowed operation.

Step	Action
1	Click Add.
	Result: The Allow Operation for ASP screen appears, with the fields defaulted as follows:

Action Step

- Service provider is the currently selected provider in other tabs
- Operation set is the first in the list for the provider
- Operation is the first in the list for the operation set



2 If required, select a new Service Provider from the drop down list.

> Note: The selected provider is also changed in the other OSD tabs and a prompt is made if there are unsaved changes.

- If required, select the Operation Set from the drop down list. 3
- 4 If required, select the Operation from the drop down list.
- 5 Click Save.

Result: The operation is added to the Allowed Operations table.

Remove Allowed Operations

Follow these steps to remove an allowed operation from this ASP.

Step	Action
1	Select the allowed operation to remove from this ASP from the Allowed Operations table.
2	Click Remove
	Result: The confirmation screen appears.
3	Click Remove to confirm the removal.
	Result: The allowed operation is removed from the list.

Notification Gateway User

Introduction


The notification gateway user enables the Notification Gateway to access OSD remotely. You set the user credentials (username and password) for the notification gateway user on a service provider basis, on the Notification Gateway tab in the OSD UI. The username and password are stored in a secure credentials vault on the SMS.

The Notification Gateway tab is available in the UI only if the <code>jnlp.ECEExtensions</code> Java application property is present and set to <code>true</code> in the /IN/html/sms.jnlp configuration file. See <code>sms.jnlp</code> Configuration (on page 42) for more information.

Note: You can override user credentials by setting the [SERVICE/USER] and [SERVICE/PASS] parameters in the Notification Gateway **config.xml** file. You should set these parameters only if you do not want to store user credentials in the NCC secure credentials vault. See *Notification Gateway Technical Guide* for more information.

Notification Gateway tab

Here is an example Notification Gateway tab.



Setting the Notification Gateway Username and Password

Follow these steps to set the user credentials for the notification gateway user for a selected service provider.

Step	Action
1	Select the Notification Gateway tab in the Open Services Development window.
2	Select the Service Provider from the drop down list.
3	Enter the name of the authorized user of the Notification Gateway in the User Name field.
4	Enter a new password for the user in the Change Password field.
5	Re-enter the password in the Confirm Password field.

Step Action Click Save. 6 **Result:** The user credentials (username and password) are stored in the NCC secure credentials vault on the SMS.

Configuration

Overview

Introduction

This chapter explains how to configure the Oracle Communications Network Charging and Control (NCC) application.

In this chapter

This chapter contains the following topics.

eserv.config Configuration

Introduction

The eserv.config file is a shared configuration file, from which many Oracle Communications Network Charging and Control (NCC) applications read their configuration. Each NCC machine (SMS, SLC, and VWS) has its own version of this configuration file, containing configuration relevant to that machine. The eserv.config file contains different sections; each application reads the sections of the file that contains data relevant to it.

The eserv.config file is located in the /IN/service packages/ directory.

The eserv.config file format uses hierarchical groupings, and most applications make use of this to divide the options into logical groupings.

Configuration File Format

To organize the configuration data within the eserv.config file, some sections are nested within other sections. Configuration details are opened and closed using either { } or [].

- Groups of parameters are enclosed with curly brackets { }
- An array of parameters is enclosed in square brackets []
- Comments are prefaced with a # at the beginning of the line

To list things within a group or an array, elements must be separated by at least one comma or at least one line break. Any of the following formats can be used, as in this example:

```
{ name="route6", id = 3, prefixes = [ "00000148", "0000473"] }
    { name="route7", id = 4, prefixes = [ "000001049" ] }
or
    { name="route6"
        id = 3
        prefixes = [
            "00000148"
```

eserv.config Files Delivered

Most applications come with an example **eserv.config** configuration in a file called **eserv.config.example** in the root of the application directory, for example, /IN/service_packages/eserv.config.example.

Editing the File

Open the configuration file on your system using a standard text editor. Do not use text editors, such as Microsoft Word, that attach control characters. These can be, for example, Microsoft DOS or Windows line termination characters (for example, ^M), which are not visible to the user, at the end of each row. This causes file errors when the application tries to read the configuration file.

Always keep a backup of your file before making any changes to it. This ensures you have a working copy to which you can return.

Loading eserv.config Changes

If you change the configuration file, you must restart the appropriate parts of the service to enable the new options to take effect.

Re-reading the config file

The system will re-read config on a SIGHUP signal and print a status report to standard output on a SIGUSR1 signal.

OSD eserv.config configuration

Here is an example OSD eserv.config section configuration.

```
OSD = {
    osdInterface = {
        allowINSECURESSLv3 = false
        basicRealm = "ASP Account"
        pollTime = 10000
        loadReportingPeriod = 600
        oracleusername = "smf"
        oraclepassword = "smf"
        oracledatabase = "nzwn-test08_SMF"
        overrideWsdlNamespaceAliasErrorCondition = false
        sslCertificateFile = "/IN/service_packages/OSD/sslCertificate.pem"
        sslKeyFile = "/IN/service_packages/OSD/sslKey.pem"
        tssfTimeOutSecs = 10
```

```
persistentConnection = true
       connectionTimeOutSecs = 60
       rateCalculationPeriodSecs = 10
       applicationContext = "0,4,0,0,1,21,3,4"
       validateRequestNameSpace = false
       databaseCachingRules = {
           operationSetsDataExpirySecs = 300
           operationDataExpirySecs = 300
           clientAspDataExpirySecs = 300
           portListsDataExpirySecs = 300
           acsProfileDataExpirySecs = 300
           mandatoryParameterDataExpirySecs = 300
       NumberRules = [
            { prefix="", min=0, max = 100, remove=0, prepend="", resultNoa=4 }
   }
   wsdlUriBaseName = "http://nzwn-test08.uk.oracle.com/wsdls"
   useDeprecatedSchema = false
   maxProfileDetailsAge = 60
   maxServiceHandleAge = 60
   osdWsdlRegenerator = {
       waitTimeSecs = 2
       useOracleAlerts = false
       oracledatabase = "/"
}
```

OSD SLC parameters

Here are the parameters in the osdInterface section of the eserv.config OSD configuration.

Note: osdInterface parameters are only relevant on an SLC.

allowINSECURESSLv3

Syntax: allowINSECURESSLv3 = true|false

Description: Whether to allow use of SSLv3 in the SSL handshake for SSL enabled systems. For

example, set this parameter to true for customers with an ASP that must use the SSLv3

protocol version. Use of SSLv3 and SSLv2 is disabled by default.

Type: Boolean

Optionality: Optional (default used if not set)

true – Use of SSLv3 protocol version enabled. Allowed:

false – Use of SSLv3 protocol version disabled.

Default: false

Notes: The allowINSECURESSLv3 parameter can be set for the DAP, PI and OSD

components. You should set allowINSECURESSLv3 to true if the ASP is able to use

only SSLv3 protocol version. Otherwise set allowINSECURESSLv3 to false.

Example: allowINSECURESSLv3 = true

applicationContext

Syntax: applicationContext = "context"

Description: The application context to specify in IDPs sent to slee_acs.

Type: String

Optionality: Optional (default used if not set). Allowed:

Default: "0,4,0,0,1,21,3,4"

Notes: This should not normally be changed.

Example: applicationContext = "0,4,0,0,1,21,3,4"

basicRealm

Syntax: basicRealm = "realm"

Description: The basic realm to specify in HTTP authentication (401) messages, WWW-

Authenticate header.

Type: String

Optionality: Optional (default used if not set).

Allowed:

Default: "ASP Account"

Notes:

Example: basicRealm = "ASP Account"

connectionTimeOutSecs

Syntax: connectionTimeOutSecs = secondsDescription: The http connection timeout in seconds.

Type: Integer, Decimal, Array, Parameter list, String, Boolean

Optionality: Optional (default used if not set).

Allowed:

Default: • 60 for persistent connection mode

• 10 for single connection mode

Notes: Default depends upon persistentConnection setting.

Example: connectionTimeOutSecs = 60

loadReportingPeriod

Syntax: loadReportingPeriod = seconds

Description: Number of seconds between automatic status reports.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 600

Notes:

Example: loadReportingPeriod = 900

oracledatabase

Syntax: oracledatabase = "database name"

Description: The remote Oracle database to connect to, from the **tnsnames.ora** file.

Type: String

Optionality: Optional (default used if not set)

Allowed:

Default: None

Notes: Usually not specified as it is usual to use the local database.

Example: oracledatabase = "test SMF"

Syntax: oraclepassword = "password"

Description: Oracle password for connecting to the database.

Type: String Optionality: Optional

Allowed: Default:

Notes: Usually the oracleusername and oraclepassword are not specified in

which case the acs_oper operator account will just connect as "/".

Example: oraclepassword = "smf"

oracleusername

Syntax: oracleusername = "user name"

Description: Oracle user name for connecting to the database.

Type: String Optionality: Optional.

Allowed: Default:

Notes: Usually the oracleusername and oraclepassword are not specified in which

case the acs oper operator account will just connect as "/".

oracleusername = "smf" Example:

osdInterface

Syntax: osdInterface = {parm1, parm2...}

Description: The OSD interface parameter list.

Type: List

Optionality: Mandatory

Allowed:

Default: None

Notes: osdInterface parameters are only relevant on an SLC.

osdInterface = { Example: parm 1

parm 2

overrideWsdlNamespaceAliasErrorCondition

Syntax: overrideWsdlNamespaceAliasErrorCondition = true | false

Description: Specifies whether error codes include the WSDL namespace prefix.

Type: Boolean

Optionality: Optional (default used if not set)

true - Error codes do not include the WSDL namespace prefix.. Allowed:

false – Error codes include the WSDL namespace prefix.

Default: false

Notes:

Example: overrideWsdlNamespaceAliasErrorCondition = true persistentConnection

Syntax: persistentConnection = true|false

Description: Run in persistent http connection mode.

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: • true - run in persistent http connection mode

• false - run in single http connection mode

Default: true

Notes:

Example: persistentConnection = true

pollTime

Syntax: pollTime = microseconds

Description: Number of microseconds to wait for a socket connection or SOAP request.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 10000

Notes:

Example: pollTime = 20000

rateCalculationPeriodSecs

Syntax: rateCalculationPeriodSecs = seconds

Description: The number of seconds for which to store transactions when calculating the

transaction rate.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 10

Notes: For example with the default of 10 seconds, and with an allowed rate of 200 per

second, new transactions will be rejected if the number of transactions started in

the last 10 seconds exceeds 2000.

Example: rateCalculationPeriodSecs = 20

sslCertificateFile

Syntax: sslCertificateFile = "location/file name"

Description: Name and location of the SSL certificate file.

Type: String

Optionality: Optional (default used if not set).

Allowed:

Default: "/IN/service packages/OSD/sslCertificate.pem"

Notes: The sslCertificate file must be created manually in order for SSL to work.

Example: sslCertificateFile =

"/IN/service_packages/OSD/sslCertificate.pem"

sslKeyFile

sslKeyFile = "location/name" Syntax:

Description: Name and location of the SSL key file for certificate.

Type: String

Optionality: Optional (default used if not set).

Allowed:

Default: "/IN/service_packages/OSD/sslKey.pem"

Notes: The sslKey file must be created manually in order for SSL to work. sslKeyFile = "/IN/service packages/OSD/sslKey.pem" Example:

tssfTimeOutSecs

Syntax: tssfTimeOutSecs = seconds

Description: The maximum period osdInterface should wait for a response from slee_acs

before giving up and sending a SOAP fault.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 10

Notes:

Example: tssfTimeOutSecs = 20

validateRequestNameSpace

Syntax: validateRequestNameSpace = true|false

Description: Do not allow incorrect WSDL namespace.

Type: Boolean

Optionality: Optional (default used if not set).

true - namespace in the request tag of the incoming request will be Allowed:

ignored.

false - the namespace must match the name space of the operation set.

Default: false

Notes:

Example: validateRequestNameSpace = true

databaseCachingRules

Syntax: databaseCachingRules = {rules}

The list of table re-read time rules Description:

Type: List

Optional (default used if not set). Optionality:

Allowed: Default: Notes:

Example: databaseCachingRules = {

operationSetsDataExpirySecs = 10
operationDataExpirySecs = 10
clientAspDataExpirySecs = 10
portListsDataExpirySecs = 10
acsProfileDataExpirySecs = 10

mandatoryParameterDataExpirySecs = 10

}

Syntax: acsProfileDataExpirySecs = seconds

Description: The maximum age data from ACS_PROFILE_DETAILS table can be before it is

re-read from the database.

Type:

Optionality: Optional (default used if not set).

Allowed:

Default: 10

Notes: Member of the databaseCachingRules (on page 35) section.

Example: acsProfileDataExpirySecs = 300

Syntax: clientAspDataExpirySecs = seconds

Description: The maximum age data from OSD_CLI_ASP and OSD_CLIENT_ASP_ACCESS

tables can be before it is re-read from the database.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 10

Notes: Member of the databaseCachingRules (on page 35) section.

Example: clientAspDataExpirySecs = 300

operationDataExpirySecs

Syntax: operationDataExpirySecs = seconds

Description: The maximum age data from OSD_OPERATION table can be before it is re-read

from the database.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 10

Notes: Member of the databaseCachingRules (on page 35) section.

Example: operationDataExpirySecs = 300

operationSetsDataExpirySecs

Syntax: operationSetsDataExpirySecs = seconds

Description: The maximum age data from OSD OPERATION SET table can be before it is

re-read from the database.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 10

Notes: Member of the databaseCachingRules (on page 35) section.

Example: operationSetsDataExpirySecs = 300

portListsDataExpirySecs

Syntax: portListsDataExpirySecs = seconds

Description: The maximum age data from OSD_PORT_LIST and OSD_PORT_LIST_ENTRY

tables can be before it is re-read from the database.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 10

Notes: Member of the databaseCachingRules (on page 35) section.

Example: portListsDataExpirySecs = 300

mandatoryParameterDataExpirySecs

Syntax: mandatoryParameterDataExpirySecs = seconds

Description: The maximum age that data from the OSD_MANDATORY_INPUT_PARAMETER table

can be before it is re-read from the database.

Type: Integer

Optionality: Optional (default used if not set)

Allowed:

Default: 10

Notes:

Example: mandatoryParameterDataExpirySecs = 300

Syntax: NumberRules = $[\{rule\ 1\}, \{rule\ 2\}...]$

Description: Rules for denormalizing numbers to send to slee_acs in an IDP.

Type: Array of number rules.

Optionality: Optional (default used if not set).

Allowed:

]

1

Notes: The rules below assume that numbers in the XML start with a country code and

should be sent in international format (NOA= 4).

Example: NumberRules = [
{ prefix="", min=0, max = 100, remove=0, prepend="",

resultNoa=4 }

max

Syntax: max = len

Description: The maximum number length.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 999

Notes: Used in number normalization and rules.

Example: max = 32

min

Syntax: min = len

Description: The minimum number length.

Type: Integer

Optional (default used if not set).

Allowed:

Default: C

Notes: Used in number normalization and rules.

Example: min = 4

prefix

Syntax: prefix = "digit"

Description: This rule is applied to numbers with this prefix.

Type: String
Optionality: Optional

Allowed: One or more decimal digits

Default:

Notes: Used in number normalization and rules.

Example: prefix = "25"

prepend

Syntax: prepend= "digits"

Description: Determines the digits that are to be prepended to the number, after stripping any

as specified previously.

Type: String

Optionality:

Allowed:

Default:

Notes: Used in number normalization and rules.

Example: prepend = "1111"

remove

Syntax: remove = num

Description: Determines the number of digits that are stripped from the beginning of the

number.

Type: Integer

Optionality:

Allowed: Default:

Notes: Used in number normalization and rules.

Example: remove = 2

resultNoa

Syntax: resultNoa = noa

Description: Resulting NOA after the normalization.

Type: Optionality: Allowed: Default:

Notes: Used in number normalization and rules.

Example: resultNoa = 4

OSD SMS parameters

Here are the parameters in the OSD section of the eserv.config.

Note: The following parameters are only relevant on an SMS.

```
OSD = {
    wsdlUriBaseName = "http://nzwn-test08.uk.oracle.com/wsdls"
    useDeprecatedSchema = false
    maxProfileDetailsAge = 60
    maxServiceHandleAge = 60
    osdWsdlRegenerator = {
        waitTimeSecs = 2
        useOracleAlerts = false
        oracledatabase = "/"
```

maxProfileDetailsAge

Syntax: maxProfileDetailsAge = seconds

Description: The maximum age data from ACS_PROFILE_DETAILS table can be before it is

re-read from the database.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 60

Notes:

Example: maxProfileDetailsAge = 80

maxServiceHandleAge

Syntax: maxServiceHandleAge = seconds

Description: The maximum age data from OSD_SERVICE_HANDLE and

OSD_MANDATORY_INPUT_PARAMETER tables can be

before data is re-read from the database.

Type: Integer

Optionality: Optional (default used if not set).

Allowed:

Default: 60

Notes:

Example: maxServiceHandleAge = 80

oracledatabase

Syntax: oracledatabase = '[user/password][@connect string]'

Description: Specifies the connection details for connecting to the Oracle database. To

connect to the database on a remote host by using SQLnet, set the oracledatabase parameter to the TNS database connection string; for

example,

oracledatabase = 'smf/smf@SMF'

Type: String

Optionality: Optional (default used if not set)

Allowed: For connections to a local database:

'user/password' or '/'

For connections to a remote database:

user/password@db_sid'

For connections to a local or a remote database by using the Oracle wallet secure external password store:

• '/@connection_string' where connection_string is the alias defined for the user and password credentials in the external password store. This alias can be either a TNS name or a service name from tnsnames.ora.

Default: '/'

Notes:

Example:

Example: oracledatabase = 'smf/smf'

osdWsdlRegenerator

Syntax: osdWsdlRegenerator = {parameter list}

Description: The osdWsdIRegenerator parameters define when a WSDL file that has changed

will be compiled and the user credentials for logging on to the Oracle database.

Type: List

Optionality: Mandatory

useOracleAlerts = true|false
oracledatabase = '[user/password][@connect_string]'

}

Default: See default values for the specific parameter

Notes: To use passwordless connection to the local database on the SMS node, set the

oracledatabase parameter to the default value: '/'.

To connect to a database on a remote host by using SQLnet, set the oracledatabase parameter to the TNS database connection string; for

example,

```
oracledatabase = 'smf/smf@SMF'
osdWsdlRegenerator = {
   waitTimeSecs = 2
```

useOracleAlerts = false
oracledatabase = '/'

}

useDeprecatedSchema

Syntax: useDeprecatedSchema = true|false

Description: Set true to force use of deprecated old product namespace and schema.

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: true, false Default: false

Notes: False means using the xmlns.oracle.com/communications/ncc namespace and

schema.

useDeprecatedSchema = false Example:

useOracleAlerts

Syntax: useOracleAlerts = true|false

Description: Whether to use Oracle alerts.

Type: Boolean Optionality: Mandatory

true - waiting for an Oracle alert Allowed:

false - sleep and re-read OSD_CHANGED_OPERATION_SET

Default: None

Notes:

Example: useOracleAlerts = false

waitTimeSecs

Syntax: waitTimeSecs = seconds

Description: The number of seconds to wait for an Oracle alert or to sleep, depending on the

useOracleAlerts setting.

Type: Integer Optionality: Mandatory

Allowed:

Default: None

Notes:

Example: waitTimeSecs = 2

wsdlUriBaseName

wsdlUriBaseName = "location" Syntax:

Description: The URL of the directory containing the xmlns.oracle.com/communications/ncc.xsd

file.

Type: String Optionality: Required

Allowed:

Default: http://IP of SMS/wsdls

Notes: This must match the corresponding value for the WSDLURL parameter in the

sms.jnlp file.

Example: wsdlUriBaseName = "http://nzwn-test08.uk.oracle.com/wsdls"

High volume configuration

If a large number of XML parameters are expected to be passed between osdInterface and slee_acs then the following configuration should be done:

- 1 Add a number of large SLEE events to SLEE.cfg (to get 500 20K events)

 MAXEVENTS=500 20480
- 2 Add the following to the acsChassis section of acs.conf minimumSizeOfConnectSleeEvent 20480

acs.conf configuration

osd acs.conf configuration

The control plan compiler requires the plug-in **libwsdlGenerator.so** for generating the WSDL file and attaching the control plan to the OSD operation. This configuration is inserted in to the **acs.conf** file on the SMS during installation.

An example acsCompilerDaemon section is shown below.

```
acsCompilerDaemon
CompilerPlugin libwsdlGenerator.so
alertTimeout 3
maxBranches 99
maxNodes 2000
maxCompiledKb 256
compressAtKb 128
compressLevel 1:
```

See Advanced Control Services Technical Guide for more acs.conf information.

SLEE.config Configuration

osd SLEE.config configuration

When OSD is installed, the **SLEE.cfg** file has the following line added by osdScp:

```
INTERFACE=osdInterface osdInterface.sh /IN/service_packages/OSD/bin EVENT However, if you wanted to loadshare across several osdInterface processes on the same SLC, then a line per interface is required, for example, loadsharing across three interfaces would require:
```

```
INTERFACE=osdIf1 osdInterface1.sh /IN/service_packages/OSD/bin EVENT INTERFACE=osdIf2 osdInterface2.sh /IN/service_packages/OSD/bin EVENT INTERFACE=osdIf3 osdInterface3.sh /IN/service packages/OSD/bin EVENT
```

Note: The interface names in the SLC ports table would be then be osdlf1, osdlf2 and osdlf3.

sms.jnlp Configuration

Notification Gateway ECEExtension parameter

The Notification Gateway tab in the OSD UI enables you to set the user credentials for the notification gateway user and to store those credentials securely in a credentials vault on the SMS node. To enable the Notification Gateway tab in the OSD UI, you set the ECEExtensions parameter to true in the sms.jnlp file.

See Notification Gateway Technoical Guide for more information about Notification Gateway configuration.

ECEExtensions

Syntax: See example

Description: Enables the Notification Gateway tab in the OSD UI when present and set to true.

Otherwise the Notification Gateway tab is disabled.

Type: Boolean

Optionality: Optional (default used if not set)

Allowed: true

false or not set

Default: Not set

Notes:

Example: <param name="ECEExtensions" VALUE="true" />

WSDL Parameters

The following two Java application properties are required for WSDL file generation. These parameters are automatically added to the sms.inlp file when you install OSD:

jnlp.osd.WSDLDirectory

jnlp.osd.WSDLURL

For more information about application properties in JNLP files, see Customizing the screens in Service Management System Technical Guide.

WSDLDirectory

Syntax: See example

Description: This is set on install to this value which forms the first part of the Operation Sets

WSDL Location field value.

Type: String Optionality: Required

Allowed:

Default:

Notes: Part of OSD.

If this parameter value is changed, the parameter wsdluriBaseName in the

eserv.config file must also be changed.

<param name="WSDLDirectory" VALUE="/IN/html/wsdls" /> Example:

WSDLURL

Syntax: <param name="WSDLURL" value="url" />

Description: This is set to the WSDL URL field value (same as wsdluriBaseName

> parameter), and has the form of: http://host name/wsdls

Type: String

Optionality: Optional (default used if not set).

Allowed:

Default:

Notes: Part of OSD.

If this parameter value is changed, the parameter wsdluriBaseName in the

eserv.config file must also be changed.

Chapter 4

<param name="WSDLURL" VALUE="http://nzwntest08.uk.oracle.com/wsdls" /> Example:

Background Processes

Overview

Introduction

This chapter explains the processes that are started automatically by Service Logic Execution Environment (SLEE).

Note: This chapter also includes some plug-ins to background processes which do not run independently.

In this chapter

This chapter contains the following topics. WSDL Generating Plug-in47

osdInterface

About the osdinterface

The Open Services Development (OSD) osdInterface is a SLEE interface that accepts SOAP requests from ASPs across a configurable range of TCP/IP ports, and transforms them into IDPs. The IDPs are sent to slee acs in SLEE events, and SOAP responses are then sent to the requesting clients based on the result of the control plan executed in response to the IDP.

The osdInterface also supports heartbeat messages, received in the form of PING requests, and sends a suitable response before closing the connection. The PING messages are used to check if the server is on-line and therefore able to process requests.

The osdInterface rejects requests that do not contain the mandatory parameters, listed in the table below, for the service being used. The interface returns a fault with errorCode 3 ("Missing parameter") when it rejects a request.

Mandatory Parameters for OSD

The following table lists the services that require mandatory parameters, and the mandatory parameters for each service. The table is ordered alphabetically by service.

Service	Mandatory Parameters
ACS	CC Service Number
ACS_Management	CC Service Number
ACS_Notification	CC Calling Party Id
ACS_Outgoing	CC Calling Party Id
ACS_Prefix	CC Service Number

Service	Mandatory Parameters
ccs	CC Calling Party Id
CCS_BPL	CC Calling Party Id
CCS_DATA	CC Calling Party Id
	CC Service Number
CCS_MO	CC Calling Party Id
	CC Service Number
CCS_MT	CC Calling Party Id
	CC Service Number
CCS_ROAM	CC Calling Party Id
	CC Service Number
CCS_SM_MO	CC Calling Party Id
	CC Service Number
CCS_SM_MT	CC Calling Party Id
	CC Service Number
Ext_Sub	CC Calling Party Id
REVERSE_CCS_SM_MT	CC Calling Party Id
	CC Service Number

Cached objects

The osdInterface maintains a cache of configuration objects largely sourced from the database.

Some caches will be augmented with runtime information NOT sourced from the database, but needed to be stored on a per-object basis.

Caching is carried out according to the databaseCachingRules configuration rules. See databaseCachingRule (on page 35)s.

This table lists the caches.

Cache	Description
ASP	Generally sourced from OSD_CLIENT_ASP and OSD_CLIENT_ASP_ACCESS
OperationSet	Generally sourced from OSD_OPERATION_SET
Operation	Fully sourced from OSD_OPERATION
ProfileTag	Fully sourced from ACS_PROFILE_DETAILS and ACS_TAG_TO_PROFILE_MAPPING
SOAPPort	This will be sourced from OSD_PORT_LIST and OSD_PORT_LIST_ENTRY

Throttling

The OSD application uses the osdInterface internal throttling mechanism to reject new requests and return errors. If osdInterface fails to create a SLEE dialog due to overload, it marks itself as overloaded for the rest of the current second.

When overloaded, osdInterface rejects requests to create a SLEE dialog with the following HTTP error:

osdInterface is currently overloaded

SOAP Requests

The osdInterface will bind to the address/port of all connections defined, and process SOAP requests on all those that are not quiescing (that is, all those that have not been dropped from the configuration table since osdInterface last loaded them from there).

When a connection is dropped from the configuration it will not be removed from the cache at the next cache expiry, but merely updated so that its isQuiescing variable is TRUE. A quiescing connection will be destroyed (and removed from the cache) only when its number of outstanding requests falls to zero.

The SOAP document is parsed and extracted tags of relevance are passed to osdInterface.

Note: Not all tags encountered in the document need be understood, or used.

Restrictions

The following restrictions apply to this version of the interface:

- osdInterface receives SOAP requests over HTTP 1.1 over HTTP or HTTPS
- A single SOAP request per connection will be accepted
- Although the WSDL files specify xs:dateTime for some date types, timezones other than GMT are not supported by osdInterface, that is, the only valid date time format is: CCYY-MM-DDThh:mm:ssZ

Heartbeat message

The OSD interface supports ping requests occasionally sent by third-party systems such as M-POS, and responds appropriately before closing the connection.

An HTTP 1.1 POST message with the message body <PING/> is interpreted as a heartbeat message. This message will be responded to with an HTTP 1.1 code 204 response (no content) before closing the connection.

Example ping request:

```
POST http://hostname/ HTTP/1.1
... header fields ...
<PING/>
```

Example OSD response:

HTTP/1.1 204 No Content

WSDL Generating Plug-in

Overview

This plug-in is used to generate WSDL files from control plan compilation.

The plug-in must be configured in acs.conf as:

```
CompilerPlugin libwsdlGenerator.so
```

The complier daemon executes each plug-in in the order they appear in the configuration file, so the order may become important when more than this plug-in is available.

Note: libwsdlGenerator.so is also used for OSD screen configuration changes to regenerate the WSDL file.

WSDL Regenerator

Overview

The WSDL regenerator is used to re-compile WSDL files after any changes made to port lists, operation sets, or operations through the OSD screens.

The re-compile is performed using libwsdlGenerator.so.

Statistics Logged

Overview

Statistics are collected using the smsStats statistics methods at appropriate points in the code.

These sets of statistics are gathered to provide the information necessary for the reports.

OSD statistics

This table lists the statistics collected.

Statistic	Description
ASP_REQUESTS_PROCESSED_SUCCESSFULLY	The number of successful SOAP requests from each Client ASP.
ASP_REQUESTS_RECEIVED	The number of SOAP requests from each Client ASP.
ASP_UNSUCCESSFUL_REQUESTS	The number of unsuccessful SOAP requests from each Client ASP.
TOTAL_REQUESTS_PROCESSED_SUCCESSFULL Y	The number of successful SOAP requests, for the system.
TOTAL_REQUESTS_RECEIVED	The number of SOAP requests, for the system.
TOTAL_UNSUCCESSFUL_REQUESTS	The number of unsuccessful SOAP requests, for the system.

Reports

Overview

The collected statistics are used for reports:

- osd ASp
- osd System

This topic covers what these reports are. For information on generating these reports see the *Report Functions* topic in *Service Management System User's Guide*.

Report Columns

The columns for the reports show:

- The reporting interval
- · The peak requests for either Client ASP or system.
- The total number of requests for either Client ASP or system.

The total number of failed requests for either Client ASP or system.

Peak requests are defined as the maximum number of requests in any on stats collection period.

For example, if the reporting interval is one hour and the stats reporting period is five minutes then the peak requests is the maximum number of requests in any one five minute period during the hour.

osd ASP report

This report provides details on SOAP requests by client ASP.

Report parameters

The table below describes the SMS parameters for this report.

Field	Description	
ASP	The client ASP name, min of 1, max of 64 characters.	
Reporting Period	Day, week, month reporting.	
Interval	nterval Granularity of report lines, min 10 minute intervals.	
Start Date Start date of report. Omitted reports on all statistics collected.		
Hours Since	End date of report. Omitted reports on all statistics collected after Start Date.	

Note: When dates are used, the format is:

YYYYMMDD[HH24[MI[SS]]]

Examples:

- 20090823
- 2009092312
- 200908231225
- 20090823122533

Report example

Here is an example of the OSD ASP Report.

OSD ASP Report

Start Date: 01 January 2008
Finish Date: 01 January 2009

Report Type: Year

ASP: boss

17 August 2009, 21:13:23

Interval	Peak	Requests	Total	Requests	Total	Failed	Requests
20080101000000		0		0			0
20080101002000		0		0			0
20080101003000		0		0			0
20080101004000		0		0			0
20080101005000		0		0			0
20080101010000		0		0			0
20080101011000		0		0			0
20080101012000		0		0			0
20080101013000		0		0			0
20080101015000		0		0			0
20080101020000		0		0			0
20080101021000		0		0			0

osd System report

This report provides details on SOAP requests for the system.

Report parameters

The table below describes the SMS parameters for this report.

Field	Description
Reporting Period3	Day, week, month reporting.
Interval	Granularity of report lines, min 10 minute intervals.
Start Date	Start date of report. Omitted reports on all statistics collected.
Hours Since	End date of report. Omitted reports on all statistics collected after Start Date.

Note: When dates are used, the format is:

YYYYMMDD[HH24[MI[SS]]]

Examples:

- 20090823
- 2009092312
- 200908231225
- 20090823122533

Report example

OSD System Report

Start Date: 01 July 2009 Finish Date: 01 August 2009 Report Type: Month

17 August 2009, 21:30:26

Interval	Peak	Requests	Total	Requests	Total	Failed	Requests
20090701000000		0		0			0
20090701002000		0		0			0
20090701003000		0		0			0
20090701004000		0		0			0
20090701005000		0		0			0
20090701010000		0		0			0
20090701011000		0		0			0
20090701012000		0		0			0
20090701013000		0		0			0
20090701015000		0		0			0
20090701020000		0		0			0

Troubleshooting

Overview

Introduction

This chapter explains the important processes on each of the server components in NCC, and describes a number of example troubleshooting methods that can help aid the troubleshooting process before you raise a support ticket.

In this chapter

This chapter contains the following topics.	
Common Troubleshooting Procedures	53

Common Troubleshooting Procedures

Introduction

Refer to System Administrator's Guide for troubleshooting procedures common to all NCC components.

Checking current processes

You can check which processes are running using the standard UNIX command: ps. To find processes being run by Oracle software, you can grep for the string 'oper', which will display all processes being run by the application operator accounts (for example, acs. oper, ccs. oper and smf. oper).

Note: Some processes which are required for proper functioning may be run by other users, including root or the user which runs the webserver.

Example command: ps -ef | grep oper

For more information about the ps command, see the system documentation for the ps command.

You can also check how much of the processor a process is using by running the standard UNIX tool: top. If you have some baseline measurements, you will be able to compare it with the current load.

Example command: top

Tip: Some processes should only have one instance. If there are two or more instances, this may indicate a problem. For example, there will usually only be one timerIF running on each SLC.

For more information about which processes should be running on each node, check the Process List for each node in Installation Guide.

HTTP Error Codes

The HTTP Error Codes are listed here.

Code	HTTP Code Meaning	Meaning	Recovery
200	HTTP_CODE_OK	Normal response.	None Required.

Code	HTTP Code Meaning	Meaning	Recovery
204	HTTP_CODE_NO_CONTE NT	The osdInterface received a <ping></ping> request. If <ping></ping> appears in the body of the request, the osdInterface will respond with a 204.	Remove <ping></ping> from the request, and retry.
400	HTTP_CODE_BAD_REQUE ST	The request could not be parsed. Either the HTTP headers are invalid, the data does not fit inside internal buffers, or the body does not start with xml.</td <td>If the client is sending a valid SOAP request, this indicates a fault. Otherwise, correct the request syntax and retry the request.</td>	If the client is sending a valid SOAP request, this indicates a fault. Otherwise, correct the request syntax and retry the request.
401	HTTP_CODE_AUTHORISA TION_REQUIRED	OSD requires ASPs to authenticate using Basic Access Authentication.	The client should retry the request with a valid Authorization header.
404	HTTP_CODE_NOT_FOUND	The request namespace was not found, and the request could not be processed.	Correct the namespace specification. It currently must be placed on the SOAP Operation Request element.
500	HTTP_CODE_INTERNAL_S ERVER_ERROR	The server encountered an internal problem and could not continue to process the request.	Usually indicates an internal software fault. Reconciliation may be required.
503	HTTP_CODE_UNAVAILABL E	The service is unable to process the ASPs request at this time. The body of the message may offer additional information.	Correct the problem indicated in the response body and retry.

SOAP release causes

The SOAP release causes are listed here.

Cause	OSD Meaning	Meanings	Recovery
1	No such subscriber	User specified through disconnect node in control plan	
2	No such service	User specified through disconnect node in control plan	
3	Missing parameter	User specified through disconnect node in control plan	
4	Mis-typed parameter	User specified through disconnect node in control plan	
5	System error	User or software specified. The system encountered an unexpected issue processing the response. This is a catch all error, and generally indicates a software fault.	The request may or may not have been completed, reconciliation may be required once the software fault is fixed. The request may or may not work if retried.

Cause	OSD Meaning	Meanings	Recovery
6	Operation does not exist	Software specified. The operation specified in the inbound OSD request is not configured on the SLC. Configure the operation of SMS.	
7	Operation not available	Software specified. The operation specified in the inbound OSD request is not enabled. Enable the operation SMS and retry the research of the operation specified in the operation spe	
8	Invalid transaction type	Software specified. UNUSED	UNUSED
9	Transaction not found	Software specified. UNUSED	UNUSED
10	No response from ACS	Software specified – transient error only, retry permitted. At the time the response was sent, ACS had not provided a response to the interface. This will happen when the system is slow or when it is being shut down.	If it is valid to execute the request multiple times, retry the request. Otherwise, use an agreed reconciliation process.
11	Too many transactions	Software specified – transient error only, retry permitted. UNUSED	UNUSED
12	Duplicate transaction	Software specified. UNUSED	UNUSED
13	Cannot Parse SOAP envelope	Software specified. The request was invalid because: 1 The XML was not valid XML 2 The service key for the operation could not be found	Ensure that the XML being presented to the service is valid, and that the SLC configuration is correct. Once this is confirmed, retry the request.
14	Operation disabled	Software specified. The ASP has insufficient permissions to execute that operation.	Grant access to the operation using the SMS screens and retry the request.
63	Invalid configuration	The request was invalid because a configuration item was incorrectly configured or missing, such as a missing service entry in the acs.conf configuration file.	Check that OSD is correctly configured.

Note: Unless otherwise specified, these error causes are permanent failures and retry should not be attempted by the ASP.

These causes are used in the errorCode parameter of SOAP faults sent to ASPs when failures occur.

For example, if there is a profile branching node on something from Incoming Session data and the data not found branch is used, then there can be a Disconnect Node with cause 3. Then, OSD interface will send a SOAP fault with error code 3 and the ASP will know that the SOAP request has been rejected because of a missing parameter.

About Installation and Removal

Overview

Introduction

This chapter provides information about the installed components for the Oracle Communications Network Charging and Control (NCC) application described in this guide. It also lists the files installed by the application that you can check for, to ensure that the application installed successfully.

In this Chapter

This chapter contains the following topics.	
Installation and Removal Overview	. 57
Post Install Replication	

Installation and Removal Overview

Introduction

For information about the following requirements and tasks, see Installation Guide:

- NCC system requirements
- Pre-installation tasks
- Installing and removing NCC packages

OSD packages

An installation of OSD includes the following packages, on the:

- SMS:
 - osdSms
 - osdCluster (for clustered SMS
- SLC:
 - osdScp

Known issue

Once installation is complete on both nodes of a cluster, the following error may appear:

WARNING: On node <host name> resource group OsdWsdlRegenerator-harg is online but the monitor of resource OsdWsdlRegenerator-hars failed to start

If this happens, enter the following command line to fix the problem:

scswitch -z -g OsdWsdlRegenerator-harg -h The Other Host Name

Post Install Replication

Additional replication

As part of the OSD installation the ACS TAG TO PROFILE MAPPING table replication is added to:

Operator Functions > Node Management > Table Replication > Apps > Acs_Service.

After installation, please ensure ACS_TAG_TO_PROFILE_MAPPING and ACS_PROFILE_DETAIL are replicated to all SLC nodes.

OSD Additional replication

Follow these steps to configure SMS replication to ensure all OSD definitions are available on all SLCs nodes which are running OSD.

For more information about how to complete these steps, see *Service Management System User's Guide*.

Step	Action	
1	Restart SMS Java (Swing) Administration screens.	
2	Open the Table Replication tab on the SMS Node Management screen.	
3	Add the following OSD tables to the SLC nodes which have OSD installed: OSD_CLIENT_ASP OSD_CLIENT_ASP_ACCESS OSD_MANDATORY_INPUT_PARAMETER OSD_OPERATION OSD_OPERATION_SET OSD_PORT_LIST OSD_PORT_LIST_ENTRY	
	OSD_SERVICE_HANDLE	
4	Save the updated node config by clicking Save .	
5	Click Create Config File update the SLCs.	

Glossary of Terms

AAA

Authentication, Authorization, and Accounting. Specified in Diameter RFC 3588.

ACS

Advanced Control Services configuration platform.

ANI

Automatic Number Identification - Term used in the USA by long-distance carriers for CLI.

ASP

- Application Service Provider, or
- Application Server Process. An IP based instance of an AS. An ASP implements a SCTP connection between 2 platforms.

CC

Country Code. Prefix identifying the country for a numeric international address.

CCS

- 1) Charging Control Services component.
- 2) Common Channel Signalling. A signalling system used in telephone networks that separates signalling information from user data.

CLI

Calling Line Identification - the telephone number of the caller. Also referred to as ANI.

cron

Unix utility for scheduling tasks.

DAP

Data Access Pack. An extension module for ACS which allows control plans to make asynchronous requests to external systems over various protocols including XML and LDAP.

Diameter

A feature rich AAA protocol. Utilises SCTP and TCP transports.

DP

Detection Point

DTMF

Dual Tone Multi-Frequency - system used by touch tone telephones where one high and one low frequency, or tone, is assigned to each touch tone button on the phone.

GUI

Graphical User Interface

HTML

HyperText Markup Language, a small application of SGML used on the World Wide Web.

It defines a very simple class of report-style documents, with section headings, paragraphs, lists, tables, and illustrations, with a few informational and presentational items, and some hypertext and multimedia.

HTTP

Hypertext Transport Protocol is the standard protocol for the carriage of data around the Internet.

IDP

INAP message: Initial DP (Initial Detection Point)

IN

Intelligent Network

INAP

Intelligent Network Application Part - a protocol offering real time communication between IN elements.

Initial DP

Initial Detection Point - INAP Operation. This is the operation that is sent when the switch reaches a trigger detection point.

IP

- 1) Internet Protocol
- 2) Intelligent Peripheral This is a node in an Intelligent Network containing a Specialized Resource Function (SRF).

IP address

Internet Protocol Address - network address of a card on a computer.

Messaging Manager

The Messaging Manager service and the Short Message Service components of Oracle Communications Network Charging and Control product. Component acronym is MM (formerly MMX).

MM

Messaging Manager. Formerly MMX, see also *XMS* (on page 63) and *Messaging Manager* (on page 60).

MO

Mobile Originated

MT

Mobile Terminated

NOA

Nature Of Address - a classification to determine in what realm (Local, National or International) a given phone number resides, for the purposes of routing and billing.

PΙ

Provisioning Interface - used for bulk database updates/configuration instead of GUI based configuration.

SCTP

Stream Control Transmission Protocol. A transport-layer protocol analogous to the TCP or User Datagram Protocol (UDP). SCTP provides some similar services as TCP (reliable, in-sequence transport of messages with congestion control) but adds high availability.

Service Provider

See Telco.

Session

Diameter exchange relating to a particular user or subscriber access to a provided service (for example, a telephone call).

SGML

Standard Generalized Markup Language. The international standard for defining descriptions of the structure of different types of electronic document.

SLC

Service Logic Controller (formerly UAS).

SLEE

Service Logic Execution Environment

SMS

Depending on context, can be:

- Service Management System hardware platform
- Short Message Service
- Service Management System platform
- NCC Service Management System application

SOAP

Simple Object Access Protocol. An XML-based messaging protocol.

SRF

Specialized Resource Function – This is a node on an IN which can connect to both the SSP and the SLC and delivers additional special resources into the call, mostly related to voice data, for example play voice announcements or collect DTMF tones from the user. Can be present on an SSP or an Intelligent Peripheral (IP).

SSL

Secure Sockets Layer protocol

SSP

Service Switching Point

System Administrator

The person(s) responsible for the overall set-up and maintenance of the IN.

TCP

Transmission Control Protocol. This is a reliable octet streaming protocol used by the majority of applications on the Internet. It provides a connection-oriented, full-duplex, point to point service between hosts.

Telco

Telecommunications Provider. This is the company that provides the telephone service to customers.

Telecommunications Provider

See Telco.

URL

Uniform Resource Locator. A standard way of specifying the location of an object, typically a web page, on the Internet.

VWS

Oracle Voucher and Wallet Server (formerly UBE).

WSDL

Web Services Description Language.

XML

eXtensible Markup Language. It is designed to improve the functionality of the Web by providing more flexible and adaptable information identification.

It is called extensible because it is not a fixed format like HTML. XML is a `metalanguage' — a language for describing other languages—which lets you design your own customized markup languages for limitless different types of documents. XML can do this because it's written in SGML.

XMS

Three letter code used to designate some components and path locations used by the Oracle Communications Network Charging and Control *Messaging Manager* (on page 60) service and the Short Message Service. The published code is *MM* (on page 60) (formerly MMX).

Index	Edit Service Providers • 18 Editing Operation Sets • 21
Α	Editing Operations • 23 Editing SLC ports • 18, 19
AAA • 59	Editing the File • 30
About Installation and Removal • 57	eserv.config Configuration • 29 eserv.config Files Delivered • 30
About the Notification Gateway • 1	Example Find screen • 16
About the osdInterface • 45	Example scenario • 3
About This Document • v	
ACS • 59	F
acs.conf configuration • 42	Find Screens • 15, 21, 23, 24
Add Allowed Operations • 24 Adding SLC ports • 18	1 IIId Screens * 13, 21, 23, 24
Additional replication • 58	G
allowINSECURESSLv3 • 31	Getting Started • 13
ANI • 59	GUI • 60
applicationContext • 31	301 - 00
Architecture • 2	Н
ASP • 59	Heartbeat message • 47
Audience • v	High volume configuration • 42
D.	HTML • 60
В	HTTP • 60
Background Processes • 45	HTTP Error Codes • 53
basicRealm • 32	
С	ı
· ·	IDP • 60
Cached objects • 46	IN • 60
CC • 59	INAP • 60
CCS • 59	Incoming SOAP message • 3, 11
CCS service handlers • 12	Initial DP • 60
Checking current processes • 53	Installation and Removal Overview • 57
CLI • 59	Introduction • 1, 2, 11, 15, 16, 19, 25, 29, 53, 57
Client ASPs • 23	IP • 60
Client ASPs fields • 24	IP address • 60
Client ASPs tab • 6, 23	K
Common Troubleshooting Procedures • 53	N .
Configuration • 29 Configuration File Format • 29	Known issue • 57
connectionTimeOutSecs • 32	1
Control Plan • 7	-
Control plan compilation • 8	Loading eserv.config Changes • 30
Copy Node Configuration • 8	loadReportingPeriod • 32
Copyright • ii	М
cron • 59	
D	Mandatory Parameters for OSD • 11, 45 mandatoryParameterDataExpirySecs • 37
DAP • 59	max • 37
databaseCachingRules • 35, 36, 37, 46	maxProfileDetailsAge • 39
Diameter • 59	maxServiceHandleAge • 39
Document Conventions • vi	Messaging Manager • 60, 63
DP • 59	min • 38
DTMF • 59	MM • 60, 63
_	MO • 60
E	MT • 61
ECEExtensions • 43 Edit Client ASPs • 24	

Edit Service Providers • 18

Report example • 50, 51 Report parameters • 49, 50
Reports • 48
Re-reading the config file • 30 Restrictions • 47 resultNoa • 39
S
Scope • v SCTP • 61 Service Handlers • 11 Service Provider • 61 Service Providers • 16 Service Providers fields • 17 Service Providers tab • 3, 17 Session • 61 Setting the Notification Gateway Username and Password • 26 SGML • 61 Signing on to Open Services Development • 13 SLC • 61 SLEE • 61 SLEE.config Configuration • 42 SMS • 61 SMS main screen • 13 sms.jnlp Configuration • 26, 42 SOAP • 61 SOAP release causes • 54 SOAP Requests • 47 SRF • 62 SSL • 62
sslCertificateFile • 34 sslKeyFile • 35 SSP • 62 Statistics Logged • 48 System Administrator • 62 System Overview • 1 T
TCP • 62 Telco • 62 Telecommunications Provider • 62 Throttling • 46 Troubleshooting • 53 tssfTimeOutSecs • 35 Typical OSD Configuration Scenario • 2 Typographical Conventions • vi
U
URL • 62
useDeprecatedSchema • 41
useOracleAlerts • 41 Using Open Services Development Screens • 15 Using the Find screen • 16

٧

validateRequestNameSpace • 35 VWS • 62

W

waitTimeSecs • 41
What is Open Services Development? • 1
WSDL • 62
WSDL Generating Plug-in • 47
WSDL Parameters • 43
WSDL Regenerator • 48
WSDLDirectory • 43
wsdlUriBaseName • 41
WSDLURL • 43

X

XML • 62 XMS • 60, 63