# Oracle® Communications Convergent Charging Controller

NP Provisioning Interface Commands Release 12.0.0

December 2017



## Copyright

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be errorfree. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

## Contents

About This Document	
Chapter 1	
PI Commands Overview	1
Overview	
Command List  Parameter Formats	
Chapter 2	
PI Number Portability Package	3
Overview	
Add a Ported Number Range	
Modify a Ported Number Range	
Delete a Ported Number Range	
Query an Active Ported Number Range	
Add a Ported Number Prefix	
Change a Ported Number Prefix	
Query a Ported Number Prefix  Delete a Ported Number Prefix	
Add New LCR Rule Set	
Modify LCR Rule Set	
Delete LCR Rule Set	
Add New LCR Rule	20
Modify LCR Rule	
Delete LCR Rule	
Add Home Routing Entry	
Modify Home Routing Entry	
Delete Home Routing EntryQuery Home Routing Entry	
Chapter 3	
Error Code Lists	33
Overview	33
PI Chassis Errors	
PI Command Errors	34
Glossary of Terms	37
Index	39

### **About This Document**

#### Scope

The scope of this document includes all the information required to configure the NP Service Pack PI commands.

#### **Audience**

The audience for this document includes system administrators responsible for the monitoring, maintenance, and configuration of the Oracle Communications Convergent Charging Controller IN applications.

#### **Prerequisites**

A solid understanding of UNIX and a familiarity with IN concepts are an essential prerequisite for safely using the information contained in this technical guide.

Although it is not a prerequisite to using this guide, familiarity with the target platform would be an advantage.

This manual describes system tasks that should only be carried out by suitably trained operators.

#### **Related Documents**

The following documents are related to this document:

- Provisioning Interface User's and Technical Guide
- Virtual Private Network User's Guide

## **Document Conventions**

## **Typographical Conventions**

The following terms and typographical conventions are used in the Oracle Communications Convergent Charging Controller documentation.

Formatting Convention	Type of Information	
Special Bold	Items you must select, such as names of tabs.	
	Names of database tables and fields.	
Italics	Name of a document, chapter, topic or other publication.	
	Emphasis within text.	
Button	The name of a button to click or a key to press.	
	Example: To close the window, either click Close, or press Esc.	
Key+Key	Key combinations for which the user must press and hold down one key and then press another.	
	Example: Ctrl+P or Alt+F4.	
Monospace	Examples of code or standard output.	
Monospace Bold	Text that you must enter.	
variable	Used to indicate variables or text that should be replaced with an actual value.	
menu option > menu option >	Used to indicate the cascading menu option to be selected.	
	Example: Operator Functions > Report Functions	
hypertext link	Used to indicate a hypertext link.	

Specialized terms and acronyms are defined in the glossary at the end of this guide.

## **PI Commands Overview**

#### **Overview**

#### Introduction

The provisioning interface (PI) uses TCP/IP-based UNIX sockets to receive provisioning commands and parameters. These are translated into SQL commands that update prepaid application tables of the SMF and E2BE Oracle databases. This chapter defines the rules and packages required to translate the provisioning commands into SQL commands.

#### In this chapter

#### **Command List**

#### **Command list**

The following table lists the Number Portability (NP) PI functions and their corresponding commands. To use the NP PI commands the npPISms package must be installed on your system in addition to the standard piSms package.

Function	npPISms
Add a ported number range.	NPDS1=ADD
Modify a ported number range.	NPDS1=CHG
Delete a ported number range.	NPDS1=DEL
Query an active ported number range.	NPDS1=QRY
Add a ported number prefix.	NPYZ1=ADD
Query a ported number prefix.	NPYZ1=QRY
Change a ported number prefix.	NPYZ1=CHG
Delete a ported number prefix.	NPYZ1=DEL
Add new LCR rule set.	NPLC1=ADD
Modify an LCR rule set.	NPLC1=CHG
Delete an LCR rule set.	NPLC1=DEL
Add a new LCR rule.	NPLC2=ADD
Modify an LCR rule.	NPLC2=CHG
Delete an LCR rule.	NPLC2=DEL
Add a new home routing entry.	NPHR1=ADD
Modify a home routing entry.	NPHR1=CHG

Function	npPISms
Delete a home routing entry.	NPHR1=DEL
Query a home routing entry.	NPHR1=QRY

## **Parameter Formats**

## **Number Portability PI Parameter Formats**

This table describes the format of each Number Portability PI parameter.

Parameter	Format
ACTIVATION_DATE	YYYYMMDDHHMMSS (24 hour clock)
ADDITIONAL_RN_ID	One to 8 digit hexadecimal number
CARRIERn (n=1 to 8)	One to 30 character string
CASCADE	Y N
DESCRIPTION	String of up to 64 characters.
DN	Four to 18 digit number.
DN_END	Four to 18 digit number, must be the same length as the associated DN_START value.
DN_START	Four to 18 digit number.
DN_TYPE	H S
DONOR_ID	One to 8 digit hexadecimal number
ENTRY_TYPE	O S
NEW_NAME	String of up to 30 characters.
NUMBER_TYPE	F M Null
PORT_ID	One to 8 digit hexadecimal number
PQYZ	String of up to 18 characters.
ROUTING_DESTINATION	String of up to 64 characters.
ROUTING_NUMBER	String of up to eight characters.
RULE_SET	String of up to 30 characters.
URI	String of up to 50 characters.

## PI Number Portability Package

#### Overview

#### Introduction

This chapter describes the available PI commands for provisioning number portability information on the SMS.

These commands are added by the npPISms package that is installed when you install Convergent Charging Controller. For more information about the PI, and the PI packages, see PI User's and Technical Guide. For more information about Number Portability, see the NP Service Pack Technical Guide and NP Service Pack User's Guide.

#### In this chapter

This chapter contains the following topics. Delete LCR Rule 25 

## Add a Ported Number Range

#### **Description**

Use the NPDS1=ADD PI command to add a new entry to the NP DN RANGE table.

#### Required parameters

This command requires the following parameters.

#### Chapter 2

DN\_START

Syntax: DN START=integer

**Description:** The start of the DN number range.

Type: Integer Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes:

Example: DN START=1230

DN\_END

Syntax: DN END=integer

**Description:** The end of the DN number range.

Type: Integer
Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes: DN END and DN START must be the same length.

Example: DN END=1250

ACTIVATION\_DATE

Syntax: ACTIVATION DATE=date

**Description:** The date the range will become active.

Type: Date String
Optionality: Required

Allowed: A valid date using this format: YYYYMMDDHHMMSS

Default: None

Notes:

Example: ACTIVATION DATE=20080714000000

ENTRY\_TYPE

Syntax:  $ENTRY_TYPE=O \mid S$ Description: The entry type to use.

Type: String

Optionality: Required when adding a ported number range

Allowed: Either:

O – For an operator entry type
 S – For a subscriber entry type

Default: None

Notes:

**Example:** ENTRY TYPE=S

ROUTING NUMBER

Syntax: ROUTING NUMBER=number

Description: The routing number.

Type: Integer Optionality: Required

Allowed: A hexadecimal number between 1 and 8 digits long.

Default: None

Notes:

Example: ROUTING NUMBER=ABC123

### **Optional parameters**

This command accepts the following optional parameters.

NUMBER TYPE

Syntax: NUMBER TYPE=F|M|D|Null value

**Description:** The number type of the DN range.

Type: String

Optionality: Optional (default used if not set)

Allowed: One of the following:

> Null value F - fixed M - mobile

D - delete (see Logic and constraints (on page 9))

Default: Null

Notes:

Example: NUMBER TYPE=F

ADDITIONAL\_RN\_ID

Syntax: ADDITIONAL RN ID=integer

**Description:** The additional routing number for the DN range.

Type: Integer Optionality: Optional

Allowed: A hexadecimal number, 1 to 8 digits long.

Default: None

Notes:

Example: ADDITIONAL RN ID=001

DONOR\_ID

DONOR ID=integer Syntax:

**Description:** The donor ID number for the DN range.

Type: Integer Optionality: Optional

Allowed: A hexadecimal number, 1 to 8 digits long. Must be a defined routing number. Default: None

Notes:

Example: DONOR ID=0011

PORT\_ID

Syntax: PORT ID=integer

**Description:** The port ID number for the DN range.

Type: Integer Optionality: Optional

Allowed: A hexadecimal number, 1 to 8 digits long. Must be a defined routing number.

Default: None

Notes:

Example: PORT ID=001

URI

Syntax: URI=string

**Description:** The uri for the DN range.

Type: String
Optionality: Optional

Allowed: Textual string, 1 to 50 characters long

Default: None

Notes:

**Example:** URI=Uri.com

#### Logic and constraints

The following rules apply when using the NPDS1=ADD command:

- The range defined by DN\_START and DN\_END must not overlap an existing entry of the same entry type in the NP\_DN\_RANGE table, except if DN\_START and DN\_END exactly match a defined range and ACTIVATION\_DATE is different.
- Overlapping ranges of different entry types but the same DN\_START and DN\_END must have a different ACTIVATION\_DATE.
- DN\_START and DN\_END must be the same length, with DN\_END being of equal or higher value.
- ROUTING\_NUMBER must be an existing routing number defined in the NP\_ROUTING\_NUMBER table.
- ADDITIONAL\_RN\_ID must be an existing routing number defined in the NP\_ROUTING\_NUMBER table. The ADDITIONAL\_RN\_ID routing number's associated RD\_ID value must equal the ROUTING NUMBER's associated RD\_ID value.
- DONOR\_ID must be a routing number defined in the NP\_ROUTING\_NUMBER table.
- If the maximum number of activation dates per number range is exceeded, then an error is returned: too many routing numbers for this range.
- If eserv.config contains the item pi.NP.checkRN = "x", and the ROUTING\_NUMBER matches this value "x", then the ADDITIONAL RN ID field must have a non-NULL value.
- If eserv.config contains the item pi.localTZ = "x", then the data specified for ACTIVATION\_DATE will be converted from the local time zone "x" to GMT before being stored in the database.

## **Modify a Ported Number Range**

Changes the entry in the NP\_DN\_RANGE table that matches the supplied DN\_START, DN\_END, ACTIVATION\_DATE and ROUTING NUMBER parameters.

#### **Description**

Use the NPDS1=CHG PI command to modify the entry to the NP DN RANGE table for the specified DN START, DN END and ACTION DATE parameters.

#### Required parameters

This command requires the following parameters.

DN START

Syntax: DN START=integer

**Description:** The start of the DN number range.

Type: Integer Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes:

Example: DN START=1230

DN END

DN END=integer Syntax:

**Description:** The end of the DN number range.

Type: Integer Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes: DN\_END and DN\_START must be the same length.

Example: DN END=1250

ACTIVATION\_DATE

Syntax: ACTIVATION DATE=date

Description: The date the range will become active.

Type: **Date String** Optionality: Required

Allowed: A valid date using this format: YYYYMMDDHHMMSS

Default: None

Notes:

ACTIVATION DATE=20080714000000 Example:

#### **Optional parameters**

This command accepts the following optional parameters.

ENTRY\_TYPE

Syntax: ENTRY\_TYPE=O|S

Description: The entry type to use.

Type: String

Optionality: Required when adding a ported number range

Allowed: Either:

O – For an operator entry type
S – For a subscriber entry type

Default: None

Notes:

**Example:** ENTRY TYPE=S

NUMBER\_TYPE

Syntax: NUMBER\_TYPE=F|M|D|Null value

**Description:** The number type of the DN range.

Type: String

Optionality: Optional (default used if not set)

Allowed: One of the following:

Null valueF - fixedM - mobile

D - delete (see Logic and constraints (on page 9))

Default: Null

Notes:

**Example:** NUMBER TYPE=F

ADDITIONAL\_RN\_ID

Syntax: ADDITIONAL RN ID=integer

**Description:** The additional routing number for the DN range.

Type: Integer Optionality: Optional

Allowed: A hexadecimal number, 1 to 8 digits long.

Default: None

Notes:

Example: ADDITIONAL RN ID=001

DONOR\_ID

Syntax: DONOR ID=integer

**Description:** The donor ID number for the DN range.

Type: Integer Optionality: Optional

Allowed: A hexadecimal number, 1 to 8 digits long. Must be a defined routing number.

Default:

None

Notes:

Example:

DONOR ID=0011

PORT\_ID

Syntax:

PORT ID=integer

Description:

The port ID number for the DN range.

Type:

Integer

Optionality:

Optional

Allowed:

A hexadecimal number, 1 to 8 digits long. Must be a defined routing number.

Default:

None

Notes:

Example:

PORT ID=001

ROUTING\_NUMBER

Syntax:

ROUTING\_NUMBER=number

**Description:** 

The routing number.

Type:

Integer

Optionality:

Required

Allowed:

A hexadecimal number between 1 and 8 digits long.

Default:

None

Notes:

Example:

ROUTING NUMBER=ABC123

URI

Syntax:

URI=string

Description:

The uri for the DN range.

Type:

String

Optionality:

Optional

Allowed:

Textual string, 1 to 50 characters long

Default:

None

Notes:

**Example:** URI=Uri.com

#### Logic and constraints

The following rules apply when using the NPDS1=CHG command:

- The range defined by DN\_START and DN\_END must be an existing entry in the NP\_DN\_RANGE table.
- The ROUTING\_NUMBER must be an existing routing number defined in the NP\_ROUTING\_NUMBER table.
- ADDITIONAL\_RN\_ID must be an existing routing number defined in the NP\_ROUTING\_NUMBER table. The ADDITIONAL\_RN\_ID routing number's associated RD\_ID value must equal the ROUTING NUMBER's associated RD\_ID value.
- DONOR ID must be a routing number defined in the NP ROUTING NUMBER table.

- If an optional parameter needs to be removed or blanked, set the value to "null" or "NULL". The
  exceptions are ROUTING NUMBER and ENTRY TYPE, which
- must have a value.
- If changing a DN range to ENTRY\_TYPE=O, set DONOR\_ID=null if a DONOR\_ID is already set.
- If eserv.config contains the item pi.NP.checkRN = "x", and the ROUTING\_NUMBER matches this value "x", the ADDITIONAL\_RN\_ID field must have a non-NULL value.
- If eserv.config contains the item pi.localTZ = "x", the data specified for ACTIVATION\_DATE will be converted from the local time zone "x" to GMT before being stored in the database.
- If an entry needs to be removed, set the value for the ROUTING\_NUMBER to "null" or "NULL" and the NUMBER\_TYPE parameter value to D or d.

## **Delete a Ported Number Range**

#### **Description**

Use the NPDS1=DEL PI command to delete the entry in the NP\_DN\_RANGE table for the specified parameters.

#### Required parameters

This command requires the following parameters.

DN\_START

Syntax: DN START=integer

**Description:** The start of the DN number range.

Type: Integer
Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes:

Example: DN\_START=1230

DN\_END

Syntax: DN END=integer

**Description:** The end of the DN number range.

Type: Integer
Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes: DN END and DN START must be the same length.

Example: DN\_END=1250

#### **Optional parameters**

This command accepts the following optional parameters.

ENTRY TYPE

Syntax: ENTRY TYPE=O|S

The entry type to use. **Description:** 

Type: String

Optionality: Required when adding a ported number range

Allowed: Either:

> O – For an operator entry type S – For a subscriber entry type

Default:

None

Notes:

ENTRY TYPE=S Example:

ACTIVATION DATE

Syntax: ACTIVATION DATE=date

Description: The date the range will become active.

Type: **Date String** Optionality: Required

Allowed: A valid date using this format: YYYYMMDDHHMMSS

Default: None

Notes:

ACTIVATION DATE=20080714000000 Example:

### Logic and constraints

The following rules apply when using the NPDS1=ADD command:

- The range defined by DN\_START and DN\_END must be an existing entry in the NP\_DN\_RANGE table.
- If eserv.config contains the item pi.localTZ = "x", then the data specified for ACTIVATION DATE will be converted from the local time zone "x" to GMT before being used to look up the row in the database.

## **Query an Active Ported Number Range**

#### **Description**

Use the command NPDS1 and action QRY to query an entry in the NP DN RANGE table for the Active Ported Number Range (APNR) of a number.

#### Required parameters

This command requires the following parameters.

DN

Syntax: DN=integer

Description: The destination number to query. The DN must be within the required DN range.

Type: Integer Optionality: Required

Allowed: Number, 4 to 18 digits long

Default: None

Notes:

**Example:** DN=4124

#### **Optional parameters**

This command accepts the following optional parameters.

ENTRY\_TYPE

Syntax:  $ENTRY_TYPE=O \mid S$ Description: The entry type to use.

Type: String

Optionality: Optional (default used if not set)

Allowed: Either:

O – For an operator entry type.
S – For a subscriber entry type.

Default: S

Notes: If the DN is provisioned in both an Operator and Subscriber DN range that overlap each

other, ENTRY\_TYPE=O must be used to show the Operator DN range.

**Example:** ENTRY TYPE=S

#### Logic and constraints

The following rules apply to the NPDS1=QRY command:

- The subscriber or operator name as defined by NAME must not be blank, and must not match an
  existing subscriber or operator.
- The range defined by DN\_START and DN\_END must not overlap an already defined range which has the same ENTRY\_TYPE.
- DN END must be the same length as DN START.
- ENTRY\_TYPE must be either 'S' for subscriber, or 'O' for operator.

#### Add a Ported Number Prefix

### **About Adding Ported Number Prefixes by Using Pl**

Use the NPYZ1=ADD PI command to add a ported number prefix definition to the NP database. To successfully add a ported number prefix definition, you must specify either the ROUTING\_NUMBER or the ROUTING DESTINATION parameter in the command. If you specify:

- Only the ROUTING\_NUMBER parameter, then ROUTING\_DESTINATION is automatically set to the routing destination that matches the specific routing number.
- Only the ROUTING\_DESTINATION parameter, then a routing number is not associated with the
  prefix in the PQYZ parameter and a prefix is not added to the number if it is matched during porting.
- Both the ROUTING\_DESTINATION and the ROUTING\_NUMBER parameters, then the routing
  destination must correspond to the value configured for the specified routing number in the
  database.

For example, the following PI command adds the 441473 ported number prefix:

NPYZ1=ADD: PQYZ=441473, ROUTING\_NUMBER=123, ROUTING\_DESTINATION=Destination1, NUMBER\_TYP E=F, URI=uri.com, DESCRIPTION=Any text

After successfully adding ported number prefixes to the NP database, the PI returns this message:

NPYZ1=ADD:ACK;

If unsuccessful, then the PI may return any of the following error codes: 68, 69, 1002, 1008 or 1020.

#### **Required Parameter**

This command requires the following parameter.

POYZ

**Syntax:** PQYZ=string

**Description:** The prefix number to use to match ported numbers.

Type: String
Optionality: Required

Allowed: A string of up to 18 characters.

**Example:** PQYZ=441473

#### **Optional parameters**

This command accepts the following optional parameters.

ROUTING\_NUMBER

Syntax: ROUTING NUMBER=string

**Description:** The routing number to prepend to numbers that match the prefix in PQYZ during

a ported number check.

Type: String
Optionality: Optional

Allowed: Specify a string of up to eight characters.

Example: ROUTING NUMBER=123

ROUTING\_DESTINATION

Syntax: ROUTING DESTINATION=string

**Description:** The routing destination.

Type: String
Optionality: Optional

Allowed: A string of up to 64 characters.

**Example:** ROUTING DESTINATION=Vodaphone

NUMBER\_TYPE

Syntax: NUMBER\_TYPE=F|M|Blank or empty value

**Description:** Sets the type of ported number.

**Note:** You unset the ported number type for an existing prefix definition by using

the NPYZ1=CHG command to specify a blank or empty value for

NUMBER TYPE.

Type: String

Optionality: Optional (default used if not set)

Allowed: One of the following:

F – For fixed numberM –For mobile number

Blank or empty value. The ported number type is not set.

Default: Blank or empty value Example: NUMBER TYPE=F

URI

Syntax: URI=string

**Description:** Defines the associated URI.

Type: String
Optionality: Optional

Allowed: A string of up to 50 characters.

Example: URI=uri.com

DESCRIPTION

Syntax: DESCRIPTION=string

**Description**: The description for the ported number.

Type: String
Optionality: Optional

Allowed: A string of up to 50 characters.

Example: DESCRIPTION=Any text

## **Change a Ported Number Prefix**

#### **About Changing Ported Number Prefixes by Using PI**

Use the NPYZ1=CHG PI command to change a ported number prefix definition in the NP database. For example, the following PI command changes the definition for the 441473 ported number prefix:

NPYZ1=CHG:PQYZ=441473,ROUTING\_NUMBER=321,ROUTING\_DESTINATION=Destination2,NUMBER\_TYP E=F,URI=uri.com,DESCRIPTION=Any text

If unsuccessful, then the PI may return any of the following error codes: 68, 69, 1002, 1008, 1021.

#### **Required Parameter**

This command requires the following parameter.

PQYZ

Syntax: PQYZ=string

Description: The prefix number, on which ported numbers are matched, that you want to

change.

Type: String
Optionality: Required

Allowed: An existing PQYZ prefix string of up to 18 characters.

Example: PQYZ=441473

#### **Optional parameters**

This command accepts the following optional parameters.

ROUTING\_NUMBER

Syntax: ROUTING\_NUMBER=string

Description: The routing number to prepend to numbers that match the prefix in PQYZ during

a ported number check.

Type: String
Optionality: Optional

Allowed: Specify a string of up to eight characters.

Example: ROUTING NUMBER=123

ROUTING\_DESTINATION

Syntax: ROUTING DESTINATION=string

**Description:** The routing destination.

Type: String
Optionality: Optional

Allowed: A string of up to 64 characters.

**Example:** ROUTING DESTINATION=Vodaphone

NUMBER\_TYPE

Syntax: NUMBER TYPE=F|M|Blank or empty value

**Description:** Sets the type of ported number.

Note: You unset the ported number type for an existing prefix definition by using

the NPYZ1=CHG command to specify a blank or empty value for

NUMBER TYPE.

Type: String

Optionality: Optional (default used if not set)

Allowed: One of the following:

F – For fixed numberM –For mobile number

Blank or empty value. The ported number type is not set.

Default: Blank or empty value Example: NUMBER TYPE=F

URI

Syntax: URI=string

**Description:** Defines the associated URI.

Type: String
Optionality: Optional

Allowed: A string of up to 50 characters.

**Example:** URI=uri.com

#### DESCRIPTION

Syntax: DESCRIPTION=string

**Description:** The description for the ported number.

Type: String
Optionality: Optional

Allowed: A string of up to 50 characters.

Example: DESCRIPTION=Any text

## **Query a Ported Number Prefix**

#### **About Querying Ported Number Prefixes by Using PI**

Use the NPYZ1=QRY PI command to query the NP database for PQYZ entries. A PQYZ entry maps a ported number prefix to a routing destination. You can query the NP database for multiple PQYZ entries by appending the % wild card character to the DN string parameter. The query returns all the PQYZ entries that match the specified network address. For example, the following PI command returns all the number prefixes for destination addresses that start with 44147328990:

```
NPYZ1=QRY:DN=44147328990%;
```

If you do not append the % character to the PQYZ string in the query, then the query returns the longest matching PQYZ entry.

By default, the maximum number of records returned when you query the NP database is 1500. You can specify a different maximum by configuring the pqyzMaxRecords parameter in the pi, NP section of the eserv.config configuration file. The PI outputs an error if the query finds more records than the configured maximum. For more information about configuring the PI, see *PI User's and Technical Guide*.

After successfully performing a prefix query, the PI returns this message:

#### Where:

- prefix is a matching PQYZ prefix.
- r number is the routing number for the prefix.
- uri is the URI associated with the prefix.
- description is the optional description for the prefix.

If no matching prefix is found, then the PI may return the following error codes: 69, 1004, or 1022.

#### **Required Parameter**

This command requires the following parameter.

DN

Syntax: DN=string

Description: A network address that is checked against PQYZ entries in the NP database. The

longest matching entry is returned by default. To query the NP database for multiple PQYZ entries, enter % as the last character in the DN query string.

Type: String
Optionality: Required.

Allowed: A string of up to 18 characters.

Example: DN=44147328990%

#### Delete a Ported Number Prefix

#### **About Deleting Ported Number Prefixes by Using PI**

Use the NPYZ1=DEL PI command to delete ported number prefixes from the NP database. You can delete multiple ported number prefixes by appending the % wild card character to the end of the PQYZ prefix string parameter. For example, the following PI command deletes all the prefix numbers that start with the digits 4414:

NPYZ1=DEL:PQYZ=4414%

If unsuccessful, then the PI may return the following the error codes: 69, 1021, or 1022.

#### Required Parameter

This command requires the following parameter.

POYZ

Syntax: PQYZ=string

**Description:** The prefix number, on which ported numbers are matched, that you want to

> delete. To delete multiple PQYZ prefix strings, specify the initial characters of the group of prefixes that you want to delete and then append it with the % wild card

character.

Type: Strina Optionality: Required

Allowed: An existing PQYZ prefix string of up to 18 characters.

Example: PQYZ=441473

## Add New LCR Rule Set

#### **Description**

Use the NPLC1=ADD Pi command to add a new rule set to the NP RULE SET table.

#### Required parameters

This command requires the following parameters.

RULE SET

RULE SET=string Syntax:

Description: The name of a the rule set you want to add, change, or delete.

Type: String Optionality: Required.

Allowed: Textual string, 1 to 30 characters long.

Default: None.

Notes:

Example: RULE SET=Rule Set 1

#### **Constraint required parameters**

There are no constraint required parameters for this command.

#### **Optional parameters**

There are no optional parameters for this command.

#### Logic and constraints

The following rule applies to the NPLC1=ADD command:

• The rule set name must not exist already.

## **Modify LCR Rule Set**

#### **Description**

Use the NPLC1=CHG PI command to change the name of a rule set in the NP\_RULE\_SET table.

#### **Required parameters**

This command requires the following parameters.

RULE\_SET

Syntax: RULE SET=string

**Description:** The name of a the rule set you want to add, change, or delete.

Type: String
Optionality: Required.

Allowed: Textual string, 1 to 30 characters long.

Default: None.

Notes:

Example: RULE SET=Rule Set 1

NEW\_NAME

Syntax: NEW\_NAME=string

**Description:** The new name for the rule set specified in RULE\_SET.

Type: String
Optionality: Required.

Allowed: Textual string of up to 30 characters.

Default: None.

Notes:

Example: NEW NAME=Rule Set 2

#### **Constraint required parameters**

There are no constraint required parameters for this command.

#### **Optional parameters**

There are no optional parameters for this command.

#### Logic and constraints

The following rules apply to the NPLC1=CHG command:

- This rule set name must exist already.
- The new name for the rule set must be unique.

### **Delete LCR Rule Set**

#### **Description**

Use the NPLC1=DEL PI command to delete a rule set from the NP\_RULE\_SET table. You can also delete any associated rules defined for the rule set.

#### Required parameters

This command requires the following parameters.

RULE\_SET

Syntax: RULE SET=string

**Description:** The name of a the rule set you want to add, change, or delete.

Type: String Optionality: Required.

Textual string, 1 to 30 characters long. Allowed:

Default: None.

Notes:

Example: RULE SET=Rule Set 1

#### **Constraint required parameters**

There are no constraint required parameters for this command.

#### Optional parameters

This command accepts the following optional parameters.

CASCADE

Syntax: CASCADE=Y | N

**Description:** Flag to determine whether or not rules based on this rule set should also be

deleted.

Type: Boolean

Optionality: Optional (default used if not set).

Allowed: Either:

> Y – Cascade deletion into the NP\_RULE table. N – Do not delete rules from the NP RULE table.

Default: N

Notes:

**Example:** CASCADE=Y

#### Logic and constraints

The following rules apply to the NPLC1=DEL command:

- This rule set must exist in the NP RULE SET table.
- If CASCADE is 'N' or not specified, the rule set must not have any associated rules in the NP\_RULE table.
- If CASCADE is 'Y', all rules from this set will be deleted from the NP\_RULE table.

## **Add New LCR Rule**

#### **Description**

Use the command NPLC2 and action ADD to add a new rule to the NP\_RULE table for the specified rule set.

#### **Required parameters**

This command requires the following parameters.

RULE\_SET

Syntax: RULE\_SET=string

**Description:** The name of a the rule set you want to add, change, or delete.

Type: String
Optionality: Required.

Allowed: Textual string, 1 to 30 characters long.

Default: None.

Notes:

Example: RULE SET=Rule Set 1

ROUTING\_DESTINATION

Type: String

Optionality: Required when adding, modifying or deleting LCR rules.

Allowed: A text string, up to 64 characters long.

Default: None

Notes:

**Example:** ROUTING\_DESTINATION=Vodaphone

CARRIER1

Syntax: CARRIER1=stringDescription: The name of the carrier.

Type: String

Optionality:

Required.

Allowed:

A text string of up to 30 characters.

Default:

None

Notes:

Example: CARRIER1=Carrier 1

#### **Constraint required parameters**

This command accepts the following constraint required parameters.

CARRIER2

Syntax:

CARRIER2=string

Description:

The name of the second carrier.

Type:

Strina

None

Optionality:

Must be specified if subsequent carriers are to be specified.

Allowed:

A text string of up to 30 characters.

Default:

Notes:

Example:

CARRIER2=Carrier 2

CARRIER3

Syntax:

CARRIER3=string

Description:

The name of the third carrier.

Type:

String

Optionality:

Must be specified if subsequent carriers are to be specified.

Allowed:

A text string of up to 30 characters.

Default:

None

Notes:

Example:

CARRIER3=Carrier 3

CARRIER4

Syntax:

CARRIER4=string

Description:

The name of the fourth carrier.

Type:

String

Optionality:

Must be specified if subsequent carriers are to be specified.

Allowed:

A text string of up to 30 characters.

Default:

None

Notes:

Example:

CARRIER4=Carrier 4

CARRIER5

Syntax:

CARRIER5=string

Description:

The name of the fifth carrier.

Type:

String

Optionality:

Must be specified if subsequent carriers are to be specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

**Example:** CARRIER5=Carrier 5

**CARRIER6** 

Syntax: CARRIER6=string

**Description:** The name of the sixth carrier.

Type: String

Optionality: Must be specified if subsequent carriers are to be specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

**Example:** CARRIER6=Carrier 6

CARRIER7

Syntax: CARRIER7=string

**Description:** The name of the 7th carrier.

Type: String

Optionality: Must be specified if subsequent carriers are to be specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

**Example:** CARRIER7=Carrier 7

#### **Optional parameters**

This command accepts the following optional parameters.

CARRIER8

Syntax: CARRIER8=string

**Description:** The name of the 8th carrier.

Type: String

Optionality: Optional. May only be specified if carriers 1 to 7 are specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

**Example:** CARRIER8=Carrier 8

#### Logic and constraints

The following rules apply to the NPLC2=ADD command:

- This rule set must exist in the NP\_RULE\_SET table.
- The routing destination must be defined in the NP ROUTING DESTINATION table.
- The combined rule set and routing destination must not already be defined in the NP RULE table.
- The carrier names must exist in the NP\_CARRIER table.

Carriers must be specified sequentially.

## **Modify LCR Rule**

#### **Description**

Use the command NPLC2 and action CHG to change a rule in the NP\_RULE table for the specified rule set.

#### Required parameters

This command requires the following parameters.

RULE\_SET

Syntax:

RULE SET=string

Description:

The name of a the rule set you want to add, change, or delete.

Type:

String

Optionality:

Required.

Allowed:

Textual string, 1 to 30 characters long.

Default:

None.

Notes:

.....

Example: RULE SET=Rule Set 1

ROUTING DESTINATION

Syntax:

ROUTING DESTINATION=string

Description:

The routing destination operator name.

Type:

String

Optionality:

Required when adding, modifying or deleting LCR rules.

Allowed:

A text string, up to 64 characters long.

Default:

None

Notes:

Example:

ROUTING\_DESTINATION=Vodaphone

CARRIER1

Syntax:

CARRIER1=string

Description:

The name of the carrier.

Type:

String

Optionality:

Required.

Allowed:

A text string of up to 30 characters.

Default:

None

Notes:

**Example:** CARRIER1=Carrier 1

#### **Constraint required parameters**

This command accepts the following constraint required parameters.

#### Chapter 2

CARRIER2

**Syntax:** CARRIER2=string

**Description:** The name of the second carrier.

Type: String

Optionality: Must be specified if subsequent carriers are to be specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

**Example:** CARRIER2=Carrier 2

CARRIER3

Syntax: CARRIER3=string

**Description:** The name of the third carrier.

Type: String

**Optionality:** Must be specified if subsequent carriers are to be specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

**Example:** CARRIER3=Carrier 3

CARRIER4

Syntax: CARRIER4=string

**Description:** The name of the fourth carrier.

Type: String

Optionality: Must be specified if subsequent carriers are to be specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

Example: CARRIER4=Carrier 4

CARRIER5

**Syntax:** CARRIER5=string

**Description:** The name of the fifth carrier.

Type: String

Optionality: Must be specified if subsequent carriers are to be specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

**Example:** CARRIER5=Carrier 5

CARRIER6

Syntax: CARRIER6=string

**Description:** The name of the sixth carrier.

Type: String

Optionality: Must be specified if subsequent carriers are to be specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

Example: CARRIER6=Carrier 6

CARRIER7

Syntax: CARRIER7=string

**Description:** The name of the 7th carrier.

Strina Type:

Optionality: Must be specified if subsequent carriers are to be specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

Example: CARRIER7=Carrier 7

#### **Optional parameters**

This command accepts the following optional parameters.

CARRIER8

CARRIER8=string Syntax:

**Description:** The name of the 8th carrier.

Type: String

Optionality: Optional. May only be specified if carriers 1 to 7 are specified.

A text string of up to 30 characters. Allowed:

Default: None

Notes:

Example: CARRIER8=Carrier 8

#### Logic and constraints

The following rules apply to the NPLC2=CHG command:

- This rule set must exist in the NP\_RULE\_SET table.
- The routing destination must be defined in the NP ROUTING DESTINATION table.
- The combined rule set and routing destination must exist in the NP\_RULE table.
- The carrier names must exist in the NP\_CARRIER table.
- Carriers must be specified sequentially.
- All carriers (carriers 1 to 8) will be updated, therefore you must specify a value for each of the required carriers. Carriers for which you do not specify a value will be set to null.

#### Delete LCR Rule

#### **Description**

Use the NPLC2=DEL PI command to delete a rule from the NP\_RULE table for the specified rule set and routing destination.

#### Required parameters

This command requires the following parameters.

RULE\_SET

Syntax: RULE SET=string

Description: The name of a the rule set you want to add, change, or delete.

Type: String
Optionality: Required.

Allowed: Textual string, 1 to 30 characters long.

Default: None.

Notes:

Example: RULE SET=Rule Set 1

ROUTING DESTINATION

Syntax: ROUTING\_DESTINATION=string

Description: The routing destination operator name.

Type: String

Optionality: Required when adding, modifying or deleting LCR rules.

Allowed: A text string, up to 64 characters long.

Default: None

Notes:

**Example:** ROUTING DESTINATION=Vodaphone

#### **Constraint required parameters**

There are no constraint required parameters for this command.

#### Optional parameters

There are no optional parameters for this command.

#### Logic and constraints

The following rules apply to the NPLC2=DEL command:

- This rule set must exist in the NP RULE SET table.
- The routing destination must be defined in the NP\_ROUTING\_DESTINATION table.
- The combination of rule set and routing destination must exist in the NP RULE table.

## **Add Home Routing Entry**

#### **Description**

Use the NPHR1=ADD PI command to add a new home routing entry in the NP HOME ROUTING table.

#### Required parameters

This command requires the following parameters.

DN START

Syntax: DN START=integer

**Description:** The start of the DN number range.

Type: Integer Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes:

Example: DN START=1230

DN\_END

Syntax: DN END=integer

**Description:** The end of the DN number range.

Type: Integer
Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes: DN\_END and DN\_START must be the same length.

Example: DN END=1250

#### **Constraint required parameters**

This command accepts the following constraint required parameters.

DN\_TYPE

Syntax:  $DN_TYPE=H \mid S$ Description: The type of DN.

Type: String

Optionality: Optional (default used if not set).

Allowed: Either:

H - homeS - special

Default: S

Notes: If the ROUTING\_DESTINATION field is not specified, DN\_TYPE must be set to

S.

**Example:** DN\_TYPE=H

#### **Optional parameters**

This command accepts the following optional parameters.

ROUTING\_DESTINATION

Syntax: ROUTING\_DESTINATION=string

Description: The routing destination operator name.

Type: String

Optionality: Required when adding, modifying or deleting LCR rules.

Allowed: A text string, up to 64 characters long.

Default: None

Notes:

**Example:** ROUTING DESTINATION=Vodaphone

#### Logic and constraints

The following rules apply to the NPHR1=ADD command:

- The range defined by DN\_START and DN\_END must not overlap an already defined range.
- DN\_END must be the same length as DN\_START.
- If specified, ROUTING\_DESTINATION must be a routing destination defined in the np routing destination table.
- The DN LENGTH field in the NP HOME ROUTING table is populated by a database trigger.
- If ROUTING DESTINATION is specified, DN TYPE must be 'H' or 'S'.
- If ROUTING DESTINATION is not specified, DN\_TYPE must be 'S'.
- DN\_TYPE will default to 'S' if the ROUTING\_DESTINATION is not specified and DN\_TYPE is not specified.

## **Modify Home Routing Entry**

#### **Description**

Use the NPHR1=CHG PI command to modify an existing entry in the NP\_HOME\_ROUTING table.

#### Required parameters

This command requires the following parameters.

DN\_START

Syntax: DN START=integer

**Description:** The start of the DN number range.

Type: Integer
Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes:

Example: DN START=1230

DN\_END

Syntax: DN END=integer

**Description:** The end of the DN number range.

Type: Integer
Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes: DN\_END and DN\_START must be the same length.

Example: DN END=1250

#### **Constraint required parameters**

This command accepts the following constraint required parameters.

DN TYPE

Syntax: DN TYPE=H|S

**Description:** The type of DN.

Type: String

Optionality: Optional (default used if not set).

Allowed: Either:

> H - home S - special

Default: S

Notes: If the ROUTING DESTINATION field is not specified, DN TYPE must be set to

Example: DN TYPE=H

#### **Optional parameters**

This command accepts the following optional parameters.

ROUTING DESTINATION

ROUTING DESTINATION=string Syntax: Description: The routing destination operator name.

Type: Strina

Optionality: Required when adding, modifying or deleting LCR rules.

Allowed: A text string, up to 64 characters long.

Default: None

Notes:

Example: ROUTING DESTINATION=Vodaphone

#### Logic and constraints

The following rules apply to the NPHR1=CHG command:

- The range defined by DN\_START and DN\_END must exist already in the NP\_HOME\_ROUTING table.
- If specified, ROUTING DESTINATION must be a routing destination defined in the NP\_ROUTING\_DESTINATION table.
- If ROUTING DESTINATION is specified, DN TYPE must be 'H' or 'S'.
- If ROUTING DESTINATION is not specified, DN TYPE must be 'S'. An existing set ROUTING\_DESTINATION will be made null.
- DN\_TYPE will default to 'S' if the ROUTING\_DESTINATION is not specified and DN\_TYPE is not specified.

## **Delete Home Routing Entry**

#### **Description**

Use the NPHR1=DEL PI command to delete an existing entry from the NP HOME ROUTING table.

#### Required parameters

This command requires the following parameters.

DN START

Syntax: DN START=integer

**Description:** The start of the DN number range.

Type: Integer
Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes:

Example: DN START=1230

DN END

Syntax: DN END=integer

**Description:** The end of the DN number range.

Type: Integer
Optionality: Required

Allowed: The specified number must have four to 18 digits.

Default: None

Notes: DN\_END and DN\_START must be the same length.

Example: DN END=1250

#### **Constraint required parameters**

There are no constraint required parameters for this command.

#### **Optional parameters**

There are no optional parameters for this command.

#### Logic and constraints

The following rule applies to the NPHR1=DEL command:

 The range defined by DN\_START and DN\_END must exist already in the NP\_HOME\_ROUTING table.

## **Query Home Routing Entry**

#### **Description**

Use the NPHR1=QRY PI command to guery an entry in the NP HOME ROUTING table for the following information:

- DN range
- Routing destination
- DN type

#### Required parameters

This command requires the following parameters.

DN

Syntax: DN=integer

Description: The destination number to query. The DN must be within the required DN range.

Type: Integer Optionality: Required

Allowed: Number, 4 to 18 digits long

Default: None

Notes:

Example: DN = 4124

#### **Constraint required parameters**

There are no constraint required parameters for this command.

#### **Optional parameters**

There are no optional parameters for this command.

#### Logic and constraints

The following rules apply to the NPHR1=QRY command:

- The DN must be within the DN range you want to query, that is, the DN must be >= DN\_START and <= DN END.
- The DN must be formatted correctly. It must be a number between 4 and 18 digits long.

## **Error Code Lists**

## **Overview**

#### Introduction

This chapter explains the error codes for NP PI commands.

### In this chapter

This chapter contains the following topics.	
PI Chassis Errors	33
PI Command Errors	

## **PI Chassis Errors**

### **Error List**

This table describes the PI Chassis error codes.

Code	Message	Description	
70	TOO MANY SESSIONS	All PI sessions are in use.	
71	LOGON SYNTAX ERROR	The login string was incorrectly formatted.	
72	INVALID LOGON - username, password	Invalid username and/or password	
73	INVALID LOGON - user not allowed on this port	The user attempted to log in to the wrong PI port.	
74	INVALID LOGON - host	The PI client is unknown.	
75	UNKNOWN COMMAND	Client sent an unknown command.	
76	USER DOES NOT HAVE SUFFICIENT SECURITY	The user's security level is less than the command's security level.	
77	SYNSTAMP NOT FOUND	Synstamps are turned on, but the client did not send one.	
78	SYNSTAMP NOT VALID	Synstamps are turned on, but the synstamp sent by the client is invalid.	
79	INVALID OR MISSING CHECKSUM	Checksums are turned on, but the client is one of the following:  • Did not send one  • It was invalid	
80	UNKNOWN PARAMETER FOR COMMAND	A parameter was sent that was not valid for this command.	
81	MISSING PARAMETERS FROM COMMAND	A required parameter is missing.	

Code	Message	Description
82		Undefined
83	DUPLICATE PARAMETER	The client sent two identically named parameters.
84	ERROR RUNNING PROCEDURE	An internal error occurred running the command.
85	USER SESSION TERMINATED	The user's session has been terminated by an administrator.
86	COMMAND TOO BIG	The command sent is too long. Indicates an incorrectly formatted command.
87	COMMAND SYNTAX ERROR	The command sent is incorrectly formatted.
88	PARAMETER NAME TOO BIG	A parameter name is too long. Indicates the command was incorrectly formatted.
89	PARAMETER VALUE TOO BIG	A parameter value is too long. Indicates the command was incorrectly formatted.
90	SYNSTAMP OUT OF PLACE	The synstamp is not at the end of the command, but before the checksum.
91	TIMEOUT	The command took too long to run.

## **PI Command Errors**

## **Number Portability PI Error Codes**

This table lists the error codes and error messages for the Number Portability PI commands.

Code	Error Message	Commands
68	Badly formatted parameter name.	All commands.
	Where name is an invalid parameter name.	
69	This error indicates that an error without a specific error code has occurred for a NP PI command. Details about the error are included in the error text.	All commands.
1000	The specified range start to end [with activation date date] overlaps an already defined range of the same entry type	NPDS1=ADD (includes text in square brackets) NPHR1=ADD
	<ul> <li>Where:</li> <li>start is the start of the DN range</li> <li>end is the end of the DN range</li> <li>date is DN range activation date</li> </ul>	NPDS1=CHG (includes text in square brackets)
1001	The end of range end is a different length to the start of range start  Where:  • end is the end of the DN range  • start is the start of the DN range	NPDS1=ADD NPDHR1=ADD
1002	This error displays one of the following error messages:  • The routing number number is not defined in the routing number table.  • The number type string is not defined	NPDS1=ADD NPDS1=CHG NPYZ1=ADD NPYZ1=CHG

Code	Error Message	Commands
	in the number type.	
	• The given URI is too long.	
	Where:	
	<ul> <li>number is the undefined routing number.</li> </ul>	
	string is the undefined number type.	
1003	The specified range start to end [with activation date date] is not defined  Where:	NPDS1=CHG (includes text in square brackets) NPDS1=DEL (includes text in square brackets)
	<ul> <li>start is the start of the DN range specified in the PI command.</li> </ul>	in square brackets) NPHR1=CHG
	<ul> <li>end is the end of the DN range specified in the PI command.</li> </ul>	NPHR1=DEL
	date is DN range activation date specified in the PI command.	
1004	The DN number was not matched.	NPDS1=QRY
	Where number is the value specified for DN in the PI	NPHR1=QRY
	command.	NPYZ1=QRY
1005	A rule set with name name is already	NPLC1=ADD
	defined	NPLC1=CHG
	Where name is the rule set name specified in RULE_SET in the PI command.	
1006	A rule set with name name is not defined	NPLC1=CHG
	Where name is the rule set name specified in RULE_SET	NPLC1=DEL
	in the PI command.	NPLC2=ADD
		NPLC2=CHG
		NPLC2=DEL
1007	The rule set <i>name</i> has associated rules	NPLC1=DEL
	Where name is the rule set name specified in RULE_SET in the PI command.	
1008	The routing destination string is not	NPLC2=ADD
	defined in the routing destination table.	NPLC2=CHG
	Where string is the value specified for	NPLC2=DEL
	ROUTING_DESTINATION in the PI command.	NPHR1=ADD
		NPHR1=CHG
		NPYZ1=ADD
		NPYZ1=CHG
1009	The rule set <i>name</i> and routing destination string are already defined in the rules table	NPLC2=ADD
	Where:	
	<ul> <li>name is the rule set name specified in RULE_SET in the PI command.</li> </ul>	
	<ul> <li>string is the value specified for ROUTING_DESTINATION in the PI command</li> </ul>	

Code	Error Message	Commands
1010	CARRIERn must be defined if CARRIERm, where m is greater than n, is defined  Where:  • n is the carrier number before CARRIERm.  • m is the carrier number after CARRIERn.  Note: Carriers must be defined in order.	NPLC2=ADD NPLC2=CHG
1011	The rule set name and routing destination string are not defined in the rules table  Where:  • name is the rule set name specified in RULE_SET in the PI command.  • string is the value specified for ROUTING_DESTINATION in the PI command.	NPLC2=CHG NPLC2=DEL
1012	The DN_TYPE <i>type</i> is not a known type Where <i>type</i> is the DN type specified in DN_TYPE in the PI command.	NPHR1=ADD NPHR1=CHG
1013	<ul> <li>The CARRIERn name is not a known carrier</li> <li>Where: <ul> <li>n is the carrier number specified in the PI command.</li> <li>The name specified in CARRIERn is not an existing carrier name for that carrier number.</li> </ul> </li> </ul>	NPLC2=ADD NPLC2=CHG
1014	The start of range start is after the end of range end Where:  • start is the value specified for the start of the DN range in the PI command.  • end is the value specified for the end of the DN range in the PI command.	NPDS1=ADD NPDS1=CHG NPDS1=DEL NPHR1=ADD NPHR1=CHG NPHR1=DEL
1015	DN_TYPE not specified when ROUTING_DESTINATION is specified	NPHR1=ADD NPHR1=CHG
1020	The specified PQYZ number is already defined.  Where number is the PQYZ number specified in the PI command.	NPYZ1=ADD
1021	The specified PQYZ number is not present.  Where number is the PQYZ number specified in the PI command.	NPYZ1=CHG NPYZ1=DEL
1022	Max query results exceeded. Try a smaller range.  To reduce the number of records found when you use the NPYZ1=QRY PI command, enter an additional character in the query string before you append the % wild card character.	NPYZ1=QRY

## **Glossary of Terms**

#### Convergent

Also "convergent billing". Describes the scenario where post-paid and pre-paid calls are handed by the same service platform and the same billing system. Under strict converged billing, post-paid subscribers are essentially treated as "limited credit pre-paid".

#### **DTMF**

Dual Tone Multi-Frequency - system used by touch tone telephones where one high and one low frequency, or tone, is assigned to each touch tone button on the phone.

#### **GUI**

Graphical User Interface

#### IN

Intelligent Network

#### IΡ

- 1) Internet Protocol
- 2) Intelligent Peripheral This is a node in an Intelligent Network containing a Specialized Resource Function (SRF).

#### NP

**Number Portability** 

#### ы

Provisioning Interface - used for bulk database updates/configuration instead of GUI based configuration.

#### SLC

Service Logic Controller (formerly UAS).

#### SMS

Depending on context, can be:

- Service Management System hardware platform
- Short Message Service
- Service Management System platform
- Convergent Charging Controller Service Management System application

#### SQL

Structured Query Language is a database query language.

#### **SRF**

Specialized Resource Function – This is a node on an IN which can connect to both the SSP and the SLC and delivers additional special resources into the call, mostly related to voice data, for example play voice announcements or collect DTMF tones from the user. Can be present on an SSP or an Intelligent Peripheral (IP).

#### SSP

Service Switching Point

#### **TCP**

Transmission Control Protocol. This is a reliable octet streaming protocol used by the majority of applications on the Internet. It provides a connection-oriented, full-duplex, point to point service between hosts.

#### **URI**

Uniform Resource Identifier.

Index  A  About Adding Ported Number Prefixes by Using PI • 12  About Changing Ported Number Prefixes by Using PI • 14  About Deleting Ported Number Prefixes by	E ENTRY_TYPE • 4, 8, 11, 12 Error Code Lists • 33 Error List • 33  G GUI • 37
Using PI • 17 About Querying Ported Number Prefixes by Using PI • 16 About This Document • v ACTIVATION_DATE • 4, 7, 11 Add a Ported Number Prefix • 12 Add a Ported Number Range • 3 Add Home Routing Entry • 26 Add New LCR Rule • 20 Add New LCR Rule Set • 17 ADDITIONAL_RN_ID • 5, 8 Audience • v C	IN • 37 IP • 37  L  Logic and constraints • 5, 6, 8, 9, 11, 12, 18, 19, 20, 22, 25, 26, 28, 29, 30, 31  M  Modify a Ported Number Range • 7  Modify Home Routing Entry • 28  Modify LCR Rule • 23  Modify LCR Rule Set • 18
CARRIER1 • 20, 23 CARRIER2 • 21, 24 CARRIER3 • 21, 24 CARRIER5 • 21, 24 CARRIER6 • 22, 24 CARRIER7 • 22, 25 CARRIER8 • 22, 25 CASCADE • 19 Change a Ported Number Prefix • 14 Command list • 1 Command List • 1 Constraint required parameters • 18, 19, 21, 23, 26, 27, 29, 30, 31 Convergent • 37 Copyright • ii	N  NEW_NAME • 18 NP • 37  Number Portability PI Error Codes • 34  Number Portability PI Parameter Formats • 2  NUMBER_TYPE • 5, 8, 13, 15  O  Optional parameters • 5, 8, 10, 12, 13, 15, 18, 19, 22, 25, 26, 27, 29, 30, 31  Overview • 1, 3, 33  P  Parameter Formats • 2  PI • 37  PI Chassis Errors • 33
Delete a Ported Number Prefix • 17 Delete a Ported Number Range • 10 Delete Home Routing Entry • 30 Delete LCR Rule • 25 Delete LCR Rule Set • 19 Description • 3, 7, 10, 11, 17, 18, 19, 20, 23, 25, 26, 28, 30, 31 DESCRIPTION • 14, 16 DN • 11, 16, 31 DN_END • 4, 7, 10, 27, 28, 30 DN_START • 4, 7, 10, 27, 28, 30 DN_TYPE • 27, 29 Document Conventions • vi DONOR_ID • 5, 8 DTMF • 37	PI Command Errors • 34 PI Commands Overview • 1 PI Number Portability Package • 3 PORT_ID • 6, 9 PQYZ • 13, 14, 17 Prerequisites • v  Q  Query a Ported Number Prefix • 16 Query an Active Ported Number Range • 11 Query Home Routing Entry • 31  R  Related Documents • v Required Parameter • 13, 14, 16, 17 Required parameters • 3, 7, 10, 11, 17, 18, 19, 20, 23, 26, 28, 30, 31

ROUTING\_DESTINATION • 13, 15, 20, 23, 26, 27, 29

ROUTING\_NUMBER • 5, 9, 13, 15

RULE\_SET • 17, 18, 19, 20, 23, 26

S

Scope • v
SLC • 37
SMS • 37
SQL • 37
SRF • 38
SSP • 38

T

TCP • 38
Typographical Conventions • vi

U

URI • 6, 9, 14, 15, 38