Oracle® Communications Services Gatekeeper

Application Developer's Guide

Release 6.1

E64617-01

September 2016



Oracle Communications Services Gatekeeper Application Developer's Guide, Release 6.1

E64617-01

Copyright © 2007, 2016, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Pr	reface	xvi
	Audience	xvi
	Documentation Accessibility	
	Related Documents	
Pa	art I Overview of Creating Applications for Services Gatekeeper	
1	About Creating Applications that Interact with Services Gatekeeper	
	Basic Concepts	1-1
	Understanding the Interfaces	
	Understanding Communication Services	1-1
	Understanding Traffic Types	
	Understanding Mobile Applications	1-3
	Understanding Management Structures	1-5
	Understanding How to Test Applications	1-5
2	Understanding the Supported Application Interfaces	
	Overview of Services Gatekeeper Supported Interfaces	2-1
	SOAP-Based Interfaces	2-1
	RESTful Interfaces	2-4
	RESTful OneAPI Interfaces	2-5
	Native Interfaces	2-6
3	Managing Communication Sessions	
	Understanding the Session Manager Web Service	3-1
	Session Management for SOAP, RESTful, and OneAPI Interfaces	3-1
	About Sessions	3-2
	Changing the Session Mode	3-3
	Session Manager WSDL File	3-3
	SessionManager Interface Reference	3-3
	Operation: getSession	
	Operation: changeApplicationPassword	3-4
	Operation: getSessionRemainingLifeTime	3-4
	Operation: refreshSession	3-5

	Operation: destroySession	
	Session Manager Examples	3-6
Pa	rt II Creating Applications Using the RESTful Interfaces	
4	Using the RESTful Interfaces	
	Supported RESTful Interfaces	4-1
	Understanding RESTful Operations	4-1
	Request-URI and HTTP Methods	
	Status-Line	
	Headers	
	Message Body	
	Example of a Request and Response	
	RESTful Authentication and Security	
	RESTful Notifications and Publish/Subscribe	
	Supported Endpoint Addresses	
	Using the Bayeux (Cometd) Protocol to Communicate with the Server Understanding RESTful Errors and Exceptions	
	Onderstanding RESTILI Errors and exceptions	4-10
5	Adding RESTful Third Party Call Support	
	About the RESTful Third Party Call Interface	5-1
	REST Service Descriptions Available at Runtime	5-1
	RESTful Third Party Call Interface Reference	
	Make Call	
	Get Call Information	
	Cancel Call	
	End Call	5-10
6	Adding RESTful Anonymous Customer Reference Support	
	About Anonymous Customer References	6-1
	Configuring ACR Support in Services Gatekeeper	6-1
	Creating an ACR Plug-in Instance	
	Setting ACR Plug-in Parameters	
	Creating Multiple ACRs for a Single Subscriber	
	RESTful APIs for ACR Support	
	Create ACR	
	Query ACR	
	Change ACR Status	
	Errors and Exceptions	
	EDRs	6-11
7	Adding RESTful Application Subscription Management Support	
	About Application Subscription Management	7-1
	REST Service Descriptions Available at Run-time	7-1
	Subscribe	7-2
	Unsubscribe	7-4

	Suspend	7-5
	Unsuspend	7-7
	Notify	
	Confirm	7-11
	queryBySubscriberAddress	7-13
	queryByApplicationName	7-15
	queryBySubscriptionID	7-17
8	Adding RESTful Call Notification Support	
	About the Call Notification Interface	8-1
	REST Service Descriptions Available at Run-time	8-1
	Common Data	8-1
	Start Call Notification	8-3
	Stop Call Notification	8-6
	Start Call Direction Notification	
	Stop Call Direction Notification	8-12
9	Adding RESTful Short Messaging Support	
	About the Short Messaging Interface	9-1
	REST Service Descriptions Available at Run-time	9-1
	Send SMS	9-2
	Send SMS Ringtone	9-4
	Send SMS Logo	9-7
	Get Received SMS	9-10
	Get SMS Delivery Status	9-12
	Start SMS Notification	9-14
	Stop SMS Notification	9-18
10	Adding RESTful Multimedia Messaging Support	
	About the Multimedia Messaging Interface	10-1
	REST Service Descriptions Available at Run-time	
	Send Message	
	Get Received Messages	
	Get Message	
	Get Message Delivery Status	
	Start Message Notification	
	Stop Message Notification	
11	Adding RESTful Email Communication Service Support	
	About the Email Communication Interface	11-1
	REST Service Descriptions Available at Run-time	
	Send Message	
	Get Received Messages	
	Get Message	
	Get Message Delivery Status	11-9

	Start Message Notification	11-11
	Stop Message Notification	11-15
12	Adding RESTful Terminal Status Support	
	About the Terminal Status Interface	12-1
	REST Service Descriptions Available at Run-time	. 12-1
	Get Status	12-2
	Get Status For Group	12-4
	Status Notification	
	End Notification	12-12
13	Adding RESTful Terminal Location Support	
	About the Terminal Location Interface	
	REST Service Descriptions Available at Run-time	
	Get Location	
	Get Location for Group	13-6
	Get Terminal Distance	13-11
	Start Geographical Notification	13-13
	Start Periodic Notification	13-20
	End Notification	13-24
14	Adding RESTful Payment Support	
	About the Payment Interface	. 14-1
	REST Service Descriptions Available at Run-time	. 14-1
	Charge Amount	. 14-2
	Refund Amount	. 14-4
	Charge Split Amount	14-6
	Reserve Amount	14-8
	Reserve Additional Amount	14-10
	Charge Volume	14-12
	Refund Volume	14-14
	Charge Split Volume	14-16
	Get Amount	14-18
	Charge Reservation	14-20
	Release Reservation	14-22
	Reserve Volume	14-23
	Reserve Additional Volume	14-25
	Get Amount Reserve Charging	14-27
15	Adding RESTful Audio Call Support	
	About the Audio Call Interface	15-1
	REST Service Descriptions Available at Run-time	. 15-1
	Play Audio Message	15-2
	Play Text Message	15-5
	Play VoiceXML Message	. 15-8
	Get Message Status	15-11

Apply QoS Apply Template-Based QoS Modify QoS Cemplate-Based Modify QoS Get QoS Status Remove QoS Register for QoS Notifications Unregister for QoS Notifications Unregister for QoS Notifications List QoS Event Notification List QoS Event Notifications Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers. Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
Example QoS Scenario Configuring QoS for Services Gatekeeper Using OAuth with QoS Apply OS Apply Template-Based QoS Modify QoS Get QoS Status Remove QoS Register for QoS Notifications Unregister for QoS Notifications Unregister for QoS Notifications Est QoS Event Notification List QoS Event Notifications List QoS Event Notifications Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
Configuring QoS for Services Gatekeeper. Using OAuth with QoS. Apply QoS. Apply Template-Based QoS. Modify QoS. Get QoS Status. Remove QoS. Register for QoS Notifications. Unregister for QoS Notifications. CoS Event Notification. List QoS Event Notifications. Adding RESTful Presence Support About the Presence Interface. REST Service Descriptions Available at Run-time. About Presentities and Watchers. Data Common to Operations in RESTful Presence Interface. attributes. presenceAttribute. unionElement. activity. place. privacy. sphere. type. communication. means typeAndValue. other Get Open Subscriptions Get My Watchers. Update Subscription Authorization	
Using OAuth with QoS Apply QoS Apply Template-Based QoS Modify QoS Template-Based Modify QoS Get QoS Status Remove QoS Register for QoS Notifications Unregister for QoS Notifications Unregister for QoS Notifications List QoS Event Notification List QoS Event Notifications Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers. Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
Apply QoS Apply Template-Based QoS Modify QoS Cemplate-Based Modify QoS Get QoS Status Remove QoS Register for QoS Notifications Unregister for QoS Notifications Unregister for QoS Notifications List QoS Event Notification List QoS Event Notifications Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers. Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
Remove QoS Register for QoS Notifications Unregister for QoS Notifications QoS Event Notification List QoS Event Notifications Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
Modify QoS Get QoS Status Remove QoS Register for QoS Notifications Unregister for QoS Notifications Unregister for QoS Notifications QoS Event Notification List QoS Event Notifications Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
Template-Based Modify QoS Get QoS Status Remove QoS Register for QoS Notifications Unregister for QoS Notifications QoS Event Notification List QoS Event Notifications Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers Data Common to Operations in RESTful Presence Interface attributes presence Attribute union Element activity place privacy sphere type communication means type And Value other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
Get QoS Status	
Remove QoS Register for QoS Notifications Unregister for QoS Notifications QoS Event Notification List QoS Event Notifications Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
Register for QoS Notifications Unregister for QoS Notifications QoS Event Notification List QoS Event Notifications. Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers. Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Authorization Update Subscription Authorization	
Unregister for QoS Notifications QoS Event Notification List QoS Event Notifications Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers	
QoS Event Notification List QoS Event Notifications Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions. Get My Watchers Update Subscription Authorization	
List QoS Event Notifications. Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers. Data Common to Operations in RESTful Presence Interface attributes. presenceAttribute unionElement. activity place privacy sphere. type. communication means typeAndValue other Get Open Subscriptions Get My Watchers. Update Subscription Authorization	
Adding RESTful Presence Support About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
About the Presence Interface REST Service Descriptions Available at Run-time About Presentities and Watchers Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
REST Service Descriptions Available at Run-time About Presentities and Watchers	
About Presentities and Watchers. Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
Data Common to Operations in RESTful Presence Interface attributes presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
attributes	
presenceAttribute unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
unionElement activity place privacy sphere type communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	
activity	
place	
privacy	
sphere	
type	
communication means typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	•••••
means	
typeAndValue other Get Open Subscriptions Get My Watchers Update Subscription Authorization	•••••
other	
Get Open Subscriptions	
Get My Watchers	
Update Subscription Authorization	
•	
Subscribe Presence	
Block Subscription	
Start Presence Notification	
End Presence Notification	

18	Adding RESTful Device Capabilities Support	
	About the Device Capabilities Interface	18-1
	REST Service Descriptions Available at Run-time	18-1
	Get Capabilities	18-2
	Get Device Id	18-4
19	Adding RESTful Binary Short Messaging Support	
	About the Binary Short Messaging Interface	19-1
	REST Service Descriptions Available at Runtime	19-1
	RESTful Binary SMS Interface Reference	19-1
	Send Binary Sms	19-2
	Start Binary Sms Notification	19-4
	Stop Binary Sms Notification	19-7
20	Adding RESTful Session Manager Support	
	About the Session Manager Interface	20-1
	REST Service Descriptions Available at Run-time	20-1
	Get Session	20-2
	Get Session Remaining Lifetime	20-3
	Destroy Session	20-4
21	Adding RESTful Subscriber Profile Support	
	About the Subscriber Profile Interface	21-1
	REST Service Descriptions Available at Run-time	21-1
	Get	21-2
	Get Profile	21-4
22	Adding RESTful WAP Push Support	
	About the WAP Push Interface	22-1
	REST Service Descriptions Available at Run-time	22-1
	Send Push Message	22-2
Par	rt III Creating Applications Using the OneAPI RESTful Interfaces	
23	Using the OneAPI RESTful Interfaces	
	About the OneAPI Facade Architecture	23-1
	Support for Anonymous Customer References	23-1
	Components of the RESTful Facade	23-2
	Supported OneAPI Interfaces	23-2
	SMS	23-3
	MMS	23-3
	Terminal Location	23-3
	Payment	23-3
	About Configuring OneAPI Server Functionality	23-3
	General Format of an Operation	23-4

	Request-URI and HTTP Methods	23-4
	Headers	23-0
	Status Line	23-
	Message Body	23-
	Example of a Request and Response	23-
	Authentication and Security	23-10
	Notifications	
	Errors and Exceptions	23-1
	1	
Pai	rt IV Creating Applications Using the SOAP Interfaces	
24	Using the SOAP Interfaces	
	Understanding the SOAP Interfaces	24-
	Requirements for Using the SOAP-Based Interfaces	
	Understanding SOAP-Based Authentication	
	Setting Callback Timeout Limits	
	Understanding How Service Correlation Orchestrates Services	
	Understanding Parameter Tunneling	
	Understanding SOAP Payload Attachments	
	Managing SOAP Headers and Attachments Programmatically	
	Wallaging SOAT Treaters and Attachments Trogrammatically	24
25	Adding a SOAP2SOAP Communication Services	
	About SOAP2SOAP Communication Services	25-
26	Adding SOAP-Based Quality of Service Support	
20		
	About the SOAP-Based QoS Interface	
	SOAP-Based Service Descriptions Available at Run-time	
	Example Parlay X 4.0 Application-Driven QoS/Diameter Scenario	
	Configuring Services Gatekeeper to Use the QoS Communication Services	26-
27	About the Supported SOAP Parlay X 2.1 Facades	
	Parlay X 2.1 Part 2: Third Party Call	27-
	Interface: ThirdPartyCall	
	Error Codes	
	Parlay X 2.1 Part 3: Call Notification	
	Interface: CallDirection	
	Interface: CallNotification	
	Interface: CallNotificationManager	
	Interface: CallDirectionManager	
	Error Codes	
	Parlay X 2.1 Part 4: Short Messaging	
	Interface: SendSms	
	Interface: SmsNotification	
	Interface: SinsNotification	
	Interface: SmsNotificationManager	∠1-

Error Codes	
Parlay X 2.1 Part 5: Multimedia Messaging	
Interface: SendMessage	
Interface: ReceiveMessage	27-
Interface: MessageNotification	27-
Interface: MessageNotificationManager	27-1
Error Codes	27-1
Parlay X 2.1 Part 8: Terminal Status	27-1
Interface: TerminalStatus	27-1
Interface: TerminalStatusNotificationManager	27-1
Interface: TerminalNotification	27-1
Error Codes	27-1
Parlay X 2.1 Part 9: Terminal Location	27-1
Understanding Parlay X 2.1 Terminal Location Precision	27-1
Interface: TerminalLocation	27-1
Interface: TerminalLocationNotificationManager	27-1
Interface: TerminalLocationNotification	27-1
Error Codes	27-1
Parlay X 2.1 Part 11: Audio Call	27-1
Interface: PlayAudio	27-1
Error Codes	
Parlay X 2.1 Part 14: Presence	27-1
Interface: PresenceConsumer	
Interface: PresenceNotification	27-1
Interface: PresenceSupplier	
Error Codes	
About Notifications	
General Exceptions	
General Error Codes	
Code Examples	
Example: sendSMS	
Example: startSmsNotification	
Example: getReceivedSms	
Example: sendMessage	
Example: getReceivedMessages and getMessage	

	Interface: Member	28-11
	Parlay X 3.0 Part 18: Device Capabilities and Configuration	28-12
	Interface: DeviceCapabilities	28-12
	Interface: DeviceCapabilitiesNotificationManager	28-12
	Interface: DeviceCapabilitiesNotification	28-13
	Interface: DeviceConfiguration	28-13
	General Exceptions	28-13
29	About the Supported SOAP Parlay X 4.0 Facades	
	Parlay X 4.0 Part 17 Application-Driven QoS	29-1
	Interface: Application-driven QoS	29-1
	Interface: ApplicationQoSNotificationManager	29-10
30	About the Supported SOAP Native Facade	
	About the Native Interfaces	30-1
	MM7	30-1
	Supported MM7 Operations	30-1
	SMPP	30-2
	Bind PDUs and Sessions	
	Error Handling	30-3
	Supported Operations	
	UCP	
	Error Handling	
	Native UCP Operations: Application-Facing Interface	
	Native UCP Operations: Network-Facing Interface	30-8
Paı 31	rt V Creating Applications Using Extended Web Service Interfaces Understanding the Extended Web Services Common Definitions Namespace	31-1
	XML Schema Datatype Definition	
	AdditionalProperty Structure	
	ChargingInformation structure	
	SimpleReference structure	
	Fault Definitions	
	ServiceException	
	PolicyException	
32	Adding Extended Web Service Binary SMSs Support	
	Understanding the Binary SMS Web Service	32-1
	Namespaces	32-1
	Endpoints	32-1
	Sequence Diagram	32-2
	Send SMS	32-2
	Receive SMS	32-3

	XML Schema data type definition	32-4
	BinaryMessage structure	32-4
	BinarySmsMessage structure	
	Interface: BinarySms	
	Interface: BinarySmsNotificationManager	
	Interface: BinarySmsNotification	
	Configuring Automatic Chunking of Binary SMSs	
	WSDLs	
	Error Codes	
	Sample Send Binary SMS	
33	Adding WAP Push Extended Web Service Message Support	
	Understanding the WAP Push Extended Web Service Interface	
	Namespaces	
	Endpoint	
	Sequence Diagram	
	XML Schema Data Type Definition	
	PushResponse Structure	
	ResponseResult structure	
	ReplaceMethod enumeration	
	MessageState enumeration	
	WAP Push Extended Web Service Interface Descriptions	
	Interface: PushMessage	
	Interface: PushMessageNotification	
	WSDLs	
	Sample Send WAP Push Message	33-10
34	Adding Subscriber Profile Extended Web Service Support	
	Understanding the Subscriber Profile Extended Web Service Interface	34-1
	Namespaces	34-1
	Endpoint	34-2
	Address schemes	34-2
	XML Schema data type definition	34-2
	PropertyTuple Structure	34-2
	WAP Push Extended Web Service Interface Descriptions	34-3
	Interface: SubscriberProfile	34-3
	WSDLs	34-5
Par	rt VI Testing Applications with the Application Test Environment	
35	Understanding the Application Test Environment	
	Understanding the ATE	35-1
	Understanding the ATE Graphical Interface	
	Supported Communication Services	
	Supported Communication Services	ა ა- ა

Testing Applications with the Application Test Environment Starting the ATE..... Starting the ATE on Mac OS X Basic Testing.... 36-2 Test with Account Credentials..... 36-3 Test Policy Enforcement..... 36-3 Substituting ATE Endpoints in Your Application 36-3 Setting Up and Using Map Elements..... 36-4 Monitoring Payment Accounts 36-24 Example Module 36-25 **Customizing the Application Test Environment**

	Customizing the SLA Manager	37-7
	Showing and Hiding the SLA Manager	37-7
	Creating Policy Enforcements	37-8
	Showing And Hiding Payment Accounts Panels	37-9
Α	ATE Endpoints	
	ATE Endpoints for SOAP-Based Interfaces	A -1
	Session Manager	
	Parlay X 2.1 Short Messaging Service/SMPP	
	Parlay X 2.1 MultiMedia Messaging Service	
	Parlay X 2.1 Terminal Location	
	Parlay X 2.1 Terminal Status	A-3
	Parlay X 3.0 Payment	
	Parlay X 2.1 Third Party Call	
	EWS Binary SMS	A-4
	ATE Endpoints for RESTful Interfaces	A-4
	Session Manager	
	Short Messaging	A-5
	Multimedia Messaging	
	Terminal Location	
	Terminal Status	A-7
	Payment	A-8
	Third Party Call	
	Binary SMS	A-10
	ATE Endpoints for Example Communication Service	
В	Virtual Communication Services Exception Codes	
	Short Messaging Exception Codes	D 1
	SendSms.sendSms SendSms.getSmsDeliveryStatus	
	•	
	ReceiveSms.getReceivedSmsSmsNotification	
	Multimedia Messaging Exception Codes	
	SendMessage.sendMessage	
	SendMessage.getMessageDeliveryStatus	
	ReceiveMessage.getMessage	
	ReceiveMessage.getReceivedMessage	
	MessageNotificationManager.startMessageNotification	
	MessageNotitifcationManager.stopMessageNotification Terminal Location Exception Codes	
	•	
	Terminal Location getLocation	
	Terminal Location Notification Manager start Coographical Notification	
	Terminal Location Notification Manager start Geographical Notification	
	Terminal Location Notification Manager and Notification	
	TerminalLocationNotificationManager.endNotification	
	Terminal Status Exception Codes Terminal Status getStatus	
	1 C111III I I I I I I I I I I I I I I I	,,,,,

TerminalStatus.getStatusForGroup	B-6
TerminalStatusNotificationManager.startNotification	B-6
TerminalStatusNotificationManager.endNotification	B-7
Third Party Call Exception Codes	B-7
ThirdPartyCallImpl.cancelCallRequest	B-7
ThirdPartyCallImpl.endCall	B-7
ThirdPartyCallImpl.getCallInformation	B-8
ThirdPartyCallImpl.makeCall	B-8
ThirdPartyCallImpl.sendMessage	B-8
ReceiveMessage.makeCall	B-8
Payment Exception Codes	B-8
AmountCharging.ChargeAmount	B-9
AmountCharging.RefundAmount	B-9
AmountCharging.ChargeSplitAmount	B-9
VolumeCharging.ChargeVolume	B-10
VolumeCharging.RefundVolume	B-10
ReserveAmountCharging.ReserveAmount	B-11
ReserveAmountCharging.ReserveAdditionalAmount	B-11
ReserveAmountCharging.ChargeReservation	B-11
Reserve Amount Charging Release Reservation	B-12
VolumeCharging.ChargeSplitVolume	B-12
ReserveVolumeCharging.ReserveVolume	B-12
ReserveVolumeCharging.ReserveAdditionalVolume	B-13
ReserveVolumeCharging.ChargeReservation	B-13
ReserveVolumeCharging.ReleaseReservation	B-13
Binary SMS Exception Codes	B-13
SendBinarySms.sendMessage	B-13
BinarySmsNotificationManager.startMessageNotification	B-14

Preface

This document describes how to integrate functionality provided by telecom networks into applications by using the SOAP and REST-based facades offered by Oracle Communications Services Gatekeeper. It includes a high-level overview of the application development process, including the login and security procedures, and a description of the interfaces and operations.

This document covers the SOAP and RESTful interfaces and the native interfaces available in Services Gatekeeper.

Audience

This book is intended for software developers who will integrate functionality provided by telecom networks into their applications using the SOAP-based, RESTful, and native interfaces.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

Related Documents

The following documents provide information related to creating applications that interact with Services Gatekeeper:

- Oracle Communications Services Gatekeeper Concepts
- Oracle Communications Services Gatekeeper Portal Developer's Guide
- Oracle Communications Services Gatekeeper Alarms Handling Guide
- Oracle Communications Services Gatekeeper Communication Service Reference Guide
- Oracle Communications Services Gatekeeper Extension Developer's Guide
- Oracle Communications Services Gatekeeper Platform Test Environment User's Guide

Part I

Overview of Creating Applications for Services Gatekeeper

Part I provides an overview of Oracle Communication Services Gatekeeper, and explains its capabilities and features.

Part I contains the following chapters:

- About Creating Applications that Interact with Services Gatekeeper
- Managing Communication Sessions

About Creating Applications that Interact with Services Gatekeeper

This chapter presents an overview of how you can develop applications that interact with Oracle Communications Services Gatekeeper.

See Services Gatekeeper Concepts for a complete description of the Services Gatekeeper structure and functionality.

Basic Concepts

These are the basic concepts you should understand before creating applications that can interact with Services Gatekeeper:

- Understanding the Interfaces
- **Understanding Communication Services**
- **Understanding Traffic Types**
 - **Understanding Application-Initiated Traffic**
 - **Understanding Network-Triggered Traffic**
- **Understanding Mobile Applications**
- **Understanding Management Structures**
- **Understanding How to Test Applications**

Understanding the Interfaces

In order to interact with Services Gatekeeper, applications use SOAP-based, RESTful, OneAPI, or native interfaces. For details about using these interfaces, see:

- Using the RESTful Interfaces
- Using the SOAP Interfaces
- Using the OneAPI RESTful Interfaces
- Understanding the Extended Web Services Common Definitions

Also, see "Understanding the Supported Application Interfaces" for a list of the supported interfaces and a brief description of each.

Understanding Communication Services

The basic functional unit in Services Gatekeeper is the communication service. A communication service consists of a service type (Short Messaging, User Location, and so on), an application-facing interface (also called a *north* interface), and a network-facing interface (also called a south interface). See "Understanding Traffic Types" for details about these traffic types.

A request for service enters the communication service through one interface, is processed internally, including evaluation for policy actions and protocol translation, and then sent on using the other interface.

For an overview of communication services, see Services Gatekeeper Concepts.

For details about the communication services that Services Gatekeeper includes, see Services Gatekeeper Communication Service Reference Guide.

For details about administering and deploying communication services, see Services Gatekeeper System Administrator's Guide.

For information about creating your own custom communication services, see Services Services Gatekeeper Extension Developer's Guide.

Note: A single application-facing interface may be using multiple protocols and hardware types in the underlying telecom network. However, an application is communicating, finally, with a specific communication service, and not only with the application-facing interface. So in some cases it is possible to send an application request to two different carriers that use different underlying network structures where the request behaves in slightly different ways, even though the initial request uses the same application-facing interface.

Understanding Traffic Types

In some communication services, request traffic can travel in two directions: from the application to the underlying network and from the underlying network to the application.

Understanding Application-Initiated Traffic

In application-initiated traffic, the application sends a request to Services Gatekeeper, the request is processed, and a response is returned synchronously. For example, an application could use the Third Party Call interface to set up a call. The initial request, **MakeCall**, is sent to Services Gatekeeper (which sends it on to the network). A string, the **callIdentifier**, is returned to the application synchronously. To find out the status of the call, the application makes a new request, **GetCallInformation**, using callIdentifier to identify the specific call. The application then receives the requested information back from Services Gatekeeper synchronously.

Understanding Network-Triggered Traffic

In many cases, application-initiated traffic provides all the functionality necessary to accomplish the desired tasks. But there are certain situations in which useful information may not be immediately available for return to the application. For example, the application might send an SMS to a mobile phone that the user has turned off. The network won't deliver the message until the user turns the phone back on, which might be hours or even days later. The application can poll to find out whether the message has been delivered by using the GetSmsDeliveryStatus request which functions such as **GetCallInformation** for application-initiated traffic. But it would be more convenient to have the network notify the application when the message has been delivered to the mobile phone. To do this, two things must happen:

- The application must inform Services Gatekeeper that it wants to receive information that originates from the network. It does this by subscribing or registering for notifications using an application-initiated request. (In certain cases, registering can also be accomplished by the operator, using Oracle Access Manager (OAM) procedures.) Often this subscription includes filtering criteria that describes exactly what kinds of traffic the application wants to receive. Depending on the underlying network configuration, Services Gatekeeper itself, or the operator using manual steps, informs the underlying network about the kind of data that is requested. These notifications may be status updates or, in some instances, may even include short or multimedia messages from a terminal on the telecom network.
- The application must arrange to receive the network-triggered information, either by implementing a Web service endpoint on its own site to which Services Gatekeeper dispatches the notifications, or by polling Services Gatekeeper to retrieve them. Notifications are kept in Services Gatekeeper for retrieval.

Securing Applications from Malicious Traffic

See "Securing Applications Against Malicious Traffic" in Services Gatekeeper Security Guide for details on how to protect Services Gatekeeper from malicious REST and SOAP traffic.

Adding Proxy Servers for Callbacks and Notifications

You can specify proxy servers to receive notifications or callback messages by adding them to the service provider or application SLA. Use the cproxyhost> and

For details and an example, see the proxyhost> and <pre Services Gatekeeper Accounts and SLAs Guide.

Understanding Mobile Applications

Application developers can create mobile applications running on devices such as smartphones and tablets that communicate with the Services Gatekeeper interfaces. Generally, the software development kit (SDK) for a mobile operating system, provided by the operating system vendor, includes the required tools for an application to communicate with Services Gatekeeper.

The following general guidelines list the basic steps used when developing a mobile application that communicates with Services Gatekeeper. The example provided uses the Google Android SDK. Though methods for interacting with web interfaces vary by operating system, the general procedure for other operating systems, such as Apple iOS or Microsoft Windows Phone, are similar.

To develop mobile applications that interface with Services Gatekeeper, consult the following sections:

- Preparing a Development Environment
- Creating a Mobile Application
- Testing a Mobile Application
- Distributing a Mobile Application

Preparing a Development Environment

You must set up a development environment before developing a mobile application for use with Services Gatekeeper. You must include downloading and configuring the appropriate mobile operating system SDK, JDK and integrated development environment (IDE) such as Eclipse. For example, download the Android application development tools needed from the following web sites:

Google Android Developer Tools (ADT) bundle: http://developer.android.com/sdk/index.html

The link above also provides a bundle for use with an existing IDE.

- Java Platform (JDK): http://www.oracle.com/technetwork/java/javase/downloads/index.html
- Eclipse IDE: http://www.eclipse.org/downloads/

Configure your application development environment according to the requirements listed by your mobile operating system vendor. After setting up your development environment, create a project in your IDE where you will develop your application.

Creating a Mobile Application

This section explains the general steps required for interfacing with Services Gatekeeper from an Android mobile application. Application requirements vary depending on the mobile operating system you are using and the functionality you are providing. See the documentation for your mobile operating system SDK for procedures and examples for developing mobile application elements such as the user interface and security.

The following steps show how to call a Services Gatekeeper API RESTful interface from an Android application. This example creates a RESTful POST method in the IDE mobile application project and sends the request to Services Gatekeeper. You interact with other Services Gatekeeper interfaces in a similar way.

To create a POST operation to Services Gatekeeper using the Android SDK and Eclipse IDE:

- 1. In the application project, create a JSON object using the org.json.JSONObject provided in the Android SDK.
- Populate the fields of this JSON object using the Services Gatekeeper communication service (or plugin) resource WADL file. See Communication Service Resource Guide for details on the communication services.
- Create an instance of the **org.apache.http.client.methods.HttpPost** object from the android.jar using the Services Gatekeeper RESTful service resource URL endpoint and the JSON object created in step 1 as the message parameters in the object.

Note: When testing your application with the Application Test Environment (ATE), use the appropriate endpoint for the URL. See "Testing a Mobile Application" for more information on ATE and "ATE Endpoints" for a list of available endpoints.

- Create an org.apache.http.impl.client.DefaultHttpClient object to send the object created in step 3.
- Send the **HttpPost** object using the **DefaultHttpClient** object to the Services Gatekeeper RESTful interface (or ATE endpoint). Services Gatekeeper (or ATE) provides a returned value as an object of **org.apache.http.HttpResponse**.
- Extract the JSON string included in the **HttpResponse** object returned by Service Gatekeeper.

- **7.** Create a JSON object from the extracted JSON string.
- Extract the desired fields required by your application from this JSON object.

Testing a Mobile Application

You must test your mobile application ensuring that it functions correctly. Mobile OS SDKs include emulators that can be used for testing the application against Services Gatekeeper. Alternatively, you can install the mobile application on a mobile device connected to your network for testing. See the mobile OS SDK documentation for more information about running your application for testing.

See "Understanding How to Test Applications" for information about testing your mobile application with Services Gatekeeper.

Distributing a Mobile Application

After completing sufficient testing of your application you distribute it to subscribers for use. Mobile OS vendors typically provide a store for application distribution. Alternative methods for distributing your application may also be available depending on mobile OS.

Understanding Management Structures

To help telecom operators organize their relationships with application providers, Services Gatekeeper uses a hierarchical system of accounts. Each application is assigned a unique application instance ID that is associated with an application account. Applications are assigned to service provider accounts. Each application account is associated with a service provider account. Application accounts with similar requirements are put into application groups, and service provider accounts with similar requirements are put into service provider groups. Each application group is associated with one application group service level agreement (SLA) and zero or more custom application group SLAs. Each service provider group is associated with one service provider group SLA and zero or more custom service provider group SLAs. These SLAs define and regulate the contractual agreements between the telecom operator and the application service provider. SLAs cover such things as which services the application may access and the maximum bandwidth available for use.


For more information about management structures, see Services Gatekeeper Portal Developer's Guide.

Understanding How to Test Applications

You test Applications in a telecom environment in stages. First, you run applications against simulators such as the Application Test Environment (ATE). The ATE emulates both Services Gatekeeper and the underlying network, and allows developers to evaluate basic functional issues without connecting to a network or network simulator. After basic functional issues are resolved, you can connect the application to an instance of Services Gatekeeper that is connected to the Platform Test Environment (PTE) network simulator for further testing. Next, the application is tested against a test network to eliminate any network related issues. Finally, the application can be placed into production on a live network.

Figure 1–1, "Application Testing Cycle" shows the application test flow, from the functional tests to deployment in a live network. Services Gatekeeper simulator-based tests can be performed in-house by an application service provider. However, the other tests require the cooperation of the target network operator.

Figure 1–1 Application Testing Cycle



See "Understanding the Application Test Environment" for details about using the ATE to test how your application functions with Services Gatekeeper.

See Services Gatekeeper Platform Test Environment User's Guide for details about testing how your application works with a network simulator.

Understanding the Supported Application Interfaces

This chapter introduces the interfaces that Oracle Communications Services Gatekeeper-hosted client applications can use. If you use HTTP-to-HTTP communication you can skip this chapter.

Overview of Services Gatekeeper Supported Interfaces

Services Gatekeeper enables you to provide client application developers with a choice of interface types, based on the needs of their applications. Services Gatekeeper provides these by default:

- SOAP-Based Interfaces for both traditional Web services and Oracle Service Bus environments
- **RESTful Interfaces**
- RESTful OneAPI Interfaces
- **Native Interfaces**

You can also createcustom interfaces, using the Network Service Supplier Portal.

SOAP-Based Interfaces

The SOAP-based Web services interfaces are based on the Parlay X standards and also include additional Extended Web services to cover functionality that is not supported by Parlay X. The SOAP-based interfaces include:

- Third Party Call (Parlay X 2.1 and 3.0; Part 2)
 - Using the communication service based on this interface, an application can set up a call between a caller and a callee, poll for the status of the call, and end the call. Using the 3.0 communication, an application can set up a call among multiple participants and add, delete, or transfer those participants. The application can use the Audio Call communication service to play audio messages to one or multiple of the call participants set up using Third Party Call and, using notifications set up with Call Notification PX 3.0, can also collect digits in response to playing the audio message.
- Application-driven Quality of Service (QoS) (Parlay X 4.0; Part 17)
 - Using the communication service based on this interface, an application can, in conjunction with a policy and charging rules function (PCRF) and policy and charging enforcement function (PCEF), apply, remove, modify, query, and receive

notifications for QoS feature profiles which can optimize various communication performance aspects.

Audio Call (Parlay X 2.1 and 3.0; Part 11)

Using the communication service based on this interface, an application can play audio to one or more call participants in an existing call session set up by the Parlay X 3.0 Third Party, find out if the audio is currently being played, and explicitly end playing the audio. It can also collect digits from a participant in response to an audio message, and with a notification set up using the Parlay X 3.0 Call communication service, can return that information to the application. It can also interrupt an ongoing interaction such as on-hold music.

Call Notification (Parlay X 2.1 and 3.0)

Using the communication service based on this interface, an application can set up and end notifications on call events. For example, an application can notify a caller that the callee's line is busy. The application can then reroute the call to another party. In addition, using the Parlay X 3.0 communication service, an application can interact with Parlay X 3.0 Audio Call to return digits collected from a call participant back to the application and to end calls. The Parlay X 3.0 version is deprecated.

Device Capabilities (Parlay X 3.0; Part 18)

Using the communication service based on this interface, an application can send a device's address (usually the telephone number) to an LDAP server and receive device capability information in return. The returned information can be either the device's equipment identifier (for example, an IMEI number), or the device capability information (the device's unique ID, device or model name, and a link to the User Agent Profile XML file).

Short Messaging (Parlay X 2.1)

Using the communication service based on this interface, an application can send SMS text messages, ringtones, or logos to one or multiple addresses, set up and receive notifications for final delivery receipts of those sent items, and arrange to receive SMS messages from the network that meet particular criteria.

Multimedia Messaging (Parlay X 2.1; Part 5)

Using this communication service based on this interface, an application can send multimedia messages to one or multiple addresses, set up and receive notifications for final delivery receipts of those sent items, and arrange to receive MMS messages from the network that meet particular criteria.

Terminal Location (Parlay X 2.1; Part 9)

Using the communication service based on this interface, an application can request the position of one or more terminals or the distance between a given position and a terminal. The application can also set up and receive notifications based on geographic location or time intervals.

Terminal Status (Parlay X 2.1)

Using the Terminal Status communication service, an application can:

- Obtain the status (reachable, unreachable, or busy) of a single terminal or group of terminals as often as you specify, within a time period you specify.
- Return the status of a terminal or group of terminals if the status changes. The terminal statuses are checked as frequently as you specify, for a time period you specify, and the status is returned if it changes.

Presence (Parlay X 2.1) (Part 14)

Using the communication service based on this interface, an application can act as either a presentity or as a watcher in a presence interaction. A presentity agrees to ensure data (called attributes) such as current activity, available. The data can be current activity, available means of communication, contact addresses, or other information. A watcher is a consumer of such data. As a watcher, an application can request to subscribe to all or a subset of a presentity's data, poll for that data, and start and end presence notifications. As a presentity, an application can publish presence data about itself, check whether any new watchers wish to subscribe to its presence data, authorize watchers to access presence data, block watchers from accessing presence data, and get a list of currently subscribed watchers.

Payment (Parlay X 3.0; Part 6)

Using the communication service based on this interface, an application can charge a user's account a specific amount, refund an amount, and split costs among multiple users. An application can also reserve an amount in an account, extend the amount associated with that reservation, make a charge against that reservation, or release the reservation.

Application-driven Quality of Service (Extended Web Service)

Using the communication service based on this interface, an application can, in conjunction with a PCRF and PCEF, apply, remove, modify and query QoS templates which can optimize various communication performance aspects.

Binary Short Messaging (Extended Web Services)

Using the communication service based on this interface, an application can send and receive generic binary objects (for example, a vCard) using SMS mechanisms, and set up and receive notifications. This interface is not based on the Parlay X standards, but instead belongs to the Services Gatekeeper Extended Web Services (EWS) set.

WAP Push (Extended Web Services)

Using the communication service based on this interface, an application can send a WAP Push message, send a replacement WAP Push message, or set up status notifications about previously sent messages. The application-facing interface of this communication service is not based on the Parlay X 2.1 specification. Many elements within it, however, are based on widely distributed standards.

Subscriber Profile (Extended Web Services)

Using the communication service based on this interface, an application can retrieve particular information or an entire profile (subject to internal filtering) for a subscriber from an LDAP server attached to the network. The application-facing interface of this communication service is based on a subset of that in a proposed Parlay X version.

Session Manager (Extended Web Services)

Using the communication service based on this interface, an application can establish a Services Gatekeeper session. Whether sessions are used is up to the operator.

For details, see "Creating Applications Using the SOAP Interfaces."

RESTful Interfaces

The RESTful interfaces provide access to functionality similar to the SOAP Facade. The RESTful interfaces include:

Audio Call

Using the communication service based on this interface, an application can play an audio file to one or more call participants in a call session. It is also possible to collect digits from a participant in response to the audio, and return that participant to the application.

Call Notification

Using the communication service based on this interface, an application can set up and remove call notifications. Call notifications notify the application about the particular state of the call, such as busy, unreachable, and so on. Call direction notifications query the application for information about how to handle a call that is in a particular state.

Device Capabilities and Configuration

Using the communication service based on this interface, an application can send a device's address (usually the telephone number) to an LDAP server and receive device capability information in return. The returned information can be either the device's equipment identifier (for example, an IMEI number), or device capability information (the device's unique ID, device or model name, and a link to the User Agent Profile XML file).

Email

Using the communication service based on this interface, an application can send and receive emails. This communication service uses MMS in the northbound interface and a plug-in that enables the sending of email through SMTP and receiving email through POP3 and IMAP protocols. See the discussion about "Parlay X 2.1 Multimedia Messaging/SMTP, POP3, and IMAP" in Services Gatekeeper Communication Service Reference Guide.

Multimedia Messaging

Using the communication service based on this interface, an application can send MMS messages, fetch MMS messages, and fetch information on MMS messages that have been received and stored on Services Gatekeeper. The application can also get delivery status on sent messages, and start and stop a notification.

Payment

Using the communication service based on this interface, an application can charge an amount to a user's account using Diameter, refund amounts to that account, and split charge amounts among multiple users. An application can also reserve amounts, reserve additional amounts, charge against the reservation, or release the reservation.

Presence

Using the communication service based on this interface, an application can act as either a presentity or a watcher in a presence interaction.

A presentity agrees to ensure that data (called attributes) is available to others. The data can be current activity, available means of communication, contact addresses, or other information. As a presentity, an application can publish presence data about itself, check whether any new watchers wish to subscribe to its presence

data, authorize watchers it chooses to access the data, block watchers from accessing the data, and get a list of currently subscribed watchers.

A watcher is a consumer of such data. As a watcher, an application can request to subscribe to all or a subset of a presentity's data, poll for that data, and start and end presence notifications.

Short Messaging

Using the communication service based on this interface, an application can send an SMS message, a ringtone, or a logo, and fetch SMS messages and delivery status reports that have been received and stored on Services Gatekeeper, start and stop a notification.

Terminal Location

Using the communication service based on this interface, an application can get a location for an individual terminal or a group of terminals; get the distance of the terminal from a specific location, and start and stop notifications based on geographic location or on a periodic interval.

Terminal Status (Parlay X 2.1)

Using the communication service based on this interface, an application can request the status (such as reachable, unreachable, or busy) of a single terminal; request the status of a group of terminals; or request to be notified if a terminal status changes within a specified time period.

Third Party Call

Using the communication service based on this interface, an application can set up a call, get information on that call, cancel the call request before it is successfully completed, or end a call that has been successfully set up.

WAP Push

Using the communication service based on this interface, an application can send a WAP Push message and receive status notifications about that message.

Session Manager

Using the communication service based on this interface, an application can establish a session with the Services Gatekeeper operator. Operators can choose whether to use Services Gatekeeper in session-based mode.

Subscriber Profile

Using the communication service based on this interface, an application can query an operator's database for the attributes of an individual subscriber profile (for example, the terminal type), or for entire subscriber profiles.

For details, see "Creating Applications Using the RESTful Interfaces."

RESTful OneAPI Interfaces

The OneAPI interfaces provide access to RESTful OneAPI operation. The interfaces include:

Short Messaging

Using the communication service based on this interface, an application can send SMS messages, fetch SMS messages, deliver status reports, and to start and stop notifications.

Multimedia Messaging

Using the communication service based on this interface, an application can send MMS messages, fetch MMS messages and delivery status reports, and to start and stop notifications.

Terminal Location

Using the communication service based on this interface, an application can get a location for an individual terminal or a group of terminals.

Payment

Using the communication service based on this interface, an application can charge an amount to a user's account using Diameter and to refund amounts to that account. Applications can also reserve amounts, reserve additional amounts, charge against the reservation or release the reservation.

For details, see "Creating Applications Using the OneAPI RESTful Interfaces."

Native Interfaces

The Native interfaces provide access to native telecom-specific protocols. The interfaces include:

Native MM7

Using the communication service based on this interface, an application can send and receive MMS messages and receive status notifications about previously sent messages. This application-facing interface is based on the 3GPP MM7 standard.

Native SMPP

Using the communication service based on this interface, an application can send and receive SMS messages and receive status notifications about previously sent messages. This application-facing interface is based on the SMS Forum standard.

Native UCP

Using the communication service based on this interface, an application can establish a session with application clients and the network, submit and receive SMS messages, and receive status notifications about previously sent messages. This application-facing interface is based on the Short Message Service Center EMI-UCP Interface 5.1 specification. It exposes Universal Computer Protocol (UCP) protocol to applications and uses UCP to connect to a Short Message Service Center (SMSC).

For details, see "About the Supported SOAP Native Facade."

Managing Communication Sessions

This chapter explains how to use the Oracle Communications Services Gatekeeper Session Manager Web service to manage the sessions that your applications use to communicate with Services Gatekeeper.

Understanding the Session Manager Web Service

The Session Manager Web service contains operations for managing a session with Services Gatekeeper, including establishing the session, changing the application's password, querying the amount of time remaining in the session, refreshing the session, and terminating the session.

Note: Not all installations of Services Gatekeeper require session management. The contents of this chapter apply only to those installations that do.

When an operator requires it, an application must establish a session with Services Gatekeeper before the application can perform any operations using the Parlay X or Extended Web Services interfaces. When a session is established, a session ID is returned, which must be used in each subsequent operation toward Services Gatekeeper.

Session Management for SOAP, RESTful, and OneAPI Interfaces

In order to interact with Services Gatekeeper, applications use SOAP-based, RESTful, OneAPI, or SOAP native interfaces. Those applications using SOAP-based interfaces must manipulate the SOAP messages that they use to make requests in certain specialized ways. They must add specific information to the SOAP header, and, if they are using Multimedia Messaging, they must send their message payload as a SOAP attachment. Applications using the native interfaces use the normal, native interface mechanisms, which are not covered in this document.

How developers program applications to manipulate SOAP messages depend on the environment in which the application is being developed.

Note: Clients created using Axis 1.2 or older do not work with some communication services. Developers should use Axis 1.4 or newer if they wish to use Axis.

For examples of using the Oracle WebLogic Server environment manipulate SOAP messages, see "Managing SOAP Headers and Attachments Programmatically".

You can configure whether SOAP, REST, or OneAPI-based applications must provide credentials and apply for a session ID before they can communicate with Services Gatekeeper. The default setting requires that these types of applications establish a session using the Session Manager Web service before they are allowed to run traffic through Services Gatekeeper. You can also make a session optional, or simply remove session checking completely.

The session requirement is useful as a security mechanism because it requires all applications to authorize themselves, and it allows Services Gatekeeper to keep track of all traffic for a session.

About Sessions

An application establishes a session in Services Gatekeeper by invoking the getSession() operation in the Session Manager Web service. The getSession() operation is the only operation that does not require a session ID to be invoked. This operation returns a string representing the session ID to the client, and Services Gatekeeper establishes a session identified by the ID string. See "Operation: getSession" for details about this operation.

Sessions last until they time out or until the application closes the session. You configure the timeout interval. Each session is valid for the entire Services Gatekeeper domain, across clusters, and covers all communication services to which the application has contractual access. Once established, the session ID must appear in the wlng: Session element in the header of every subsequent SOAP request.

Example 3-1 Example of a Session Header element

```
<Session>
 <SessionId>app:-2810834922008400383</SessionId>
</Session>
```

You can configure the session mode that determines whether session IDs are required. The mode has these possible values:

- **Required** The default value. Requires that all applications authorize themselves with credentials before requesting a session ID. Services Gatekeeper validates session IDs and rejects communication attempts if the IDs are invalid. If the mode is **Required**, a session ID is required for all communication through Services Gatekeeper.
- Disabled (sessionless) Services Gatekeeper does not check whether a session ID exists. If applications successfully authenticate themselves, they receive a session ID string of sessionless, which is used in all communication within the session. If they do not authenticate, no session ID is provided or required. In this case the application uses whichever Web services Security (WS-Security) mechanism is required by the Services Gatekeeper operator for security.
- **Optional** Services Gatekeeper does not require that an application log on or request a session ID. If the application successfully authenticates, it is provided with a session ID that is checked for validity. If found invalid, the request is rejected. If the application passes in a header with a session ID of sessionless, or if no session ID is passed in, the request is accepted.

Changing the Session Mode

To change the Services Gatekeeper session mode:

- Start the MBean browser that you use to configure Services Gatekeeper.
 - You can browse MBeans by using JConsole or PTE, which are supplied with Services Gatekeeper.
- 2. Navigate to wlng, then AccountService, then ApplicationSessionMBean, and then **SessionRequired**.
- **3.** Check the box representing the session behavior that your implementation requires:
 - Required
 - Disabled
 - **Optional**

See "About Sessions" for details on the different options.

Session Manager WSDL File

The WSDL file for the Session Manager Web service can be found here:

http://host:port/session_manager/SessionManager

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

SessionManager Interface Reference

The Session Manager Web service interface includes these operations:

- Operation: getSession
- Operation: changeApplicationPassword
- Operation: getSessionRemainingLifeTime
- Operation: refreshSession
- Operation: destroySession

Operation: getSession

Establishes a session using WS-Security. Authentication information must be provided according to WS-Security. See "Understanding SOAP-Based Authentication" for more information.

Input message: getSession

Table 3-1 Input Message: getSession

Part name	Part type	Optional	Description
N/A	N/A	N/A	N/A

Output message: getSessionResponse

Table 3–2 Output Message: getSessionResponse

Part name	Part type	Optional	Description
getSessionReturn	xsd:String	N	The session ID to use in subsequent requests.

Referenced faults

GeneralException

Operation: changeApplicationPassword

Changes the password for an application.

Input message: changeApplicationPassword

Table 3-3 Input Message: changeApplicationPassword

Part name	Part type	Optional	Description
sessionId	xsd:string	N	The ID of an established session.
oldPassword	xsd:string	N	The current password.
newPassword	xsd:string	N	The new password.

Output message: changeApplicationPasswordResponse

Table 3–4 Output Message: changeApplicationPasswordResponse

Part name	Part type	Optional	Description
N/A	N/A	N/A	N/A

Referenced faults

None

Operation: getSessionRemainingLifeTime

Gets the remaining lifetime of an established session. The default lifetime is configured in Services Gatekeeper.

Input message: getSessionRemainingLifeTime

Table 3–5 Input Message: getSessionRemainingLifeTime

Part name	Part type	Optional	Description
sessionId	xsd:string	N	The ID of an established session.

Output message: getSessionRemainingLifeTimeResponse

Table 3–6 Output Message: getSessionRemainingLifeTimeResponse

Part name	Part type	Optional	Description
getSessionRemainingLifeTimeReturn	xsd:string	N	The remaining lifetime of the session. Given in milliseconds.

Referenced faults

None

Operation: refreshSession

Refreshes the lifetime of a session. The session can be refreshed during a time interval after the session has expired. This time interval is configured in Services Gatekeeper.

Input message: refreshSession

Table 3-7 Input Message: refreshSession

Part name	Part type	Optional	Description
sessionId	xsd:string	N	The ID of an established session.

Output message: refreshSessionResponse

Table 3-8 Output Message: refreshSessionResponse

Part name	Part type	Optional	Description
refreshSessionReturn	xsd:string	N	The session ID to be used in subsequent requests. The same ID as the original session ID is returned.

Referenced faults

None

Operation: destroySession

Destroys an established session.

Input message: destroySession

Table 3–9 Input Message: destroySession

Part name	Part type	Optional	Description
sessionId	xsd:string	N	The ID of an established session.

Output message: destroySessionResponse

Table 3–10 Output Message: destroySessionResponse

Part name	Part type	Optional	Description
destroySessionReturn	xsd:boolean	N	True if the session was destroyed.

Referenced faults

None

Session Manager Examples

Example 3–2 illustrates how to get the Session Manager Web service and how to prepare the generated stub with WS-Security information. The stub is generated from the Session Manager Web service.

Example 3–2 Get the Session Manager Web Service

```
protected ClientSessionManImpl(String sessionManagerURL, PolicyBase pbase) throws Exception {
 SessionManagerService accessservice =
   new SessionManagerService_Impl(sessionManagerURL+"?WSDL");
 port = accessservice.getSessionManager();
 pbase.prepareStub((Stub)port);
  }
```

Example 3–3 illustrates how to prepare the Session Manager Web service stub with username token information according to WS-Policy.

Example 3–3 Prepare the Session Manager with Username Token information

```
package com.bea.wlcp.wlng.client.access.wspolicy;
{\tt import\ weblogic.wsee.security.unt.ClientUNTCredentialProvider;}
import weblogic.xml.crypto.wss.WSSecurityContext;
import javax.xml.rpc.Stub;
import java.util.ArrayList;
import java.util.List;
public class UsernameTokenPolicy implements PolicyBase {
 private String username;
 private String password;
public UsernameTokenPolicy(String username, String password) {
   this.username = username;
   this.password = password;
  }
 public void prepareStub(Stub stub) throws Exception {
   List<ClientUNTCredentialProvider> credProviders = new ArrayList<ClientUNTCredentialProvider>();
   credProviders.add(new ClientUNTCredentialProvider(username.getBytes(),
                                                       password.getBytes()));
   System.out.println("setting standard wssec");
   stub._setProperty(WSSecurityContext.CREDENTIAL_PROVIDER_LIST,
                      credProviders);
  }
}
```

Part II

Creating Applications Using the RESTful Interfaces

Part II describes how to use the interfaces in the RESTful facade to create applications that interact with Oracle Communications Services Gatekeeper.

Part II contains the following chapters:

- Using the RESTful Interfaces
- Adding RESTful Third Party Call Support
- Adding RESTful Anonymous Customer Reference Support
- Adding RESTful Application Subscription Management Support
- Adding RESTful Call Notification Support
- Adding RESTful Short Messaging Support
- Adding RESTful Multimedia Messaging Support
- Adding RESTful Email Communication Service Support
- Adding RESTful Terminal Status Support
- Adding RESTful Terminal Location Support
- Adding RESTful Payment Support
- Adding RESTful Audio Call Support
- Adding RESTful Quality of Service Support
- Adding RESTful Presence Support
- Adding RESTful Device Capabilities Support
- Adding RESTful Binary Short Messaging Support
- Adding RESTful Session Manager Support
- Adding RESTful Subscriber Profile Support
- Adding RESTful WAP Push Support

Using the RESTful Interfaces

This chapter presents an overview of Oracle Communications Services Gatekeeper RESTful interfaces, and explains how to use them to create applications that interact with Services Gatekeeper.

Supported RESTful Interfaces

The RESTful interfaces provide applications with the operations they use to interact with Services Gatekeeper.

See Understanding the Supported Application Interfaces for a complete list and short description of the RESTful interfaces supported by Services Gatekeeper. These interfaces are explained in detail in the chapters that follow.

Understanding RESTful Operations

The following basic elements are present in the requests that an application makes to the RESTful interfaces and the responses it receives from the interface:

- Request-URI and HTTP Methods in requests
- Status-Line in responses
- Headers

Sometimes messages (for example, multimedia messages) contain attachments. Special headers are provided to specify the attachment details when a message has multiple parts. See "Headers for Multipart Messages with Attachments".

Message Body

Request-URI and HTTP Methods

Applications use one of four methods, "GET", "POST", "PUT", or "DELETE", to request a required action to be performed on an abstract or physical resource. The resource has a specific Uniform Resource Identifier (URI). The Request-URI identifies the abstract or physical resource that an HTTP method acts upon or uses and is therefore the most important part of any request that an application makes to the RESTful interfaces.

Here is the GET method used to query for the status of a terminal:

GET /rest/terminal_status/status?query="%7B%22address%22%3A%22tel%3A123%22%7D" HTTP/1.1

where, the string %7B%22address%22%3A%22telA123%22%7D is the address of the terminal (or the { "address": "tel: 123" } JavaScript Object Notation (JSON) object).

General Format of a Request-URI

A fully qualified Request-URI consists of a sequence of concatenated sections that are each separated by a forward slash. For example:

https://host:port/rest_facade_context_root/URI/path_info_param/query-string

where,

- host:port: The hostname or IP address and port of your Services Gatekeeper installation; for example, 127.0.0.1 and 8001.
- rest_facade_context_root: The location of the set of resources that the particular interface uses; for example, rest, in the following example query for the status of a

GET /rest/terminal_status/status?query="%7B%22address%22%3A%22tel%3A123%22%7D" HTTP/1.1

In Services Gatekeeper, the *rest_facade_context_root* entry is always **rest**.

- *URI*: The location of a specific kind of functionality within the interface; for example, terminal_status.
- path_info_param: An identifier of a specific resource, for example, calls. This is seen in the Make Call request, POST /rest/third_party_call/calls HTTP/1.1. See Example 4–8. The path-info-param entry does not occur in all URIs.
- query_string: A set of name-value pairs that describes what is being requested; for example, status?query="%7B%22address%22%3A%22tel%3A123%22%7D, in the above GET query for rest_facade_context_root. The query-string entry is not seen in every URI.

POST

The POST method accesses a resource factory to create a resource that does not yet have a URI. Multiple requests to a resource factory can create multiple new resources.

The following example statement will set up a call between two parties:

Example 4-1 POST Statement

POST /rest/third_party_call/calls HTTP/1.1

For the POST method:

- The URI in the request represents the factory resource accessed to create a resource. In Example 4–1, /rest/third_party_call/calls is the factory resource accessed to create a resource.
- The request body contains the information required to create the resource. See Example 4–6.
- If the resource is created, the response body will contain the identifier for the new resource. See Example 4–7. If the operation fails, the response body will contain the error response.

PUT

The PUT method creates a resource that has a predetermined URI. This method can be used to update a resource (or to start a stateful process). For example, an application uses the following statement to start notifications on a specific terminal:

Example 4–2 PUT Statement

PUT /rest/terminal_location/periodic_notification HTTP/1.1

For the PUT method:

- The URI in the request represents the resource to update or the resource for which to start a stateful process. In Example 4–2, /rest/terminal_location/periodic_ notification represents the resource accessed to start periodic notifications on a terminal's location.
- The request body will contain the required information. (The JSON object will contain, for example, information on the terminal, the criteria to monitor, the frequency and duration of the monitoring, where to place the notification, and the correlator to identify the session.
- The Location header in the response will specify the location that contains the resulting notifications. For example, the application may see the following header for the above PUT request:

```
Location://terminalloc_host:port/rest/terminal/notifications
```

In order to complete the operation, the application must access the specified location and use the correlator to retrieve the notifications.

If the operation fails, the response body will contain the error response.

GET

The GET method retrieves the state of a specific resource that has been previously set up. The specific resource is identified in the query string as shown in Example 4–3, where an application attempts to retrieve the status of a terminal whose address is specified as "tel:123".

Example 4-3 GET Statement

GET /rest/terminal_status/status?query=%7B%22address%22%3A%22tel%3A456%22%7D HTTP/1.1

For the GET method:

- The URI in the request represents the query string that uniquely identifies the resource whose status the application wishes to retrieve. In Example 4–3, the value for status?query is ({"address": "tel:456"}, the unique address of the terminal in JSON representation).
- The request body will be empty.
- The response will provide information on the state of the resource.
 - In order to complete the operation, the application must access the specified location and use the correlator to retrieve the notification.
- If the operation fails, the response body will contain the error response.

DELETE

The DELETE method removes a specified resource. The application provides the correlator or the identifier for the resource that must be removed in the Request-UR, as shown here:

Example 4-4 DELETE Statement

DELETE /rest/terminal_status/notifications/6789 HTTP/1.1

For the DELETE method:

- The URI in the request contains the correlator, which is a value that uniquely identifies the resource the application wishes to remove. In Example 4-4, 6789 is the value which the application provided as the correlator when it requested notifications on a terminal's status.
- The request body will be empty.
- The response body will be empty.
- If the operation fails, the response body will contain the error response.

Status-Line

The Status-Line is the first line in any response that an application receives when it interacts with a RESTful interface in Services Gatekeeper. The Status-Line has this syntax:

HTTP/1.1 Status-Code Reason-Phrase

where,

- Status-Code: A three-digit indicator of the success or failure to fulfill the request.
- Reason-Phrase: A brief description of the (successful) action performed, or the reason for the failure.

For example:

HTTP/1.1 201 Created

Table 4–1 lists some of the status codes and reason-phrases commonly encountered when interacting with the Services Gatekeeper RESTful interfaces:

Table 4–1 A Sampling of Status Codes and Reason Phrases

Status-Code	Reason-Phrase	Description
200	OK	Success. The request has succeeded. The information returned with the response is dependent on the method used in the request.
201	Created	Success. The requested resource was created.
204	No Content	Success. The server has fulfilled the request but does not need to return an entity-body.
501	Internal Server Error	Indicates failure. An unexpected condition prevented the server from fulfilling the request.

For a complete listing of the HTTP status codes and their definitions, see RFC 2616 at:

http://www.ietf.org/rfc/rfc2616.txt

Headers

The requests and responses for RESTful operations include the following header fields:

Authorization: The Authorization header field is required and is found in all requests. It indicates the type of authentication and security. For example:

```
Authorization: Basic QWxhZGRpbjpvcGVuIHNlc2FtZQ==
```

For more information, see "RESTful Authentication and Security".

Session ID: When Services Gatekeeper is running in Session mode, the X-Session-ID header must be present in all request messages to identify the application.

In session mode, an application's first task is to obtain a session ID from the Session Manager Web service. All traffic requests (for that session) include this identifier in the key-value pair for the X-Session-ID key. For example:

```
X-Session-ID: app: -1780934689905632396
```

The X-Session-ID header is not present when Services Gatekeeper is running in Sessionless mode. For more information on sessions, see "Adding RESTful Session Manager Support"

- Service correlation ID (X-SCID): The X-SCID header will be present if the application wishes to set up service correlation. This is a key-value pair of the format key=X-SCID. For more information on service correlation, see "Service Correlation".
- Tunneled parameters: Tunneled parameters (also called xparams) are present if the application wishes to supply parameters that are not supported in the RESTful interface itself and need to be passed on to the network. The key-value pairs are:
 - X-Param-Key and X-Param-Values: The X-Param-Key and X-Param-Values headers are found in the requests.
 - X-Plugin-Param-Key and X-Plugin-Param-Values: The X-Plugin-Param-Key and X-Plugin-Param-Values headers are returned in the response headers.

See Services Gatekeeper Communication Service Reference Guide for descriptions of the tunneled parameters that are applicable to your communication service.

Location: Location headers are found in responses to certain requests. They are used to identify a new resource or to redirect the recipient to a location other than the Request-URI for completion of the request.

For example, the call identifier for a newly-setup call is returned in the Location header as:

```
Location: http://local:host:8001/rest/third_party_
call/call/app-1q39oi07wpvjl|e9674e8214447c1663a016d434c@sipcalling_
host | -50d94925ab34bf0
```

Below, the Location header specifies the location that the application must access to receive notifications about a terminal (for which the application had previously initiated a notification request).

Location: http://notificationloc_host:port/rest/terminal_location/notifications

- Content-Length: The length of the request or response body.
- Content-Type: The MIME-type value for the Content-Type header field can be multipart/form-data or application/json. The multipart/form-data value for the Content-Type header field is described in the next section.

Headers for Multipart Messages with Attachments

The RESTful interfaces for Multimedia Messaging and WAP Push use HTTP attachments to transport their content. Both interfaces support multipart/form-data POST requests. When you use RESTful interfaces with Services Gatekeeper, multiple attachments are supported in both application-initiated and network-triggered messages.

When a request message contains one or more messages embedded within it, a specified boundary is placed between the parts of the message and at the beginning and end of the message. For multipart message requests:

- The MIME-type value for the Content-Type header field can be multipart/form-data or application/json. If the MIME-type value for the Content-Type header field is **multipart/form-data**, the **boundary** entry is used to provide a value for the boundary between the message parts.
- Each message part contains the following:
 - Content-Disposition header field that has a value of form-data and a name attribute with the appropriate value. For example, the message part name is messagePart.
 - Content-Type header field that has a value of application/json and the charset attribute with the appropriate value.
 - Content-Transfer-Encoding field with the appropriate value.
- If the content of the message is pure ASCII, the response body contains the message. Otherwise the response body contains an identifier that is used to fetch the actual message.

Example 4-5 Example of a Multipart Message Request

```
POST /rest/multimedia_messaging/messages HTTP/1.1
X-Session-ID: app: -123456789012346789
Authorization: Basic ZG9tY1uX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Kevs:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host: localhost:8001
Content-Length: 1215
Content-Type: multipart/form-data; boundary=kboiiFPAakDPYKeY7hBAW9I5c0rT48
--kboiiFPAakDPYKeY7hBAW9I5c0rT48
Content-Disposition: form-data; name="messagePart"
Content-Type: application/json; charset=US-ASCII
Content-Transfer-Encoding: 8bit
  "addresses":["tel:8765"],
  "subject": "Hello World",
  "priority":null,
  "senderAddress": "tel:1234",
  "charging":null
  "receiptRequest":
           "correlator": "981234",
           "endpoint": "http://endpt_host:port/jaxws/MessageNotification",
           "interfaceName": "interfaceName",
         }
 }
```

```
--kboiiFPAakDPYKeY7hBAW9I5c0rT48
Content-Disposition: form-data; name="Attachment-txt-1"
Content-Type: text/plain; charset=US-ASCII
Content-Transfer-Encoding: 8bit
This sentence represents the attachment text.
--kboiiFPAakDPYKeY7hBAW9I5c0rT48
```

Service Correlation

In some cases the service that an application provides to its end-users may involve accessing multiple Services Gatekeeper communication services.

For example, a mobile user might send an SMS to an application asking for a pizza restaurant nearest to his current location. The application then makes a Terminal Location request to find the user's current location, looks up the address of the closest pizza restaurant, and then sends the user an MMS with all the appropriate information. Three Services Gatekeeper communication services are involved in executing what, for the application, is a single service.

Services Gatekeeper uses a service correlation ID to correlate the three communication service requests. The service correlation ID (SCID) is a string that is captured in all the charging data records (CDRs) and event data records (EDRs) generated by Services Gatekeeper. The CDRs and EDRs can then be orchestrated in order to provide special treatment for a given chain of service invocations, by, for example, applying charging to the chain as a whole rather than to the individual invocations.

How Service Correlation IDs are Provided Services Gatekeeper does not provide the service correlation ID. The type of request determines the service correlation ID:

- Application-Initiated Requests: When the chain of services is initiated by an application-initiated request, the application must provide and ensure the uniqueness of the SCID within the chain of service invocations.
 - In certain circumstances, it is also possible for a custom service correlation service to supply the SCID, in which case it is the custom service's responsibility to ensure the uniqueness of the SCID.
- Network-Triggered Requests: When the chain of services is initiated by a network-triggered request, Services Gatekeeper calls an external interface to get the SCID.

This interface must be implemented by an external system. Integration of such an external interface must be a part of a system integration project. It is the responsibility of the external system to provide and ensure the uniqueness of the SCID.

Message Body

The message body for a request or response is present only when required. The message body is a JSON object.

Request Body

When present, the request body provides additional data required to complete the specific request. The following request body for an example Make Call operation provides the addresses of the called and calling parties and any charges to apply for the call:

Example 4–6 Request Body for Make Call

```
{"calledParty": "sip:ann@sipcalled_host:port",
"charging":null,
 "callingParty": "sip:zach@sipcalling_host:port"
```

Response Body

When present, the response body provides data that the application will need for later action. The following response body for the Make Call operation provides the application with the identifier for the call that was set up. The application will use this identifier to end the call, when necessary.

Example 4–7 Response Body for a Make Call Operation

```
{"result": "app-1q39oi07wpvj1 | e9674e8214447c1663a016d434c@sipcalling_
host | -50d94925ab34bf0" }
```

Example of a Request and Response

Example 4–8 shows an application's request to set up a call between two parties using the Make Call operation in the Service Gatekeeper RESTful interface.

Example 4–8 Request associated with a Make Call Operation

```
POST /rest/third_party_call/calls HTTP/1.1
X-Session-ID: app: -1780934689905632396
Authorization: Basic ZG9tY1uX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host: localhost:8001
Content-Length: 105
Content-Type: application/json
{"calledParty": "sip:alice@sipcalled_host:port",
 "charging":
     {
       "description": "init_call",
      "amount":"11",
       "code":"1111",
       "currency": "rmb"
 "callingParty": "sip:bob@sipcalling_host:port"
```

Example 4–9 shows the response which the application receives for a successful setup of the requested call.

Example 4–9 Response associated with a Make Call Operation

```
HTTP/1.1 201 Created
Date: Wed, 20 Oct 2010 06:58:06 GMT
Location: http://local:host:8001/rest/third_party_
call/call/app-1q39oi07wpvjl|e9674e8214447c1663a016d434c@sipcalling_
host | -50d94925ab34bf0
Content-Length: 96
Content-Type: application/json
X-Plugin-Param-Keys:
```

```
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
{"result":"app-1q39oi07wpvj1|e9674e8214447c1663a016d434c@sipcalling_
host | -50d94925ab34bf0" }
```

RESTful Authentication and Security

The RESTful interfaces use HTTP basic authentication, using username/password. SSL is required. For instance:

```
Authorization: Basic QWxhZGRpbjpvcGVuIHNlc2FtZQ==
```

For more information on HTTP basic authentication, see RFC 2617 at

http://www.ietf.org/rfc/rfc2617.txt

RESTful Notifications and Publish/Subscribe

When an application needs to receive a notification, (about a message delivery receipt for example), the application uses the publish/subscribe functionality in Services Gatekeeper.

An application can subscribe only to its own notifications (that is, to the notifications associated with its start notification requests). Any attempt to subscribe to notifications for other applications will be rejected.

Supported Endpoint Addresses

The application provides an endpoint address that resides on a publish/subscribe server. You can specify one of the following endpoint addresses:

- RESTful: a Bayeux protocol channel name
- SOAP: a Web service implemented by the application

A SOAP endpoint for the notification of a message sent using RESTful interfaces in Services Gatekeeper is valid only if the SOAP and RESTful interfaces reside in the same cluster.

Endpoint Addresses for RESTful Interfaces

The RESTful interfaces in Services Gatekeeper rely on the publish/subscribe model supported by the Publish-Subscribe Server functionality of Oracle WebLogic Server 10.3.1.

For more information on the publish/subscribe model, please see the discussion on "Using the HTTP Publish-Subscribe Server" in Oracle Fusion Middleware Developing Web Applications, Servlets, and JSPs for Oracle WebLogic Server.

Using the Bayeux (Cometd) Protocol to Communicate with the Server

When using RESTful interfaces, the application client must use the Bayeux protocol to communicate with the Web server. In this model, clients subscribe to a channel (similar to a topic in JMS) and receive messages (notifications) as they become available. The endpoint address resides on a Bayeux server.

Understanding Bayeux Connections and Subscriptions

The mechanisms for connecting to the Web server and subscribing to a channel are covered by the Bayeux protocol itself. The Bayeux client manages connections to the server and subscriptions to a channel. If the channel does not exist when the client subscribes to it, the channel is created.

Once the Bayeux client connects to the server and subscribes to a channel, the RESTful client can start sending notifications. It does so by providing the Bayeux protocol channel name as the endpoint entry in a start notification request.

Understanding the Bayeux Protocol Channel Name

The Bayeux protocol channel name begins with /bayeux/appInstanceID where applinstanceID is the client application's application instance account ID. In Example 4–10, the *appInstanceID* is domain-user.

An application places the endpoint address for delivery notifications in the body of the request message. In the following example, it is inside a reference object.

Example 4–10 Example of an Endpoint Address in a Reference Object

```
"reference":
      { "interfaceName": "interfaceName",
        "correlator": "6789",
       "endpoint": "/bayeux/domain-user/ts"
       }
```

See Example 12–5 for the complete request body of the status notification request.

For more information on application instances, see the discussion of application instances in Services Gatekeeper Portal Developer's Guide.

Using the Data at the Endpoint Address

Services Gatekeeper delivers notifications to the Bayeux channel name provided by the application in the associated request. It is the client's responsibility to interact with the publish/subscribe server to access the messages/data placed at the **endpoint** address. The mechanisms to do so are outside the scope of the Services Gatekeeper RESTful facades.

Understanding RESTful Errors and Exceptions

In the case of an error, the Status-Line in the response message indicates the protocol version, the three-digit status code, and the reason for the request failure.

Service exception and policy exception objects are represented in the response body as JSON with the following form:

```
{"error":
           "type": "class name of the error object"
           "message": "error message"
 }
```

For service exceptions, the value for **type** is:

[&]quot;type": "org.csapi.schema.parlayx.common.v2_1.ServiceException"

For policy exceptions, the value for **type** is:

```
"type": "org.csapi.schema.parlayx.common.v2_1.PolicyException"
```

For example, when an MMS message sent by an application cannot be delivered to the multimedia messaging service (MMSC), the response from the MMSC contains the statusCode and statusText. Services Gatekeeper returns these values to the application in the requestError object. The requestError object contains the SVC0001 serviceException with the error code **MMS-000005**.

The format for the error code is

```
MMS-000005:<StatusCode from MMSC>:<StatusText from MMSC>
```

The requestError object is:

```
{"requestError":
       "serviceException":
             "messageId": "SVC0001",
             "text": "A service error occurred. Error code is %1",
             "variables":["MMS-000005:3002:Message rejected"]
       }
}
```

A variable substitution is performed for PX exceptions in error messages.

Adding RESTful Third Party Call Support

This chapter describes the operations in the Third Party Call interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the RESTful Third Party Call Interface

Applications use the RESTful Third Party Call interface in Services Gatekeeper to set up a call, get information on that call, cancel the call request before it is successfully completed, or end a call that has been successfully set up.

Additionally, applications use this interface to specify the data required for the billing operation associated with the call.

REST Service Descriptions Available at Runtime

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at:

http://host:port/rest/third_party_call/index.html

Where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

RESTful Third Party Call Interface Reference

The RESTful Third Party Call interface includes these operations:

- Make Call
- Get Call Information
- Cancel Call
- **End Call**

Make Call

To set up a call between two parties (referred to as the calling party and the called party), provide the SIP-formatted URI of the calling party and the called party in the body of the request for the call. Optionally, the request can also indicate any cost-charging parameters to be applied to the call.

If the call setup is successful, the response header will contain the URI of the newly created resource as the value of the Location header field. Additionally, the response body will contain the call identifier for the newly created call object. Use this call identifier to reference the call later.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/third_party_call/calls

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the POST request accepts the following parameters:

- **calledParty**: String. Required. The address (URI) of the party to whom the call is made. Specified as sip:user_name@destination_ip:destination_port.
- callingParty: String. Required. The address (URI) of the party making the call. Specified as sip:user_name@origin_ip:origin_port.
- charging: a JSON object. Optional. This object defines the cost charging parameters for the call. A call with no charging parameters can be entered as "charging": null.

If a charge is to be applied, provide values for the following in the **charging** object:

- **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
- **amount**: Number (integer, or decimal). Optional. The amount to be charged.
- **code**: String. Optional. The charging code, from an existing contractual description.
- currency: String. Optional. The currency identifier as defined in ISO 4217 [9].

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

{

```
"calledParty": "URI",
  "callingParty": "URI",
  "charging": {
   "description": "String",
   "amount": "BigDecimal",
   "code": "String",
   "currency": "String"
 }
}
```

Response Header

The value in the Location header field is a single absolute URI in the following format:

```
http://host:port/rest/third_party_call/{${result}}
```

where *result* is a string-formatted call identifier for the newly-created call. See Example 5–2.

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body for the POST request contains the call identifier returned in the Location header field. The call identifier is the value for the result term in the response body represented by the following name/value pair structure:

```
{"result": "String"}
See Example 5–2.
```

Examples

Example 5-1 HTTP POST Request to Set Up a Call

```
POST /rest/third_party_call/calls HTTP/1.1
X-Session-ID: app: -1780934689905632396
Authorization: Basic ZG9tY1uX3VzZXI6ZG9tYW1uX3VzZXI=
X-Param-Kevs:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host: localhost:8001
Content-Length: 105
Content-Type: application/json
{"calledParty": "sip:alice@sipcalled_host:port",
 "charging":
      {
       "description": "testing",
       "amount":"11",
       "code":"1111",
       "currency": "rmb"
 "callingParty": "sip:bob@sipcalling_host:port"
```

Example 5–2 HTTP POST Response to Setting Up a Call

```
HTTP:/1.1 201 Created
```

Date: Wed, 20 Oct 2010 06:58:06 GMT

Location: http://local:host:8001/rest/third_party

_call/call/app-1q39oi07wpvj1|e9674e8214447c1663a016d434c@sipcalling

_host | -50d94925ab34bf0 Content-Length: 96

Content-Type: application/json

X-Plugin-Param-Keys: X-Plugin-Param-Values:

X-Powered-By: Servlet/2.5 JSP/2.1

{"result": "app-1q39oi07wpvjl | e9674e8214447c1663a016d434c@sipcalling _host|-50d94925ab34bf0"}

Get Call Information

The Get Call Information operation retrieves the information on a previously-established call.

To retrieve the information on a previously-established call, provide the appropriate call identifier in the HTTP GET request. This call identifier should have been obtained by the set up request for the call as the value for result in the response received for the HTTP POST request to set up the call. See Example 5–2.

If the operation is successful, the response body will contain the time the call started and the current status of the call. Additionally, if the call was terminated, the response body will indicate the total duration of the call and the reason for its termination.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/third_party_call/call/\${callIdentifier}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- callIdentifier is the call identifier obtained from the response to the POST request to set up the call.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

When the GET request is successful, the response body contains the appropriate values for the following parameters that describe the call:

- **callStatus**: String. The current status of the call as one of the following values:
 - **CallInitial**: The call is being established.
 - **CallConnected**: The call is active.
 - **CallTerminated**: The call was terminated.

- duration: Integer. The duration of the call in seconds. Present in the response body when callStatus is CallTerminated.
- startTime: String. The start time for the call in the ISO 8601 extended format, yyyy-mm-ddThh-mm-ss.
- terminationCause: String. The reason for the termination of the call. Present in the response body only when callStatus is CallTerminated. Its value can be one of the following:
 - **CallAborted**
 - CalledPartyBusy
 - CalledPartyNoAnswer
 - CalledPartyNotReachable
 - CallHangUp
 - CallingPartyBusy
 - CallingPartyNoAnswer
 - CallingPartyNotReachable

The parameter values are placed in a data structure as the value for **result** in the following JSON structure, where the value part of each name/value pair indicates its data type:

```
{"result": {
  "callStatus": "CallInitial | CallConnected | CallTerminated",
  "duration": "Integer",
  "startTime": "Calendar",
 "terminationCause": "CallingPartyNoAnswer|CalledPartyNoAnswer|CallingPartyBusy|C
alledPartyBusy|CallingPartyNotReachable|CalledPartyNotReachable|CallHangUp|CallA
borted"
}}
```

Examples

Example 5-3 HTTP GET Request

```
GET /rest/third_party
_call/call/app-1q39oi07wpvjl|e9674e8214447c1663a016d434c@sipcalling
_host | -50d94925ab34bf0 HTTP/1.1
X-Session-ID: app: -123456789012346789
Authorization: Basic ZG9tY1uX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host: localhost:8001
```

Example 5-4 HTTP GET Response

```
HTTP:/1.1 201 Created
Date: Wed, 20 Oct 2010 06:58:06 GMT
Content-Length: 124
Content-Type: application/json
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
{"result":
```

```
 \verb| {"startTime":"2010-10-20T4:58:18.254+08:00",} \\
   "terminationCause":null,
   "duration":"0",
  "callStatus": "CallConnected"
}
```

Cancel Call

The Cancel Call operation cancels a previously-requested call that is in its initial state and not yet active. This operation will have no effect if the call is already established.

To cancel a call before it is established, provide the appropriate call identifier in the Request-URI for the POST method. This identifier should have been obtained by the initial setup request for the call.

There is no request or response body for the POST request to cancel a call. If the request fails, the body of the error response will contain the call identifier and the type of exception.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/third_party_call/cancel-call/\${callIdentifier}

where:

- *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.
- callIdentifier is the call identifier obtained from the response to the HTTP POST reqest to set up the call.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Examples

Example 5-5 HTTP POST Request to Cancel a Call

The POST command to cancel the call contains the required call identifier.

POST /rest/third_party

```
_call/cancel-call/app-1q39oi07wpvjl|e9674e8214447c1663a016d434c@sipcalling
_host|-50d94925ab34bf0 HTTP/1.1
X-Session-ID: app: -123456789012346789
Authorization: Basic ZG9tY1uX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host: localhost:8001
Content-length: 0
```

Example 5-6 Response for the HTTP POST Request to Cancel a Call

If the request to cancel the call succeeds, you will see a response similar to the following:

```
HTTP:/1.1 204 No Content
Date: Wed, 20 Oct 2010 07:48:14 GMT
Content-Length: 0
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
```

Example 5-7 Error Response Example

If the request to cancel the call fails, you will see an error response similar to the following. The error body will contain the call identifier as the value for the correlator attribute.

```
HTTP:/1.1 500 Internal Server Error
Date: Wed, 20 Oct 2010 07:48:26 GMT
Content-Length: 261
Content-Type: application/json
X-Powered-By: Servlet/2.5 JSP/2.1
{"error" :
  {"message":"Invalid input value for message part Could not find a plugin for
this message: correlator:
app-1q39oi07wpvj1|e9674e8214447c1663a016d434c@sipcalling
_host|-50d94925ab34bf0",
   "type": "org.csapi.schema.parlayx.common.v2_1.ServiceException"
```

End Call

The End Call operation ends a call that is active.

To end a call, provide the appropriate call identifier in the Request-URI for this operation. This identifier should have been obtained by the initial setup request for the call.

There is no request or response body for this operation. If the request fails, the body of the error response will contain the call identifier and the type of exception.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/third_party_call/end-call/\${callIdentifier}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\${callIdentifier}* is the call identifier obtained from the response to the Make Call request.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Examples

Example 5–8 End Call Request

```
POST /rest/third_party_call/end-call/app-1q39oi07wpvjl|
e9674e8214447c1663a016d434c@sipcalling_host|-50d94925ab34bf0 HTTP/1.1
X-Session-ID: app: -123456789012346789
Authorization: Basic ZG9tY1uX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
```

X-Param-Values:

User-Agent: Jakarta Commons-HttpClient/3.0

Host: localhost:8001 Content-length: 0

Example 5–9 End Call Response

If the End Call operation succeeds, you will see a response similar to the following:

HTTP:/1.1 204 No Content

Date: Wed, 20 Oct 2010 07:48:14 GMT

Content-Length: 0 X-Plugin-Param-Keys: X-Plugin-Param-Values:

X-Powered-By: Servlet/2.5 JSP/2.1

Adding RESTful Anonymous Customer Reference Support

This chapter describes how you can add RESTful Anonymous Customer References (ACRs) to provide secure access for Web applications in Oracle Communications Services Gatekeeper.

About Anonymous Customer References

An Anonymous Customer Reference (ACR) represents a unique identifier that replaces a subscriber's secure information, such as MSISDN or phone number, ensuring privacy when the subscriber interacts with Web applications.

According to GSM Association, an ACR is a string issued by the operator, which maps to a customer (or customers). The operator can pass the ACR in request headers, so you can create an ACR per application per user, and personalize your application based on the user's previous behavior.

Information about ACR API is available at the GSM webs site:

http://technical.openmobilealliance.org/Technical/technical-information/re lease-program/current-releases/rest-netapi-acr-v1-0

See the discussion on anonymous customer reference specifications in Services *Gatekeeper Statement of Compliance* for supported specification.

A Web application requiring an ACR for a subscriber requests one from Services Gatekeeper using the RESTful interface. Services Gatekeeper generates and manages one or more ACRs for the subscriber when requested by the Web application.

Configuring ACR Support in Services Gatekeeper

Services Gatekeeper supports ACR operations by default. After you create an ACR plug-in instance, applications can create, query and refresh ACRs using the RESTful interface on a Services Gatekeeper system.

Creating an ACR Plug-in Instance

Services Gatekeeper and the Platform Test Environment MBean interface can be used to create and manage ACR plug-ins. For information on using the Platform Test Environment, see Services Gatekeeper Platform Test Environment User's Guide.

To create an instance of the ACR plug-in in Services Gatekeeper:

1. Log in to the Administration Console.

- **2.** Expand the **OCSG** node under **Domain Structure**.
- Click the name of the administration or managed server on which to create the ACR plug-in instance.
- 4. Expand the Container Services node under Oracle Communications Services Gatekeeper.
- 5. Select PluginManager.
- **6.** Click **Operations**.
- 7. In the **Select An Option** menu, select **createPluginInstsance**.
- **8.** Enter **Plugin_acr** in the **PluginServiceId** field.
- Enter a unique name in the **PluginInstanceId** field.
- 10. Click Invoke.
- **11.** Add a route to the ACR plug-in using the **pluginManager** Mbean.

Setting ACR Plug-in Parameters

To configure the ACR plug-in attributes in Table 6–1:

- **1.** Log in to the Administration Console.
- **2.** Expand the **OCSG** node under **Domain Structure**.
- 3. Select the administration or managed server where you created the ACR plug-in.
- 4. Expand the Communication Services node under Oracle Communications Services Gatekeeper.
- **5.** Select the ACR plug-in instance to configure.
- 6. Click Attributes.
- **7.** Select the checkboxes of the attributes you want to change.
- **8.** Enter the new values for the attributes.
- 9. Click Update Attributes.

Table 6-1 ACR Plug-in Attributes

Attribute	Туре	Description
Ncc	String	The network-code of the operator. In Services Gatekeeper, this is the same as a service provider group.
AcrExpiredLifeTime	Integer	The number of seconds that ACR is kept in Expired state before being deleted. Default Value: 60
AcrLifeTime	Integer	The number of seconds a generated or refreshed ACR is valid. Default value: 3600
TrafficAcrMappingEnabled	Boolean	Whether to enable ACR mapping in network traffic. Default value: False

Creating Multiple ACRs for a Single Subscriber

You can create multiple ACRs for the same subscriber or MSISDN. Services Gatekeeper creates a unique ACR for each application. Use this setup to route application requests containing ACR identifiers to the correct service provider group.

RESTful APIs for ACR Support

You can generate and manage ACRs in Services Gatekeeper using the RESTful API described below.

- Create ACR
- Query ACR
- Change ACR Status
- **Errors and Exceptions**

Create ACR

The Create ACR operation creates a new ACR for a subscriber based on the MSISDN.

Authorization

Basic or OAuth

HTTP Method

POST

URI

http://host:port/customerReference/version/address

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- version is the supported version of the RESTful Network API for Roaming Provisioning.
- address is the subscriber identifier MSISDN. Services Gatekeeper supports an address entry of acr: authorization, where authorization is an OAuth accessToken.

Note: *address* must be URL-escaped in accordance with RFC 1738.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for Create ACR accepts the following parameters:

- acr: String.
- status: String.
- expiry: String.

Response Header

The response header indicates whether the ACR was successfully created. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Errors and Exceptions" for more information.

Response Body

The response body contains the following parameters:

- acr: String. The Services Gatekeeper generated ACR.
- status: String. The current status of the ACR: Valid or Expired.
- **expiry**: String. The expiration time of the ACR.

Examples

Example 6–1 shows a sample Create ACR request.

Example 6–1 Create ACR Request Example

```
POST http://example.com/customerReference/v1/tel%3A%2B7990123456
HTTP/1.1
Host: example.com:80
Accept: application/json
{"acr":{"status":"Valid"}}
```

Example 6–2 shows a sample Create ACR response.

Example 6-2 Create ACR Response Example

```
HTTP/1.1 201 Created
Content-Type: application/json
Content-Length: 1234
Date: Thu, 04 Jun 2009 02:51:59 GMT
{"acr": "acr:0123456890123456789;ncc=23415",
"status": "Valid",
"expiry": "Thu 11 Jun 2009 02:51:59 GMT"}
```

Query ACR

The Query ACR operation queries for the ACR status of the referenced subscriber. The status of the ACR indicates whether the reference is valid or expired.

Authorization

Basic or OAuth

HTTP Method

GET

URI

http://host:port/customerReference/version/address/acr

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- version is the supported version of the RESTful Network API for Roaming Provisioning.
- address is the subscriber MSISDN.
- acr is the ACR for which the status query is being made, including the network-code (ncc).

Note: address and acr must be URL-escaped in accordance with RFC 1738.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Errors and Exceptions".

Response Body

The response body contains the following parameters:

- **acr**: String. The Services Gatekeeper generated ACR.
- status: String. The current status of the ACR: Valid or Expired.

Examples

Example 6–3 shows a sample Query ACR request.

Example 6–3 Query ACR Request Example

789%3Bncc=23415

Example 6–4 shows a sample Query ACR response.

Example 6-4 Query ACR Response Example

{"acr":{"status":"Valid"}}

Change ACR Status

The Change ACR Status operation refreshes an expired ACR to a valid status.

Authorization

Sessionless: Basic, Sessionful: Basic and Session ID, or OAuth

HTTP Method

POST

URI

http://host:port/customerReference/version/address/acr

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- version is the supported version of the RESTful Network API for Roaming Provisioning.
- address is the subscriber MSISDN.
- acr is the ACR for which the status query is being made, including the network-code (ncc).

Note: *address* and *acr* must be URL-escaped in accordance with RFC 1738.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for Change ACR Status accepts the following parameters:

- acr: String.
- status: String.
- expiry: String.
- developerId: String. Required. The RESTful developer ID.
- applicationId: String. Optional. The Services Gatekeeper application ID.

Response Header

The response header indicates whether the ACR status was successfully changed. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Errors and Exceptions" for more information.

Response Body

The response body contains the following parameters:

- acr: String. The Services Gatekeeper generated ACR.
- status: String. The updated status of the ACR.
- **expiry**: String. The new expiration time of the ACR.

Examples

Example 6–5 shows a sample Change ACR request.

Example 6–5 Change ACR Status Request Example

```
http://example.com/customerReference/v1/tel%3A%2B7990123456/acr%3A0123456890123456
789%3Bncc=23415
HTTP/1.1
Host: example.com:80
Accept: application/json
{"acr":{"status":"Valid"}}
```

Example 6–6 shows a sample Change ACR response.

Example 6-6 Change ACR Status Response Example

```
Content-Type: application/json
Content-Length: 1234
Date: Thu, 04 Jun 2009 02:51:59 GMT
{"acr": "acr:0123456890123456789;ncc=23415",
"status": "Valid",
"expiry": "Thu 11 Jun 2014 02:51:59 GMT"
```

Errors and Exceptions

The Status-Line in the response message indicates the protocol version, the three-digit status code, and the reason for the failure of a request. Table 6–2 lists the possible error codes for failed requests.

Table 6–2 ACR Operations Error Codes

Error Code	Cause	
303	The request to create the ACR failed, because the ACR for the MSISDN exists.	
400	Bad request. Check the error message and correct the request syntax.	
	For example, a request with {address} whose value is "MSISDN B" is attempting to query/change acr of an {address} whose value is "MSISDN A"	
401	The request from network-code A is attempting to change/query acr of network-code B	
404	The request is attempting to query an invalid or expired ACR	
503	Server busy and service unavailable. Retry the request.	

EDRs

Table 6–3 lists the EDRs generated by ACR operations.

Table 6–3 ACR Operations EDRs

EDR	Service	Method	Description	
408001	oracle.ocsg.parlayrest.plugin.AcrPlugin	CreateAcrResp createAcr	create acr code for address	
408002	oracle.ocsg.parlayrest.plugin.AcrPlugin	QueryAcrResp queryAcr	query acr code for address	
408003	oracle.ocsg.parlayrest.plugin.AcrPlugin	ChangeAcrResp ChangeAcr	change acr code for address	

Adding RESTful Application Subscription Management Support

This chapter describes the operations in the Application Subscription Management interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About Application Subscription Management

The Services Gatekeeper Application Subscription Management supports Open Mobile Alliance (OMA) General Service Subscription Management (GSSM) functionality including subscription management, subscription profile access, and subscription validation.

For information on the OMA GSSM specification see:

http://technical.openmobilealliance.org/Technical/release program/gssm v1

Application Subscription Management includes both a communication service and RESTful interfaces for managing and querying service subscription status. Applications use the RESTful interfaces to manage subscriptions and query subscription status. Application Subscription Management grants or restricts application access to a subscriber's communication services based on the subscription status. Application Subscription Management also supports OAuth authentication when required.

For information on using the Application Subscription Management communication service, including deploying, configuring and monitoring, see Services Gatekeeper Communication Service Reference Guide.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of Service Subscription Management interface operations can be found at

http://host:port/subscription/application.wadl

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Subscribe

The Subscribe operation creates a new application service subscription request for a subscriber based on the MSISDN.

Authorization

Basic or OAuth

HTTP Method

POST

URI

http://host:port/subscription

where:

host and port are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for Subscribe accepts the following parameters:

- **applicationName**: String. The name of the application subscribed to.
- **subscriberAddress**: String. The MSISDN of the subscriber making the request.

Response Header

The response header indicates whether the subscription request was successfully created. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See Services Gatekeeper Communication Service Reference *Guide,* for more information on error messages.

Response Body

The response body contains the following parameters:

- **subscriptionResponse**: String. The Services Gatekeeper generated response containing the subscription ID.
 - **subscriptionID**: String. The ID of the new subscription.

Examples

Example 7–1 shows a sample Subscribe request.

Example 7–1 Subscribe Request Example

POST /subscription HTTP/1.1 Content-Type: application/x-www-form-urlencoded Authorization: Basic YXBwX3VzZXI6YXBwX3VzZXI=

```
Accept: application/json
Content-Length: 60
Host: vm-at1:8001
Connection: Keep-Alive
User-Agent: Apache-HttpClient/4.1.1 (java 1.5)
applicationName=Mickey News&subscriberAddress=tel:0703322124
```

Example 7–2 shows a sample Subscribe response.

Example 7–2 Subscribe Response Example

```
HTTP/1.1 201 Created
Date: Wed, 01 Jul 2015 07:13:07 GMT
Content-Length: 78
Content-Type: application/json
{"subscriptionResp":{"subscriptionId":"1a7afc44-9e68-4dc6-aaf4-07610a9fdef0"}}
```

Unsubscribe

The Unsubscribe operation is used to request a subscription deletion.

Authorization

Basic or OAuth

HTTP Method

DELETE

URI

 $\verb|http://host:port/subscription||$

where:

host and port are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The Unsubscribe request header contains the subscription ID to be deleted. The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no response body.

Response Header

The response header indicates whether the ACR status was successfully changed. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See Services Gatekeeper Communication Service Reference Guide, for more information on error messages.

Response Body

The response body contains no content.

Examples

Example 7–3 shows a sample Unsubscribe request.

Example 7–3 Unsubscribe Request Example

```
DELETE /subscription/e4e3cb51-994b-46e1-b0d1-0757a8bca25f HTTP/1.1
Host: example.com:80
Accept: application/json
```

Example 7–4 shows a sample Unsubscribe response.

Example 7-4 Unsubscribe Response Example

HTTP/1.1 204 No Content

Suspend

The Suspend operation suspends an existing service subscription for a subscriber based on the subscription ID.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/subscription/suspend/subscriptionID

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *subscriptionID* is the ID of the subscription to be suspended.

Request Header

The Suspend request header contains the ID of the subscription to be suspended. The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for Suspend is empty.

Response Header

The response header indicates whether the subscription was successfully suspended. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See Services Gatekeeper Communication Service Reference Guide, for more information on error messages.

Response Body

The response body contains no content.

Examples

Example 7–5 shows a sample Suspend request.

Example 7–5 Suspend Request Example

```
PUT /subscription/suspend/e4e3cb51-994b-46e1-b0d1-0757a8bca25f HTTP/1.1
Host: example.com:80
Accept: application/json
```

Example 7–6 shows a sample Suspend response.

Example 7–6 Suspend Response Example

HTTP/1.1 204 No Content

Unsuspend

The Unsuspend operation unsuspends an existing service subscription for a subscriber based on subscription ID.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/subscription/unsuspend/subscriptionID

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *subscriptionID* is the ID of the subscription to be suspended.

Request Header

The Unsuspend request header contains the subscription ID to be unsuspended. The MIME-type for the Content-Type header field is application/json

Request Body

The request body for unsuspend is empty.

Response Header

The response header indicates whether the subscription was successfully removed from being suspended. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See Services Gatekeeper Communication Service Reference Guide, for more information on error messages.

Response Body

The response body contains no content.

Examples

Example 7–7 shows a sample Unsuspend request.

Example 7–7 Unsuspend Request Example

```
PUT /subscription/unsuspend/e4e3cb51-994b-46e1-b0d1-0757a8bca25f HTTP/1.1
Host: example.com:80
Accept: application/json
```

Example 7–8 shows a sample Unuspend response.

Example 7–8 Unsuspend Response Example

HTTP/1.1 204 No Content

Notify

The Notify operation notifies a registered application of a subscription management request.

Authorization

Basic or OAuth

HTTP Method

POST

URI

http://host:port/notify

where:

host and port are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for Notify accepts the following parameters:

- subscriptionNotification. The Services Gatekeeper generated notification containing the following parameters:
 - **subscriptionID**: String. The ID of the subscription request.
 - **applicationName**: String. The name of the application receiving the request.
 - subscriberAddress: String. The MSISDN of the requesting subscriber.
 - **operation**: String. The subscription request type. For example, **Subscribe** or Unsubscribe.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. Services Gatekeeper Communication Service Reference Guide, for more information on error messages.

Response Body

The response body contains no content.

Examples

Example 7–9 shows a sample Notify request.

Example 7–9 Notify Request Example

POST /notifysubscription HTTP/1.1

```
Host: example.com:80
Accept: application/json
Content-Type: application/json
Content-Length: 173
{"subscriptionNotification":{"subscriptionId":
\verb|"e4e3cb51-994b-46e1-b0d1-0757a8bca25f", \verb|"applicationName": \verb|"Oracle|| \\
News", "subscriberAddress":"tel:1111", "operation":"Subscribe"}}
```

Example 7–10 shows a sample Notify response.

Example 7–10 Notify Response Example

HTTP/1.1 204 No Content

Confirm

The Confirm operation is used by applications to confirm subscription requests.

Authorization

Basic or OAuth

HTTP Method

PUT

URI

http://host:port/subscription/confirm

where:

host and port are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for Confirm accepts the following parameters:

- **operation**: String. The subscription request operation being confirmed. For example, **Subscribe** or **Unsubscribe**.
- **confirmResult**: String. The subscription request status. For example, **approved**.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See Services Gatekeeper Communication Service *Reference Guide*, for more information on error messages.

Response Body

The response body contains the following parameter:

oauthAccessToken: String. If OAuth is required, Services Gatekeeper returns an OAuth accessToken in the response.

Examples

Example 7–11 shows a sample Confirm request.

Example 7-11 Confirm Request Example

```
PUT /subscription/confirm/e4e3cb51-994b-46e1-b0d1-0757a8bca25f HTTP/1.1
Host: example.com:80
Accept: application/json
Content-Type: application/x-www-form-urlencoded
Content-Length: 42
operation=Subscribe&confirmResult=Approved
```

Example 7–12 shows a sample Confirm response with an OAuth accessToken.

Example 7–12 Confirm Response Example

HTTP/1.1 200 OK

Content-Type: application/json Date: Wed, 07 Nov 2012 06:39:50 GMT

{"oauthAccessToken":{"oauthAccessToken":"e4e3cb51-994b-46e1-b0d1-0757a8bca25f"}}

queryBySubscriberAddress

The queryBySubscriberAddress operation retrieves a user's subscription information based on the subscriber address.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/subscription/query/queryBySubscriberAddress

where:

host and port are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The queryBySubscriberAddress request header contains the subscriber address (MSISDN) to be queried. The MIME-type for the Content-Type header field is application/json.

Request Body

The request body for queryBySubscriberAddress is empty.

Response Header

The response header includes the request status. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See Services Gatekeeper Communication Service Reference Guide, for more information on error messages.

Response Body

The request body for queryBySubscriberAddress contains the following parameters:

- **subscriptionList**. The Services Gatekeeper generated list containing the following parameters:
 - subscriptionInfo. Array. Contains the following parameters for each subscription.
 - **applicationName**: String. The name of the subscribed application.
 - **subscriberAddress**: String. The MSISDN of the subscriber.
 - status: String. The subscription status. For example, Pending.

Examples

Example 7–13 shows a sample queryBySubscriberAddress request.

Example 7-13 queryBySubscriberAddress Request Example

```
GET /subscription/query/queryBySubscriberAddress/tel:1111?offSet=0&batchSize=2
HTTP/1.1
Host: example.com:80
Accept: application/json
```

Example 7–14 shows a sample queryBySubscriberAddress response.

Example 7–14 queryBySubscriberAddress Response Example

```
HTTP/1.1 200 OK
Content-Type: application/json
Date: Wed, 07 Nov 2012 06:56:05 GMT
{"subscriptionList":{"subscriptionInfo":[{"applicationName":"coderslist",
"subscriberAddress":"tel:1111", "status": "SubscribePending"}, { "applicationName":
"Oracle News", "subscriberAddress": "tel:1111",
"status": "UnSubscribePending"}]}}
```

queryByApplicationName

The queryByApplicationName operation retrieves a list of subscribers to an application based on the application ID.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/subscription/query/queryByApplicationName

where:

host and port are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The queryByApplicationName request header contains the application name to be queried. The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for queryBySubscriberAddress is empty.

Response Header

The response header includes the request status. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See Services Gatekeeper Communication Service Reference Guide, for more information on error messages.

Response Body

The request body for queryByApplicationName contains the following parameters:

- subscriptionList. The Services Gatekeeper generated list containing the following parameters:
 - subscriptionInfo. Array. Contains the following parameters for each subscribed user.
 - **applicationName**: String. The name of the subscribed application.
 - **subscriberAddress**: String. The MSISDN of the subscriber.
 - status: String. The subscription status. For example, Pending.

Examples

Example 7–15 shows a sample queryByApplicationName request.

Example 7–15 queryByApplicationName Request Example

```
GET /subscription/query/queryByApplicationName/Oracle%20News?offSet=0&
batchSize=2 HTTP/1.1
Host: example.com:80
Accept: application/json
```

Example 7–16 shows a sample queryByApplicationName response.

Example 7–16 queryByApplicationName Response Example

```
HTTP/1.1 200 OK
Content-Type: application/json
Date: Wed, 07 Nov 2012 06:56:05 GMT
{"subscriptionList":{"subscriptionInfo":[{"applicationName":"Oracle
News", "subscriberAddress": "tel:1111", "status": "UnSubscribePending"},
{"applicationName":"Oracle
News","subscriberAddress":"tel:1112","status":"Active"}]}}
```

queryBySubscriptionID

The queryBySubscriptionID operation retrieves application subscription information for a subscriber based on the subscription ID.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/subscription/query/queryBySubscriptionID

where:

host and port are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The queryBySubscriptionID request header contains the subscription ID to be queried. The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for queryBySubscriptionID is empty.

Response Header

The response header includes the request status. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See Services Gatekeeper Communication Service Reference Guide, for more information on error messages.

Response Body

The request body for queryBySubscriptionID contains the following:

- subscriptionInfo. The Services Gatekeeper generated list with the following parameters:
 - **applicationName**: String. The name of the subscribed application.
 - subscriberAddress: String. The MSISDN of the subscriber.
 - status: String. The subscription status. For example, Pending.

Examples

Example 7–17 shows a sample queryBySubscriptionID request.

Example 7–17 queryBySubscriptionID Request Example

GET /subscription/query/queryBySubscriptionId/e4e3cb51-994b-46e1-b0d1-0757 a8bca25f HTTP/1.1

```
Host: example.com:80
Accept: application/json
```

Example 7–18 shows a sample query By Subscription ID response.

Example 7–18 queryBySubscriptionID Response Example

```
HTTP/1.1 200 OK
Content-Type: application/json
Date: Wed, 07 Nov 2012 06:56:05 GMT
{"subscriptionInfo":{"applicationName":"Oracle
News", "subscriberAddress": "tel:1111", "status": "UnSubscribePending"}}
HTTP/1.1 200 OK
```

Adding RESTful Call Notification Support

This chapter describes the operations in the Call Notification interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Call Notification Interface

Applications use the RESTful Call Notification interface to set up and remove call notifications which inform the application about the particular state of a call (such as busy, unreachable, and so on).

Additionally, applications use this interface to set up and remove call direction notifications (which require the application to provide further directions on handling a call that is in a particular state).

For the interface operations, the application client subscribes to and uses the Bayeux channel to which Services Gatekeeper is subscribed. The application provides the Bayeux channel name as the location for Services Gatekeeper to publish the notifications that the application client requires. See "RESTful Notifications and Publish/Subscribe" for more information about publishing and subscribing to notifications.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/call_notification/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Common Data

The details the application receives about a call event are identical whether the called party was busy (**Busy**), not reachable (**NotReachable**), or did not answer (**NoAnswer**), or the call was still being attempted (CalledNumber).

These details are provided to the application in a JSON object which contains the following parameters:

- calledParty: String. Required. The address (URI) of the party to whom the call is
- callingParty: String. Required. The address (URI) of the party making the call.

- correlator: String. Required. The correlator used to identify the notification and provided in the Start Call Notification request.
- callingPartyName: String. Optional. The name of the party making the call.

These details are specified in the following structure:

```
"calledParty": "URI",
  "callingParty": "URI",
  "correlator": "String",
  "callingPartyName": "String"
}
```

You will find this object in the following operations:

- Start Call Notification: For this operation, the JSON object is used to provide the call details in the notifications sent (by Services Gatekeeper) to the application following a successful Start Call Notification Request. See "Notification Data Object Delivered to Bayeux Channel Name".
- Start Call Direction Notification: For this operation, the JSON object is used to provide the call details in the notifications sent (by Services Gatekeeper) to the application to request instructions (from the application) on handling a call event that has occurred. See "Notification Data Object Requesting Instruction from Application".

Start Call Notification

The Start Call Notification operation sets up call notifications to a specified endpoint address for call events associated with the addresses specified in the request.

To set up a call notification, provide the SIP-formatted URI of the addresses for which the application must receive notifications, the criteria that will trigger notifications, and a **reference** object for the delivery of the notifications. The criteria can be one or more of four possible call events: **Busy**, **NotReachable**, **NoAnswer**, and **CalledNumber**. If you do not specify any value for **criteria**, each call event will trigger a notification.

The reference object (also a JSON object) contains the **correlator** for the notification, the **endpoint** address to which the notifications must be sent and, optionally, the interface name (a string to identify the notification).

If the Start Call Notification request is successful:

- The response header will contain the URI of the publish/subscribe server.
- Notification data objects appropriate to the call event will be sent to the endpoint address specified in the request body. Each data object will contain the appropriate notification on the call.

When the application receives such a response, it must access the **endpoint** address to retrieve the specific call event notifications.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/call_notification/call_notification

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for Start Call Notification accepts the following parameters:

- addresses: Array of string values. Required. The set of addresses to be monitored, provided as a list of URIs separated by commas.
- **criteria**: String. Optional. The call event for which the notification is required.

If you do not specify any value for **criteria**, all call events will trigger a notification. The call events are:

Busy: This entry indicates that the called party is busy.

- **CalledNumber**: This entry indicates that a call between the two parties is being attempted.
- **NoAnswer**: This entry indicates that the called party does not answer.
- **NotReachable**: This entry indicates that the called party is not reachable.
- **reference.** A JSON object. Required. Use this object to provide the following information about the endpoint address that is to receive the notification:
 - **correlator**: String. Required. The correlator used to identify the call notifications for the specified addresses.
 - endpoint: String. Required. The endpoint address to which the notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where appInstanceID is the client application's application instance account ID.
 - For more information on application instances, see the discussion on managing application instances in Services Gatekeeper Portal Developer's Guide.
 - interfaceName: String. Optional. A descriptive string to identify the notification.

The request body for this operation is represented by the following JSON structure, where the value part of each name/value pair indicates its data type:

```
"addresses": ["String"],
"reference": {
  "correlator": "String",
 "endpoint": "URI",
  "interfaceName": "String"
},
"criteria": ["Busy | NotReachable | NoAnswer | CalledNumber"]
```

Response Header

The Location header field contains the URI of the publish/subscribe server as:

```
http://host:port/rest/call_notification/notifications
```

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body. The appropriate notifications are sent to the **endpoint** address provided by the application in the request body of this operation. See "Notification Data Object Delivered to Bayeux Channel Name" for a description of each type of notification object.

Notification Data Object Delivered to Bayeux Channel Name

Services Gatekeeper delivers the appropriate notification for each of the following call events:

Busy: When the called party is busy, the notification is sent as the value for **notifyBusy**, represented by the following JSON structure:

```
{"notifyBusy": {
 "calledParty": "URI",
```

```
"callingParty": "URI",
"correlator": "String",
"callingPartyName": "String"
```

NotReachable: When the called party is not reachable, the notification is sent as the value for **notifyNotReachable**, represented by the following JSON structure:

```
{"notifyNotReachable": {
  "calledParty": "URI",
 "callingParty": "URI",
 "correlator": "String",
  "callingPartyName": "String"
}}
```

NoAnswer: When the called party does not answer, the notification is sent as the value for **notifyNoAnswer**, represented by the following JSON structure:

```
{"notifyNoAnswer": {
  "calledParty": "URI",
  "callingParty": "URI",
  "correlator": "String",
  "callingPartyName": "String"
```

CalledNumber: When the called party call is being attempted, the notification is sent as the value for notifyCalledNumber, represented by the following JSON structure:

```
{"notifyCalledNumber": {
  "calledParty": "URI",
  "callingParty": "URI",
 "correlator": "String",
  "callingPartyName": "String"
```

Stop Call Notification

The Stop Call Notification operation generates a request that terminates a previously set up call notification.

To stop a previously set up call notification, use the appropriate correlator in the DELETE method for this operation. This correlator should have been specified earlier in the request body of the Start Call Notification operation.

There is no request or response body for the Stop Call Notification operation. If the request fails, the body of the error response will contain the identifier for the notification and the type of exception.

Authorization

Basic

HTTP Method

DELETE

URI

http://host:port/rest/call_notification/call_notification/\${correlator}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\${correlator}* is the correlator for the notification provided in the **reference** object of the initial Start Call Notification request.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Start Call Direction Notification

The Start Call Direction Notification operation initiates notifications to a specified endpoint for call events associated with the addresses specified in the request. The notifications provided by Services Gatekeeper will contain the information necessary for the application to provide instructions on directing the call.

To set up a call direction notification, provide the SIP-formatted URI of the addresses for which the application must receive notifications, the criteria that will trigger notifications, and a reference object for the delivery of the notifications. The criteria can be one more of four possible call events: Busy, NotReachable, NoAnswer, and CalledNumber. If you do not specify any value for criteria, each event will trigger a notification.

The reference object (also a JSON object) contains the **correlator** for the notification, the endpoint address (a specific Bayeux channel name) to which the call direction notifications must be sent and, optionally, the interface name (a string to identify the notification).

If the Start Call Direction Notification request is successful:

- The response header will contain the URI of the publish/subscribe server.
- A notification data object appropriate to the call event will be sent to the endpoint address specified in the request body. This data object will contain the appropriate notification on the call. It will also contain the reply-to private channel address to be used by the application to provide further instructions on handling and routing the call.

When it receives a response, the application:

- 1. Retrieves the notification data object from the endpoint address. See "Notification Data Object Requesting Instruction from Application".
- 2. Sets up a data object with instructions on how the call must be handled (and charged); and an address to which the call must now be routed. See "Call-Handling Instructions".
- Publishes the data object to the reply-to private channel address it received. See "Application's Call-Handling Response to Services Gatekeeper".

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/call_notification/call_direction

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Start Call Direction Notification accepts the following parameters:

- addresses: Array of string values. Required. The set of addresses to be monitored, provided as a list of SIP-formatted URIs separated by commas.
- **criteria**: String. Optional. The call event for which the notification is required.

If you do not specify any value for **criteria**, all call events will trigger a notification. The call events are:

- **Busy**: This entry indicates that the called party is busy.
- **CalledNumber**: This entry indicates that a call between the two parties is being attempted.
- **NoAnswer**: This entry indicates that the called party does not answer.
- **NotReachable**: This entry indicates that the called party is not reachable.
- reference: A JSON object. Required. Use this object to provide the following information about the call direction notification:
 - **correlator**: String. Required. The correlator used to identify the call direction notification for the specified addresses.
 - endpoint: String. Required. The URI which represents the endpoint address to which the call direction notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where *appInstanceID* is the client application's application instance account ID.

For more information on application instances, see the discussion on managing application instances in Services Gatekeeper Portal Developer's Guide.

interfaceName: String. Optional. A descriptive string to identify the notification.

The request body for this operation is represented by the following JSON structure, where the value part of each name/value pair indicates its data type:

```
"addresses": ["String"],
"reference": {
  "correlator": "String",
  "endpoint": "URI",
  "interfaceName": "String"
"criteria": ["Busy|NotReachable|NoAnswer|CalledNumber"]
```

Response Header

The Location header in the response displays the URI of the publish/subscribe server:

```
http://host:port/rest/call_notification/notifications
```

The application must access this location to retrieve the notification or delivery status information about the request.

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

The **endpoint** address holds the appropriate notification data object containing information on the type of call event when there is a match for the **criteria** value specified in the request body of this operation.

Notification Data Object Requesting Instruction from Application

When the application needs to take further action on a call event, Services Gatekeeper provides the application with a corresponding notification data object for the application to act upon.

Services Gatekeeper places this notification data object at the **endpoint** address mentioned in the response header. The notification data object is a nested JSON object containing the following parameters:

- reply-to: String. The Bayeux channel address to which the application must deliver its instructions for handling the call. This is a private Bayeux channel set up by Services Gatekeeper.
- data: Nested JSON object. Services Gatekeeper provides the appropriate call details as the value for handleBusy, handleNotReachable, handleNoAnswer, handleCalledNumber, which are named for the four types of call events. These details have been described under "Common Data".
 - handleBusy: For a Busy call event, Services Gatekeeper provides the appropriate call details as the value for the attribute **handleBusy** in the following JSON structure:

```
{"handleBusy": {
  "calledParty": "URI",
  "callingParty": "URI",
  "correlator": "String",
  "callingPartyName": "String"
}}
```

handleNotReachable: For a NotReachable call event, Services Gatekeeper provides the appropriate call details as the value for the attribute handleNotReachable in the following JSON structure:

```
{"handleNotReachable": {
 "calledParty": "URI",
 "callingParty": "URI",
 "correlator": "String",
  "callingPartyName": "String"
}}
```

handleNoAnswer: For a NoAnswer call event, Services Gatekeeper provides the appropriate call details as the value for the attribute handleNoAnswer in the following JSON structure:

```
{"handleNoAnswer": {
  "calledParty": "URI",
  "callingParty": "URI",
  "correlator": "String",
  "callingPartyName": "String"
}}
```

handleCalledNumber: For a CalledNumber call event, Services Gatekeeper provides the appropriate call details as the value for the attribute handleCalledNumber in the following JSON structure:

```
{"handleCalledNumber": {
  "calledParty": "URI",
  "callingParty": "URI",
  "correlator": "String",
  "callingPartyName": "String"
}}
```

Call-Handling Instructions

Whether the call event is Busy, NotReachable, NoAnswer or CalledNumber, the application needs to specify the following:

- actionToPerform: String. Required. Specifies the required action to take on the call. Services Gatekeeper must perform the following actions with respect to the call:
 - **Route**: Re-route the call to a specified address.
 - **Continue**: Handle the call in the normal way.
 - **EndCall**: Terminate the call.
- charging: A JSON object. Optional. This object defines the cost charging properties for the call. A call with no charging parameters is entered as "charging: null. If a charge is to be applied, provide values for the following in the **charging** object:
 - **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
 - amount: Number (integer, or decimal). Optional. The amount to be charged.
 - code: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- routingAddress: String. URI. The address to which the call must be routed.

Application's Call-Handling Response to Services Gatekeeper

The application sends the appropriate instruction as the response to the **reply-to** address it had retrieved earlier from the endpoint address. See "Notification Data Object Requesting Instruction from Application".

The possible responses that the application provides to Services Gatekeeper are:

Instructions to handle a **Busy** call event: The application provides the instruction data as the value for **handleBusyResponse** in the following JSON structure:

```
{"handleBusyResponse": {"result": {
  "actionToPerform": "Route | Continue | EndCall",
  "charging": {
    "description": "String",
    "amount": "BigDecimal",
    "code": "String",
    "currency": "String"
  "routingAddress": "URI"
}}}
```

Instructions to handle a **NotReachable** call event: The application provides the instruction data as the value for handleNotReachableResponse in the following ISON structure:

```
{"handleNotReachableResponse": {"result": {
  "actionToPerform": "Route | Continue | EndCall",
  "charging": {
   "description": "String",
   "amount": "BigDecimal",
   "code": "String",
   "currency": "String"
 },
  "routingAddress": "URI"
}}}
```

Instructions to handle a **NoAnswer** call event: The application provides the instruction data as the value for handleNoAnswerResponse in the following JSON structure:

```
{"handleNoAnswerResponse": {"result": {
  "actionToPerform": "Route | Continue | EndCall",
  "charging": {
   "description": "String",
   "amount": "BigDecimal",
   "code": "String",
   "currency": "String"
 },
  "routingAddress": "URI"
}}}
```

Instructions to handle a **CalledNumber** call event: The application provides the instruction data as the value for handleCalledNumberResponse call event in the following JSON structure:

```
{"handleCalledNumberResponse": {"result": {
  "actionToPerform": "Route | Continue | EndCall",
  "charging": {
    "description": "String",
    "amount": "BigDecimal",
   "code": "String",
    "currency": "String"
 },
  "routingAddress": "URI"
}}}
```

Stop Call Direction Notification

The Stop Call Direction Notification operation terminates a previously set up call direction notification.

To stop a previously set-up call direction notification, use the appropriate correlator in the DELETE request for this operation. This correlator should have been specified earlier in the request body of the Start Call Direction Notification operation.

There is no request or response body for the Stop Call Direction Notification operation. If the request fails, the body of the error response will contain the identifier for the notification and the type of exception.

Authorization

Basic

HTTP Method

DELETE

URI

http://host:port/rest/call_notification/call_direction/\${correlator}

where:

- *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.
- *\${correlator}* is the correlator for the notification provided in the **reference** object of the initial Start Call Direction Notification request.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Adding RESTful Short Messaging Support

This chapter describes the operations in the Short Messaging interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Short Messaging Interface

Applications use the RESTful Short Messaging interface to send an SMS, a ringtone, or a logo, to fetch SMS messages and delivery status reports; and to start and stop a notification.

When the request body for an SMS operation contains a request for a delivery receipt, the application provides a correlator for the message being sent and includes an endpoint address for returning the delivery notification.

For such operations, the application client subscribes to and uses the Bayeux channel to which Services Gatekeeper is subscribed. The application provides the Bayeux channel name as the location for Services Gatekeeper to publish the notifications that the application client requires. See "RESTful Notifications and Publish/Subscribe" for more information about publishing and subscribing to RESTful notifications.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/sms/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Send SMS

The Send SMS operation delivers a text message.

To send an SMS message, provide the SIP-formatted URI of the addresses which must receive the message in the request body. If there is to be a charge for the messaging, the request body should contain the required charging object. If the sender requires a delivery receipt, specify the required parameters for the receipt.

If the Send SMS operation is successful, the **Location** header field in the response will contain the request identifier (which is also provided in the response body for this operation).

If the application requested a receipt for delivery of the message, the application must access the **endpoint** address to retrieve the delivery notifications.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/sms/messages

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Send SMS operation accepts the following parameters:

- addresses: Array of string values. Required. The set of addresses of the recipients as an array of SIP-formatted URIs.
- **message**: String. Required. The text of the message.
- charging: A JSON object. Optional. This object defines the cost charging properties for the operation. The entry "charging": null indicates no charge. If a charge is to be applied, provide values for the following in the **charging** object:
 - **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
 - **amount**: Number (integer, or decimal). Optional. The amount to be charged.
 - code: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- receiptRequest: A JSON object. Optional. If a delivery receipt is required, provide values for each of the following parameters which define this object:

correlator: String. Required. Used to correlate the receipt with the initial message.

If the callback reference **correlator** is defined in the **receiptRequest** object of the Send SMS request message, Services Gatekeeper will invoke the Notify SMS Delivery Receipt operation and discard the delivery status information.

- endpoint: String. Required. The endpoint address (URI) to which the receipt must be delivered.
- interfaceName: String. Required. A description provided to identify the type of receipt.
- **senderName**: String. Optional. The sender's name.

The request body for this operation is represented by the following JSON structure, where the value part of each name/value pair indicates its data type:

```
"addresses": ["URI"],
  "message": "String",
  "charging": {
    "description": "String",
    "amount": "BigDecimal",
    "code": "String",
    "currency": "String"
  "receiptRequest": {
    "correlator": "String",
    "endpoint": "URI",
    "interfaceName": "String"
 },
  "senderName": "String"
}
```

Response Header

The Location header field contains the URI:

```
http://host:port/rest/sms/delivery_status/result
```

where, *result* is the string identifier returned in the response body.

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The body of the response contains the request identifier as the string value for the result object; it is the request identifier returned in the Location header field of the response message. The application uses this request identifier (in the Get SMS Delivery Status operation) to retrieve the delivery status for the sent message.

The response body for this operation is represented by the following JSON structure, where the value part of the name/value pair indicates its data type:

```
{"result": "String"}
```

Send SMS Ringtone

The Send SMS Ringtone operation delivers a ringtone.

To send an SMS Ringtone message, provide the SIP-formatted URI of the addresses which must receive the message, the ringtone data and its format in the request body for this operation. If there is to be a charge for the messaging, the request body should contain the required charging object. If the sender requires a delivery receipt, specify the required parameters for the receipt.

If the Send SMS Ringtone operation is successful, the Location header field in the response will contain the request identifier (which is also provided in the response body for this operation).

If the application requested a receipt for delivery of the message, the application must access the endpoint address to retrieve the delivery notifications.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/sms/ringtones

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body is a nested JSON object containing the following parameters:

- addresses: Array of string values. Required. The set of addresses of the recipients as an array of SIP-formatted URIs.
- ringtone: String. Required. The ringtone data in Extended Ringtone (RTX) format.
- smsFormat: String. Required. The encoding format for the ringtone entered as one of the following:
 - **Ems**
 - SmartMessaging
- charging: A JSON object. Optional. This object defines the cost charging properties for the operation. The entry "charging": null indicates no charge. If a charge is to be applied, provide values for the following in the **charging** object:
 - **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
 - amount: Number (integer, or decimal). Optional. The amount to be charged.

- **code**: String. Optional. The charging code, from an existing contractual description.
- currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- receiptRequest: A JSON object. Optional. If a delivery receipt is required, provide values for each of the following parameters which define this object:
 - correlator: String. Required. Used to correlate the receipt with the initial message.
 - If the callback reference **correlator** is defined in the **receiptRequest** object of the Send SMS request message, Services Gatekeeper will invoke the Notify SMS Delivery Receipt operation and discard the delivery status information.
 - endpoint: String. Required. The endpoint address (URI) to which the receipt must be delivered.
 - **interfaceName**: String. Required. A description provided to identify the type of receipt.
- senderName: String. Optional. The sender's name.

The request body for this operation is represented by the following JSON structure, where the value part of each name/value pair indicates its data type:

```
"addresses": ["URI"],
  "ringtone": "String",
  "smsFormat": "Ems | SmartMessaging",
  "charging": {
   "description": "String",
    "amount": "BigDecimal",
    "code": "String",
    "currency": "String"
  },
  "receiptRequest": {
    "correlator": "String",
    "endpoint": "URI",
    "interfaceName": "String"
 },
  "senderName": "String"
}
```

Response Header

http://host:port/rest/sms/delivery_status/result

where, *result* is the string identifier returned in the request body.

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The body of the response contains the **result** object whose value is the request identifier returned in the Location header field of the response message. The application uses this request identifier (in the Get SMS Delivery Status operation) to retrieve the delivery status for the sent message.

The response body for this operation is represented by the following JSON structure, where the value part of the name/value pair indicates its data type:

{"result": "String"}

Send SMS Logo

The Send SMS Logo operation delivers a logo.

To send an SMS Logo, provide the SIP-formatted URI of the addresses which must receive the message, the logo data and its format in the request body for this operation. If there is to be a charge for the messaging, the request body should contain the required charging object. If the sender requires a delivery receipt, specify the required parameters for the receipt.

If the Send SMS Logo operation is successful, the **Location** header field in the response will contain the request identifier (which is also provided in the response body for this operation).

If the application requested a receipt for delivery of the message, the application must access the **endpoint** address to retrieve the delivery notifications.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/sms/logo

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Send SMS operation accepts the following parameters:

- addresses: Array of string values. Required. The set of addresses of the recipients as an array of SIP-formatted URIs.
- image: String. Required. The logo data, a base64-encoded image in GIF, PNG or JPG format.
- smsFormat: String. Required. The encoding format for the logo entered as one of the following:
 - **Ems**
 - SmartMessaging
- charging: A JSON object. Optional. Use this object to define the cost charging properties for the operation. The entry "charging": null indicates no charge. If a charge is to be applied, provide values for the following in the **charging** object:
 - description: String. Required if the charging object is present in the body of the request. The text to be used for information and billing.
 - **amount**: Number (integer, or decimal). Optional. The amount to be charged.

- **code**: String. Optional. The charging code, from an existing contractual description.
- currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- receiptRequest: A JSON object. Optional. If a delivery receipt is required, provide values for each of the following parameters which define this object:
 - correlator: String. Required. Used to correlate the receipt with the initial message.

If the callback reference **correlator** is defined in the **receiptRequest** object of the Send SMS request message, Services Gatekeeper will invoke the Notify SMS Delivery Receipt operation and discard the delivery status information.

- endpoint: String. Required. The endpoint address (URI) to which the receipt must be delivered.
- **interfaceName**: String. Required. A description provided to identify the type of receipt.
- senderName: String. Optional. The sender's name.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"addresses": ["URI"],
  "image": "base64Binary",
  "smsFormat": "Ems | SmartMessaging",
  "charging": {
   "description": "String",
   "amount": "BigDecimal",
   "code": "String",
   "currency": "String"
 },
  "receiptRequest": {
   "correlator": "String",
    "endpoint": "URI",
    "interfaceName": "String"
 },
  "senderName": "String"
}
```

Response Header

The Location header field contains the URI:

```
http://host:port/rest/sms/delivery_status/result
```

where, *result* is the string identifier returned in the request body.

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains the **result** object whose value is the request identifier returned in the Location header field of the response message. The application uses this request identifier (in the Get SMS Delivery Status operation) to retrieve the delivery status for the sent message.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

{"result": "String"}

Get Received SMS

The Get Received SMS operation polls Services Gatekeeper for the SMS messages that have been received from the network for an application.

The request header for the Get Received SMS operation contains the registration identifier necessary to retrieve the required SMS messages intended for the application. This registration value should have been set up with the off-line provisioning step that enables the application to receive notification of SMS reception.

There is no request body.

If the Get Received SMS operation is successful, the response body will contain the message, the URI of the sender, the SMS service activation number and the date and time when the message was sent.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/sms/receive-messages/\${registrationIdentifier}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- registrationIdentifier is the value previously set up to enable the application to receive notification of SMS reception according to specified criteria.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains an array of structures as the value for **result**. Each element in the array contains values for the following parameters.

- **message**: String. The text of the SMS message.
- **senderAddress**: String. The SIP-formatted URI of the sender.

- smsServiceActivationNumber: String. URI. The number associated with the invoked message service, that is the destination address used to send the message.
- dateTime: String. The start time for the call in ISO 8601 extended format, yyyy-mm-ddThh-mm-ss.

The response body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"result": [{
  "message": "String",
  "senderAddress": "URI",
  "smsServiceActivationNumber": "URI",
  "dateTime": "Calendar"
}]}
```

Get SMS Delivery Status

The Get SMS Delivery Status operation retrieves the delivery status of a message that was previously sent using Send SMS, Send SMS Ringtone or Send SMS Logo operation.

The Get SMS Delivery Status operation is valid only if the **correlator** callback reference was not defined in the receiptRequest object of the initial request to send the short message. In such a scenario, Services Gatekeeper stores the delivery status for a configurable period.

If the callback reference correlator is defined in the receiptRequest object of the initial request to send the short message, Services Gatekeeper will invoke the Notify SMS Delivery Receipt operation and discard the delivery status information.

The request header for Get SMS Delivery Status contains the request identifier from the initial Send operation for the short message.

If Get SMS Delivery Status is successful, the response body will contain the SIP-formatted URIs from the address field in the request body of the Send operation for the short message and corresponding delivery status for each message.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/sms/delivery-status/\${requestIdentifier}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- requestIdentifier is the identifier returned in the result object of the corresponding Send operation.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains an array of structures as the value for **result**. Each element in the array contains values for the following parameters.

address: String. The SIP-formatted URI to which the initial message was sent.

deliveryStatus: Enumeration value. Table 9–1 lists the possible status:

Table 9-1 **Enumeration Values for Delivery Status**

Value	Description
DeliveredToNetwork	Successful delivery to network. For concatenated messages, returned only when all the SMS-parts have been successfully delivered to the network.
DeliveryUncertain	Delivery status unknown; for example, if the message was handed off to another network.
DeliveryImpossible	Unsuccessful delivery; the message could not be delivered before it expired.
MessageWaiting	The message is still queued for delivery. This is a temporary state, pending transition to one of the preceding states.
DeliveredToTerminal	Successful delivery to terminal. For concatenated messages, returned only when all the SMS-parts have been successfully delivered to the terminal.
DeliveryNotificationNotSupported	Unable to provide delivery receipt notification.

The response body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"result": [{
  "address": "URI",
  "deliveryStatus":
```

 $[\]verb|"DeliveredToNetwork|| DeliveryUncertain|| DeliveryImpossible|| MessageWaiting|| DeliveredToNetwork|| DeliveryUncertain|| D$ oTerminal|DeliveryNotificationNotSupported" }]}

Start SMS Notification

The Start SMS Notification operation starts a notification for the application.

To set up an SMS notification, provide the criteria which will trigger notifications and a reference object for the delivery of the notifications. The criteria can be a string which, when matched, could be the notification of an SMS received or of a delivery receipt. The reference object (also a JSON object) contains the correlator for the notification, the **endpoint** address (a specific Bayeux channel name) to which the call direction notifications must be sent and, optionally, the interface name (a string to identify the notification).

If the Start SMS Notification request is successful:

- The response header will contain the URI of the publish/subscribe server.
- A data object associated with the result of the short message operation will be sent to the **endpoint** address specified in the request body. This data object will contain the appropriate notification (that the message was received or a delivery receipt for the call).

When the Start SMS notification request is successful, the application can access the **endpoint** address to retrieve the specific call event notifications.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/sms/notification

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Start SMS Notification operation accepts the following parameters:

- **criteria**: String. Optional. The text to match against in determining whether or not the application should receive the notification:
 - notifySmsReception
 - notifySmsDeliveryReceipt
- **reference.** JSON object. Required. Use this object to provide the following information about the endpoint that is to receive the notification:
 - **correlator**: String. Required. The correlator used to identify the notification.

- endpoint: String. Required. The URI which represents the endpoint address to which the notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where *appInstanceID* is the client application's application instance account ID.
 - For more information on application instances, see the discussion on managing application instances in Services Gatekeeper Portal Developer's Guide.
- interfaceName: String. Required. A descriptive string to identify the type of notification.
- smsServiceActivationNumber: String. Required. The number associated with the invoked message service, that is the destination address used to send the message

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"reference": {
  "correlator": "String",
 "endpoint": "URI",
 "interfaceName": "String"
"smsServiceActivationNumber": "URI",
"criteria": "String"
```

Response Header

}

The Location header field contains the URI of the publish/subscribe server:

```
http://host:port/rest/sms/notifications
```

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body. The appropriate notifications (described below) are sent to the **endpoint** address provided by the application in the request body of this operation.

Notification Data Object for SMS Reception (notifySmsReception)

When an SMS message is successfully retrieved by the called party and the value for **criteria** in the request body is **notifySmsReception**, Services Gatekeeper will send a nested JSON data object to the **endpoint** address.

notifySmsReception is a nested JSON object and contains the following values:

- **correlator**: String. Required. The correlator used to identify the notification.
- **message**: Nested JSON object. Required. It contains the following:
 - **message**: String. Required. The contents of the SMS message.
 - senderAddress: String. Required. The SIP-formatted URI of the sender of the SMS message.
 - smsServiceActivationNumber: String. Required. The number associated with the invoked message service, that is the destination address used to send the message.

dateTime: String. Optional. The time at which the message was sent in ISO 8601 extended format, yyyy-mm-ddThh-mm-ss.

The notification data object delivered to the **endpoint** address when the criteria is notifySmsReception is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"notifySmsReception": {
  "correlator": "String",
  "message": {
   "message": "String",
    "senderAddress": "URI",
    "smsServiceActivationNumber": "URI",
    "dateTime": "Calendar"
 }
}}
```

Notification Data Object for SMS Delivery Receipt (notifySmsDeliveryReceipt)

When an SMS message is successfully retrieved by the called party and the value for criteria in the request body is , Services Gatekeeper sends a nested JSON data object to the **endpoint** address.

notifySmsDeliveryReceipt is a nested JSON object and contains the following values:

- **correlator**: String. The correlator used to identify the notification.
- **deliveryStatus**. Enumeration value. Table 9–2 lists the possible status values:

Table 9–2	Enumeration	Values 1	for Deli	very Status
-----------	-------------	----------	----------	-------------

Value	Description
DeliveredToNetwork	Successful delivery to network. For concatenated messages, this is the value only when all the parts of the SMS message have been successfully delivered to the network.
DeliveryUncertain	Delivery status unknown; for example, if the message was handed off to another network.
DeliveryImpossible	Unsuccessful delivery; the message could not be delivered before it expired.
DeliveredToTerminal	Successful delivery to terminal. For concatenated messages, this is the value only when all the parts of the SMS message have been successfully delivered to the terminal.
DeliveryNotificationNotSupported	Unable to provide delivery receipt notification.

The notification data object delivered to the **endpoint** address when the criteria is **notifySmsDeliveryReceipt** is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"notifySmsDeliveryReceipt": {
  "correlator": "String",
  "deliveryStatus": {
    "address": "URI",
    "deliveryStatus":
"DeliveredToNetwork|DeliveryUncertain|DeliveryImpossible|MessageWaiting|
DeliveredToTerminal | DeliveryNotificationNotSupported"
  }
```

}}

Stop SMS Notification

The Stop SMS Notification operation terminates a previously set up SMS notification for the application.

To stop a previously set up SMS notification, provide the correlator for the notification passed earlier in the Start SMS Notification request.

There is no request or response body for the Stop SMS Notification operation. If the request fails, the body of the error response will contain the identifier for the notification and the type of exception.

Authorization

Basic

HTTP Method

DELETE

URI

http://host:port/rest/sms/notification/\${correlator}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- correlator is the correlator for the notification provided in the reference object of the initial Start SMS Notification request body.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Examples

Example 9–1 Stop Message Notification Request

```
DELETE /rest/sms/notification/12345 HTTP/1.1
X-Session-ID: app:4130997928482260925
Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Kevs:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
```

Example 9–2 Stop Message Notification Response

HTTP/1.1 204 No Content

Connection: close

Date: Thu, 04 Nov 2101 09:59:05 GMT

Content-Length: 0 X-Plugin-Param-Keys: X-Plugin-Param-Values:

X-Powered-By: Servlet/2.5 JSP/2.1

Adding RESTful Multimedia Messaging Support

This chapter describes the operations in the Multimedia Messaging interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Multimedia Messaging Interface

Applications use the RESTful Multimedia Messaging interface to send a multimedia message (MMS message) and to fetch information on MMS messages that have been received for the applications and stored on Services Gatekeeper.

Applications use the interface to fetch those messages, get delivery status on sent messages, and start and stop a notification.

The actual message is sent as an attachment. See "Headers for Multipart Messages with Attachments" for more information.

For an application to be informed that a party has received an MMS message or that a message delivery receipt has been sent, the application includes an application **endpoint** address for such delivery notifications in the body of the request message. This address resides on a publish/subscribe server. See "RESTful Notifications and Publish/Subscribe" for more information about publishing and subscribing to RESTful notifications.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/multimedia_messaging/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Send Message

The Send Message operation delivers a multimedia message.

To send a multimedia message, provide the SIP-formatted URI of the addresses which the must receive the message in the request body. If there is to be a charge for the messaging, the request body should contain the required charging object. If the sender requires a delivery receipt, specify the required parameters for the receipt and the SIP formatted URI address of the sender. Also, a priority value, and a subject line can be provided in the request body.

If the Send Message operation is successful, the response header will contain the URI of the publish/subscribe server and the request identifier which is also provided in the response body for this operation.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/multimedia_messaging/messages

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The request headers depend on the type of message:

- If the message content is in the form of an attachment, the request will be multipart and the request header must contain the header fields that describe the parts of the message.
- If the message does not contain an attachment, the special headers associated with the multipart messaged are not used.

See Example 10–1 for a listing of both types of headers.

Message Part Content

The Message Part Content for the Send Message operation accepts the following parameters:

- addresses: Array of string values. Required. The set of addresses of the recipients as an array of URIs.
- **subject**: String. Optional. The text of the message.
- **priority**: String. Optional. The message priority specified as one of the following:
 - Default
 - Low
 - Normal

- High
- senderAddress: String. Optional. The sender's address (URI).
- charging: A JSON object. Optional. This object defines the cost charging properties for the operation. The entry "charging": null indicates no charge. If a charge is to be applied, provide values for the following in the **charging** object:
 - description: String. Required if the charging object is present in the body of the request. The text to be used for information and billing.
 - **amount**: Number (integer, or decimal). Optional. The amount to be charged.
 - **code**: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- receiptRequest: A JSON object. Optional. If a delivery receipt is required, provide values for each of the following parameters which define this object:
 - **correlator**: String. Required. Used to correlate the receipt with the initial message.
 - If the callback reference **correlator** is defined in the **receiptRequest** object of the Send Message request, Services Gatekeeper will invoke Notify Message Delivery Receipt and discard the delivery status information.
 - endpoint: String. The endpoint address (URI) to which the receipt must be delivered: a Bayeux protocol channel name that is the client application's application instance account ID.
 - **interfaceName**: String. Required. A description provided to identify the type of receipt.

The message part Content for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"addresses": ["URI"],
  "charging": {
   "description": "String",
    "amount": "BigDecimal",
    "code": "String",
    "currency": "String"
  },
  "priority": "Default | Low | Normal | High",
  "receiptRequest": {
   "correlator": "String",
    "endpoint": "URI",
    "interfaceName": "String"
  "senderAddress": "String",
  "subject": "String"
}
```

Response Header

The Location header field contains the URI of the publish/subscribe server as:

http://host:port/rest/multimedia_messaging/delivery-status/result

where, result is the string identifier for the request that is returned in the response

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The body of the response contains the request identifier returned in the **Location** header field of the response message as value for **result**.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": "String"}
```

Examples

Example 10-1 Send Message Requests (Single Part Message)

This first example shows a POST method with a message in a single part.

```
POST /rest/multimedia_messaging/messages HTTP/1.1
X-Session-ID: app:-7603991555266551180
Authorization: Basic ZG9tY1uX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host: localhost:8001
Content-Length: 253
Content-Type: application/json
{
  "addresses":["tel:8765","tel:7654","tel:6543"],
  "subject": "Meeting starts at 2 p.m.",
  "priority":null,
  "senderAddress": "tel:1234",
  "charging":null
  "receiptRequest":
         {
           "correlator": "981234",
           "endpoint": "http://endpt_host:port/jaxws/MessageNotification",
           "interfaceName": "interfaceName",
         }
 }
```

Example 10–2 Send Message Requests (Single Part Message)

The second example shows a POST method with a multipart message. Note the use of header fields to describe the content and the boundary attribute to distinguish the message parts.

```
POST /rest/multimedia_messaging/messages HTTP/1.1
X-Session-ID: app: -123456789012346789
Authorization: Basic ZG9tY1uX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host: localhost:8001
```

```
Content-Length: 1215
Content-Type: multipart/form-data; boundary=kboiiFPAakDPYKeY7hBAW9I5c0rT48
--kboiiFPAakDPYKeY7hBAW9I5c0rT48
Content-Disposition: form-data; name="messagePart"
Content-Type: application/json; charset=US-ASCII
Content-Transfer-Encoding: 8bit
  "addresses":["tel:8765","tel:7654","tel:6543"],
  "subject": "Hello World",
  "priority":null,
  "senderAddress": "tel:1234",
  "charging":null,
  "receiptRequest":
           "correlator": "981234",
           "endpoint": "http://endpt_host:port/jaxws/MessageNotification",
           "interfaceName": "interfaceName"
         }
}
--kboiiFPAakDPYKeY7hBAW9I5c0rT48
Content-Disposition: form-data; name="Attachment-txt-1"
Content-Type: text/plain; charset=US-ASCII
Content-Transfer-Encoding: 8bit
Oracle Communications Services Gatekeeper is a powerful, flexible, secure
interface which provides a simple way for application developers to include
telephony-based functionality in their software applications and guarantee the
security, stability, and performance required by network operators and demanded by
their subscribers.
--kboiiFPAakDPYKeY7hBAW9I5c0rT48
```

Get Received Messages

The Get Received Messages operation retrieves an array of network-triggered messages that have arrived at Services Gatekeeper.

The request body for Get Received Messages contains the registration identifier necessary to retrieve the required multimedia messages intended for the application and, optionally, it may also contain a priority for the retrieval. The registration identifier should have been set up with the off-line provisioning step completed earlier.

If the Get Received Messages operation is successful, the response body will contain the data about the message. If the content of the message is pure ASCII, the response body contains the message. Otherwise the response body contains an identifier that is used to fetch the actual message.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/multimedia_messaging/receive-messages

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Get Received Messages operation accepts the following parameters:

registrationIdentifier: String. Required. The value previously set up to enable the application to receive notification of multimedia message reception according to specified criteria.

See "Configuring Offline Notifications for MMS Messages" for more information on provisioning offline notifications.

- **priority**: String. Optional. The message priority specified as one of the following:
 - **Default**
 - Low
 - Normal
 - High

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

{

```
"registrationIdentifier": "String",
"priority": "Default | Low | Normal | High "
```

Response header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains an array of structures as the value for result. Each element in the array contains values for the following parameters.

- messageServiceActivationNumber: String. The number associated with the invoked message service, that is the destination address used to send the message.
- **priority**: String. The message priority value from the request.
- senderAddress: String. The SIP-formatted URI of the sender.
- dateTime: String. The start time for the call in ISO 8601 extended format, yyyy-mm-ddThh-mm-ss.
- message: String. Present if the text of the message is purely ASCII text.
- messageIdentifier: String. An identifier used to fetch the message, when it is not pure ASCII text. This value is used in the URI of the request for the "Get Message" operation.
- subject: String. The subject line of the multimedia message.

The response body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"result": [{
  "messageServiceActivationNumber": "String",
  "priority": "Default | Low | Normal | High",
  "senderAddress": "URI",
  "dateTime": "Calendar",
  "message": "String",
  "messageIdentifier": "String",
  "subject": "String"
}]}
```

Get Message

The Get Message operation fetches a network-triggered message for the application from Services Gatekeeper.

To get a message, provide the appropriate message identifier in the URI for the GET method.

The actual message is returned as an attachment.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/multimedia_messaging/message/\${messageRefIdentifier}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *messageRefIdentifier* is the value for *messageIdentifier* in:
 - The response body of the "Get Received Messages" operation.
 - The notifyMessageReception data object. See "Notification Data Object for Message Reception (notifyMessageReception)".

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

The MIME-type for the Content-Type header field is **multipart/mixed**.

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Get Message Delivery Status

The Get Message Delivery Status operation retrieves the delivery status of a previously sent message.

This operation is valid only if the **correlator** callback reference was not defined in the receiptRequest object of the initial request to send the multimedia message. In such a scenario, Services Gatekeeper stores the delivery status for a configurable period. If the callback reference correlator is defined in the receiptRequest object of the initial multimedia message request, Services Gatekeeper will invoke the Notify Message Delivery Receipt operation and discard the delivery status information.

The request header for the Get Message Delivery Status operation contains the request identifier from **result** object of the initial request.

If the Get Message Delivery Status operation is successful, the response body will contain the SIP-formatted URI from the address field in the Send Message request and corresponding delivery status for the message.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/multimedia_messaging/delivery-status/\${requestIdentifier}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- requestIdentifier is a string returned in the result object of the initial Send Message request.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains an array of structures as the value for result. Each element in the array contains values for the following parameters.

address: String. The SIP-formatted URI to which the initial message was sent.

deliveryStatus. Enumeration value. Table 10–1 lists the possible statuses:

Table 10–1 Enumeration Values for Delivery Status

Value	Description
DeliveredToNetwork	Successful delivery to network. For concatenated messages, returned only when all the MMS parts have been successfully delivered to the network.
DeliveryUncertain	Delivery status unknown; for example, if it was handed off to another network.
DeliveryImpossible	Unsuccessful delivery; the message could not be delivered before it expired.
MessageWaiting	The message is still queued for delivery. This is a temporary state, pending transition to one of the preceding states.
DeliveredToTerminal	Successful delivery to terminal. For concatenated messages, returned only when all the MMS parts have been successfully delivered to the terminal.
DeliveryNotificationNotSupported	Unable to provide delivery receipt notification.

The response body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"result": [{
  "address": "URI",
  "deliveryStatus":
"DeliveredToTerminal | DeliveryUncertain | DeliveryImpossible | MessageWaiting |
{\tt DeliveredToNetwork}\,|\,{\tt DeliveryNotificationNotSupported"}
}]}
```

Start Message Notification

The Start Message Notification operation starts a notification for the application.

To set up a multimedia message notification, provide the criteria which will trigger notifications and a reference object for the delivery of the notifications. The criteria can be a string which, when matched, could be the notification of a multimedia message received or of a delivery receipt. The reference object (also a JSON object) contains the correlator for the notification, the endpoint address (a specific Bayeux channel name) to which the call direction notifications must be sent and, optionally, the interface name (a string to identify the notification).

If the Start Message Notification request is successful:

- The response header will contain the URI of the publish/subscribe server.
- A data object associated with the result of the short message operation will be sent to the endpoint address specified in the request body. This data object will contain the appropriate notification (that the message was received or a delivery receipt for the call).

When the application receives such a response, it must access the endpoint address to retrieve the specific call event notifications.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/multimedia_messaging/notification

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body is a nested JSON object containing the following parameters:

- **reference.** JSON object. Required. Use this object to provide the following information about the endpoint that is to receive the notification:
 - **correlator**: String. Required. The correlator used to identify the notification.
 - endpoint: String. Required. The URI which represents the endpoint address to which the notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where *appInstanceID* is the client application's application instance account ID.

For more information on managing application instances, see Services *Gatekeeper Portal Developer's Guide.*

- interfaceName: String. Required. A descriptive string to identify the type of
- messageServiceActivationNumber: String. Required. The number associated with the invoked message service, that is the destination address used to send the
- criteria: String. Optional. The text to match against in determining whether or not the application should receive the notification:
 - notifyMessageReception
 - notifyMessageDeliveryReceipt

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"messageServiceActivationNumber": "URI",
"reference": {
 "correlator": "String",
 "endpoint": "URI",
 "interfaceName": "String"
},
"criteria": "String"
```

Response Header

The Location header field contains the URI of the publish/subscribe server:

```
http://host:port/rest/multimedia_messaging/notifications
```

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body. The appropriate notifications (described below) are sent to the **endpoint** address provided by the application in the request body of this operation.

Notification Data Object for Message Reception (notifyMessageReception)

When a multimedia message is successfully retrieved by the called party and the value for **criteria** in the request body is **notifyMessageReception**, Services Gatekeeper sends a nested JSON data object to the endpoint address.

This nested JSON object contains the following as the value of the attribute name notifyMessageReception:

- **correlator**: String. The correlator used to identify the notification.
- message. Nested JSON object. It contains the following:
 - message: String. The contents of the multimedia message.
 - **senderAddress**: String. The SIP-formatted URI of the sender of the multimedia message.

- messageServiceActivationNumber: String. The number associated with the invoked Message service, that is the destination address used to send the message.
- dateTime: String. The time at which the message was sent in ISO 8601 extended format, yyyy-mm-ddThh-mm-ss.

The notification data object delivered to the **endpoint** address when the criteria is notifyMessageReception is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"notifyMessageReception": {
  "correlator": "String",
  "message": {
    "messageServiceActivationNumber": "String",
    "priority": "Default | Low | Normal | High",
    "senderAddress": "URI",
    "dateTime": "Calendar",
    "message": "String",
    "messageIdentifier": "String",
    "subject": "String"
  }
}}
```

Notification Data Object for MMS Delivery Receipt (notifyMessageDeliveryReceipt)

When a multimedia message is successfully retrieved by the called party and the value for **criteria** in the request body is **notifyMessageDeliveryReceipt**, Services Gatekeeper sends a nested JSON data object to the **endpoint** address.

This nested JSON object contains the following as the value of the attribute name notifyMessageDeliveryReceipt:

- **correlator**: String. The correlator used to identify the notification.
- **deliveryStatus**: Enumeration value. Table 10–2 lists the possible statuses:

Table 10–2 Enumeration Values for Delivery Status

Value	Description
DeliveredToNetwork	Successful delivery to network. For concatenated messages, returned only when all the MMS parts have been successfully delivered to the network.
DeliveryUncertain	Delivery status unknown; for example, if it was handed off to another network.
DeliveryImpossible	Unsuccessful delivery; the message could not be delivered before it expired.
DeliveredToTerminal	Successful delivery to terminal. For concatenated messages, returned only when all the MMS parts have been successfully delivered to the terminal.
DeliveryNotificationNotSupported	Unable to provide delivery receipt notification.

The notification data object delivered to the **endpoint** address when the criteria is notifyMessageDeliveryRecipt is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"notifyMessageDeliveryReceipt": {
  "correlator": "String",
```

```
"deliveryStatus": {
    "address": "URI",
    "deliveryStatus":
"DeliveredToTerminal | DeliveryUncertain | DeliveryImpossible | MessageWaiting |
{\tt DeliveredToNetwork}\,|\,{\tt DeliveryNotificationNotSupported"}
  }
}}
```

Stop Message Notification

The Stop Message Notification operation terminates a previously set up multimedia message notification for the application.

To stop a previously set up multimedia message notification, provide the correlator for the notification passed earlier in the Start Message Notification request.

There is no request or response body for the Stop Message Notification operation. If the request fails, the body of the error response will contain the identifier for the notification and the type of exception.

Authorization

Basic

HTTP Method

DELETE

URI

http://host:port/rest/multimedia_messaging/notification/correlator

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- correlator is the correlator for the notification provided in the reference object of the initial Start Message Notification operation.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Examples

Example 10–3 Stop Message Notification Request

DELETE /rest/multimedia_messaging/notification/6789 HTTP/1.1 X-Session-ID: app:4130997928482260925 Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI= X-Param-Kevs: X-Param-Values: User-Agent: Jakarta Commons-HttpClient/3.0 Host:servgtkpr_host.port

Example 10–4 Stop Message Notification Response

HTTP/1.1 204 No Content Connection: close

Date: Thu, 04 Nov 2101 09:59:05 GMT

Content-Length: 0 X-Plugin-Param-Keys: X-Plugin-Param-Values:

X-Powered-By: Servlet/2.5 JSP/2.1

Adding RESTful Email Communication Service Support

This chapter describes the operations in the Email Communication interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Email Communication Interface

Applications use the RESTful Email Communication interface to send an email message and to fetch information on email messages that have been received for the applications and stored on Services Gatekeeper.

Applications use the interface to fetch those messages, get delivery status on sent messages, and start and stop a notification.

The actual message is sent as an attachment. See "Headers for Multipart Messages with Attachments" for more information.

For an application to be informed that a party has received an MMS message or that a message delivery receipt has been sent, the application includes an application **endpoint** address for such delivery notifications in the body of the request message. This address resides on a publish/subscribe server. See "RESTful Notifications and Publish/Subscribe" for information on publishing and subscribing to RESTful notifications.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/multimedia_messaging/index.html

where *host* and *port* are the host name and port of the Services Gatekeeper access tier server.

Send Message

The Send Message operation delivers an email message.

To send an email message, provide the SIP-formatted URI of the addresses which the must receive the message in the request body. If there is to be a charge for the messaging, the request body should contain the required charging object. If the sender requires a delivery receipt, specify the required parameters for the receipt and the SIP formatted URI address of the sender. Also, a priority value, and a subject line can be provided in the request body.

The Plug-In Manager uses the email: prefix in the sender address and destination address to route the email message to the email plug-in instance.

If the Send Message operation is successful, the response header will contain the URI of the publish/subscribe server and the request identifier which is also provided in the response body for this operation.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/multimedia_messaging/messages

where *host* and *port* are the host name and port number of the Services Gatekeeper access tier.

Request Header

The request headers depend on the type of message:

- If the message content is in the form of an attachment, the request will be multipart and the request header must contain the header fields that describe the parts of the message.
- If the message does not contain an attachment, the special headers associated with the multipart messaged are not used.
- The X-Parameter ContentInFirstAttachment is added to indicate whether or not there is an email body. If this X-Parameter is set to **true** or is absent, then the first attachment contains the email body and remaining attachments are handled as regular attachments. If this X-Parameter is set to false, then all attachments are handled as regular attachments and the email body is empty.

See Example 11–1 for a listing of both types of headers.

Message Part Content

The message part content for the Send Message operation accepts the following parameters:

- addresses: Array of string values. Required. Use the email: prefix in the sender address and destination address to indicate to the Plug-in Manager that it is an email message intended for the email plug-in.
- **subject**: String. Optional. The text of the message.
- **priority**: String. Optional. The message priority specified as one of the following:
 - **Default**
 - Low
 - Normal
 - High
- senderAddress: String. Use the email: prefix.
- receiptRequest: A ISON object. Provide values for each of the following parameters which define this object:
 - **correlator**: String. Required. Used to correlate the receipt with the initial message.

If the callback reference **correlator** is defined in the **receiptRequest** object of the Send Message request, Services Gatekeeper will invoke notifyMessage Delivery Receipt and discard the delivery status information.

- endpoint: String. The endpoint address (URI) to which the receipt must be delivered. The address is a Bayeux protocol channel name that is the client application's application instance account ID.
- **interfaceName**: String. Required. A description provided to identify the type of receipt.

The message part content for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"addresses": ["URI"],
  "priority": "Default | Low | Normal | High",
  "receiptRequest": {
   "correlator": "String",
    "endpoint": "URI",
    "interfaceName": "String"
  },
  "senderAddress": "String",
  "subject": "String"
}
```

See Example 11–1 for a listing of the message part.

Response Header

The Location header field contains the URI of the publish/subscribe server as:

```
http://host:port/rest/multimedia_messaging/delivery-status/result
```

where, result is the string identifier for the request that is returned in the response body.

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The body of the response contains the request identifier returned in the **Location** header field of the response message as value for **result**.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": "String"}
```

Examples

Example 11–1 Send Message Operation (Single Part MMS)

This example shows a POST method with a message.

```
POST /rest/multimedia_messaging/messages HTTP/1.1
X-Session-ID: app:-7603991555266551180
Authorization: Basic ZG9tY1uX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys: ContentInFirstAttachment
X-Param-Values: false
User-Agent: Jakarta Commons-HttpClient/3.0
Host: localhost:8001
Content-Length: 253
Content-Type: application/json
"addresses":["email:sam@example.com","email:john@example.com","email:tom@example.c
  "subject": "Meeting starts at 2 p.m.",
  "priority":null,
  "senderAddress": "email:bob@example.com",
  "charging":null
  "receiptRequest":
           "correlator": "981234",
           "endpoint": "http://endpt_host:port/jaxws/MessageNotification",
           "interfaceName": "interfaceName",
 }
```

Example 11–2 Send Message Operation (Multipart MMS)

This example shows a POST method with a multipart message. Note the use of header fields to describe the content and the boundary attribute to distinguish the message parts.

```
POST /rest/multimedia_messaging/messages HTTP/1.1
X-Session-ID: app: -123456789012346789
Authorization: Basic ZG9tY1uX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys: ContentInFirstAttachment
X-Param-Values: true
User-Agent: Jakarta Commons-HttpClient/3.0
Host: localhost:8001
Content-Length: 1215
{\tt Content-Type: multipart/form-data; boundary=kboiiFPAakDPYKeY7hBAW9I5c0rT48}
--kboiiFPAakDPYKeY7hBAW9I5c0rT48
```

```
Content-Disposition: form-data; name="messagePart"
Content-Type: application/json; charset=US-ASCII
Content-Transfer-Encoding: 8bit
"addresses":["email:sam@example.com","email:john@example.com","email:tom@example.c
  "subject": "Hello World",
  "priority":null,
  "senderAddress": "email:bob@example.com",
  "charging":null,
  "receiptRequest":
         {
           "correlator": "981234",
           "endpoint": "http://endpt_host:port/jaxws/MessageNotification",
           "interfaceName": "interfaceName"
}
--kboiiFPAakDPYKeY7hBAW9I5c0rT48
Content-Disposition: form-data; name="Attachment-txt-1"
Content-Type: text/plain; charset=US-ASCII
Content-Transfer-Encoding: 8bit
Oracle Communications Services Gatekeeper is a powerful, flexible, secure
interface which provides a simple way for application developers to include
telephony-based functionality in their software applications and guarantee the
security, stability, and performance required by network operators and demanded by
their subscribers.
--kboiiFPAakDPYKeY7hBAW9I5c0rT48
```

Get Received Messages

The Get Received Messages operation retrieves an array of network-triggered messages that have arrived at Services Gatekeeper.

The request body for Get Received Messages contains the registration identifier necessary to retrieve the required email messages intended for the application and, optionally, it may also contain a priority for the retrieval. The registration identifier should have been set up with the off-line provisioning step completed earlier.

If Get Received Messages is successful, the response body will contain the data about the message. If the content of the message is pure ASCII, the response body contains the message. Otherwise the response body contains an identifier that is used to fetch the actual message.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/multimedia_messaging/receive-messages

where host and port are the host name and port number of the Services Gatekeeper access tier.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Get Received Messages operation accepts the following parameters:

- registrationIdentifier: String. Required. The value previously set up to enable the application to receive notification of email reception according to specified criteria.
- **priority**: String. Optional. The message priority specified as one of the following:
 - Default
 - Low
 - Normal
 - High

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"registrationIdentifier": "String",
"priority": "Default | Low | Normal | High"
```

Response header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains an array of structures as the value for result. Each element in the array contains values for the following parameters.

- messageServiceActivationNumber: String. The number associated with the invoked message service, that is the destination address used to send the message.
- **priority**: String. The message priority value from the request.
- senderAddress: String.
- dateTime: String. The start time for the call in ISO 8601 extended format, yyyy-mm-ddThh-mm-ss.
- message: String. Present if the text of the message is purely ASCII text.
- messageIdentifier: String. An identifier used to fetch the message, when it is not pure ASCII text. This value is used in the URI of the request for the "Get Message" operation.
- subject: String. The subject line of the email message.

The response body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"result": [{
  "messageServiceActivationNumber": "String",
  "priority": "Default | Low | Normal | High",
  "senderAddress": "URI",
  "dateTime": "Calendar",
  "message": "String",
  "messageIdentifier": "String",
  "subject": "String"
```

Get Message

The Get Message operation fetches a network-triggered message for the application from Services Gatekeeper.

To get a message, provide the appropriate message identifier in the URI for the GET method.

The actual message is returned as an attachment.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/multimedia_messaging/message/\${messageRefIdentifier}

where:

- host and port are the host name and port number of the Services Gatekeeper access tier.
- *messageRefIdentifier* is the value for *messageIdentifier* in:
 - the response body of the "Get Received Messages" operation
 - notifyMessageReception data object. See "Notification Data Object for Message Reception (notifyMessageReception)"

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

The MIME-type for the Content-Type header field is **multipart/mixed**.

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Get Message Delivery Status

The Get Message Delivery Status operation retrieves the delivery status of a previously sent message.

This operation is valid only if the correlator callback reference was not defined in the receiptRequest object of the initial request to send the email message. In such a scenario, Services Gatekeeper stores the delivery status for a configurable period.

If the callback reference correlator is defined in the **receiptRequest** object of the initial send email request, Services Gatekeeper will invoke the Notify Message Delivery Receipt operation and discard the delivery status information.

The request header for the Get Message Delivery Status operation contains the request identifier from **result** object of the initial request.

If Get Message Delivery Status operation is successful, the response body will contain the SIP-formatted URI from the address field in the Send Message request and corresponding delivery status for the message.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/emailmultimedia_messaging/delivery_ status/\${requestIdentifier}

where:

- host and port are the host name and port number of the Services Gatekeeper access
- requestIdentifier is a string returned in the result object of the initial Send Message request.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains an array of structures as the value for result. Each element in the array contains values for the following parameters.

- address: String. The SIP-formatted URI to which the initial message was sent.
- **deliveryStatus**: Enumeration value. Table 11–1 lists the possible status:

Table 11–1 Enumeration Values for Delivery Status

Value	Description
DeliveredToNetwork	Successful delivery to network. For concatenated messages, returned only when all the email-parts have been successfully delivered to the network.
DeliveryUncertain	Delivery status unknown; for example, if it was handed off to another network.
DeliveryImpossible	Unsuccessful delivery; the message could not be delivered before it expired.
MessageWaiting	The message is still queued for delivery. This is a temporary state, pending transition to one of the preceding states.
DeliveryNotificationNotSupported	Unable to provide delivery receipt notification.

The response body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"result": [{
  "address": "URI",
  "deliveryStatus":
"DeliveredToTerminal|DeliveryUncertain|DeliveryImpossible|MessageWaiting|Delivered
ToNetwork"
}]}
```

Start Message Notification

The Start Message Notification operation starts a notification for the application.

To set up an email message notification, provide the criteria which will trigger notifications and a reference object for the delivery of the notifications. The criteria can be a string which, when matched, could be the notification of an email received or of a delivery receipt. The reference object (also a JSON object) contains the correlator for the notification, the endpoint address (a specific Bayeux channel name) to which the call direction notifications must be sent and, optionally, the interface name (a string to identify the notification).

If the Start Message Notification request is successful:

- The response header will contain the URI of the publish/subscribe server.
- A data object associated with the result of the short message operation will be sent to the endpoint address specified in the request body. This data object will contain the appropriate notification (that the message was received or a delivery receipt for the call).

When the application receives such a response, it must access the endpoint address to retrieve the specific call event notifications.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/multimedia_messaging/notification

where *host* and *port* are the host name and port number of the Services Gatekeeper access tier.

Request Header

The request header depends on the type of message:

- The MIME-type for the Content-Type header field is **application/json**.
- The X-Parameter **Password** to indicate the credential of the email service activation number. The value should be encrypted by AES (Advanced Encryption Standard) or 3DES (Triple Data Encryption Standard) algorithm.
- The X-Parameter **SizeLimit** to indicate the maximum total size (in kilobyte) of an email message attachment accepted by Services Gatekeeper.

Request Body

The request body is a nested JSON object containing the following parameters:

- **reference.** JSON object. Required. Use this object to provide the following information about the endpoint that is to receive the notification:
 - **correlator**: String. Required. The correlator used to identify the notification.

endpoint: String. Required. The URI which represents the endpoint address to which the notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where *appInstanceID* is the client application's application instance account ID.

For more information on application instances, see Services Gatekeeper Portal Developer's Guide.

- interfaceName: String. Required. A descriptive string to identify the type of notification.
- messageServiceActivationNumber: String. Required. The number associated with the invoked message service, that is the destination address used to send the
- **sizeLimit**: Integer. The maximum size for the email allowed in Services Gatekeeper.

The request body for this operation is represented by the following ISON data structure, where the value part of each name/value pair indicates its data type:

```
"messageServiceActivationNumber": "URI",
 "reference": {
   "correlator": "String",
   "endpoint": "URI",
   "interfaceName": "String"
 },
 "sizeLimit": "Integer"
}
```

Response Header

The Location header field contains the URI of the publish/subscribe server:

```
http://host:port/rest/multimedia_messaging/notifications
```

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body. The appropriate notifications (described below) are sent to the **endpoint** address provided by the application in the request body of this operation.

Notification Data Object for Message Reception (notifyMessageReception)

When an email message is successfully retrieved by the called party and the value for **criteria** in the request body is **notifyMessageReception**, Services Gatekeeper sends a nested JSON data object to the **endpoint** address.

This nested JSON object contains the following as the value of the attribute name notifyMessageReception:

- **correlator**: String. The correlator used to identify the notification.
- message. Nested JSON object. It contains the following:
 - **message**: String. The contents of the email message.
 - senderAddress: String.

- messageServiceActivationNumber: String. The number associated with the invoked Message service, that is the destination address used to send the message.
- dateTime: String. The time at which the message was sent in ISO 8601 extended format, yyyy-mm-ddThh-mm-ss.

The notification data object delivered to the **endpoint** address when the criteria is notifyMessageReception is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"notifyMessageReception": {
  "correlator": "String",
  "message": {
    "messageServiceActivationNumber": "String",
    "priority": "Default | Low | Normal | High",
    "senderAddress": "URI",
    "dateTime": "Calendar",
    "message": "String",
    "messageIdentifier": "String",
    "subject": "String"
  }
}}
```

Notification Data Object for Email Delivery Receipt (notifyMessageDeliveryReceipt)

When an email message is successfully retrieved by the called party and the value for **criteria** in the request body is **notifyMessageDeliveryReceipt**, Services Gatekeeper sends a nested JSON data object to the endpoint address.

This nested JSON object contains the following as the value of the attribute name notifyMessageDeliveryReceipt:

- **correlator**: String. The correlator used to identify the notification.
- **deliveryStatus**. Enumeration value. Table 11–2 lists the possible statuses:

Table 11–2 Enumeration Values for Delivery Status

•	
Value	Description
DeliveredToNetwork	Successful delivery to network. For concatenated messages, returned only when all the email-parts have been successfully delivered to the network.
DeliveryUncertain	Delivery status unknown; for example, if it was handed off to another network.
DeliveryImpossible	Unsuccessful delivery; the message could not be delivered before it expired.
DeliveredToTerminal	Successful delivery to terminal. For concatenated messages, returned only when all the email-parts have been successfully delivered to the terminal.
DeliveryNotificationNotSupported	Unable to provide delivery receipt notification.

The notification data object delivered to the **endpoint** address when the criteria is notifyMessageDeliveryReceipt is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"notifyMessageDeliveryReceipt": {
 "correlator": "String",
```

```
"deliveryStatus": {
    "address": "URI",
    "deliveryStatus":
"DeliveredToTerminal | DeliveryUncertain | DeliveryImpossible | MessageWaiting |
DeliveredToNetwork"
  }
}}
```

Stop Message Notification

The Stop Message Notification operation terminates a previously set up email message notification for the application.

To stop a previously set up email notification, provide the correlator for the notification passed earlier in the Start Message Notification request.

There is no request or response body for the Stop Message Notification operation. If the request fails, the body of the error response will contain the identifier for the notification and the type of exception.

Authorization

Basic

HTTP Method

DELETE

URI

http://host:port/rest/multimedia_messaging/notification/correlator

where:

- where *host* and *port* are the host and port number of the Services Gatekeeper access tier.
- correlator is the correlator for the notification provided in the reference object of the initial Start Message Notification operation.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Examples

Example 11–3 Stop Message Notification Request

DELETE /rest/multimedia_messaging/notification/6789 HTTP/1.1 X-Session-ID: app:4130997928482260925 Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI= User-Agent: Jakarta Commons-HttpClient/3.0 Host:servgtkpr_host.port

Example 11–4 Stop Message Notification Response

HTTP/1.1 204 No Content Connection: close

Date: Thu, 04 Nov 2101 09:59:05 GMT

Content-Length: 0 X-Plugin-Param-Keys: X-Plugin-Param-Values:

X-Powered-By: Servlet/2.5 JSP/2.1

Adding RESTful Terminal Status Support

This chapter describes the operations in the Terminal Status interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Terminal Status Interface

Applications use the RESTful Terminal Status interface to get the status of an individual terminal or a group of terminals, or to receive notifications of changes in the status of a terminal.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/terminal_status/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Get Status

The Get Status operation retrieves the status of a single terminal.

To retrieve the status of a specific terminal, provide its URI as the address value of the query object in the Request-URI of the GET method. The interface returns an error if the query object contains more than one address.

If the Get Status operation is successful, the response body contains a JSON data object indicating whether the specific terminal is reachable, unreachable or busy.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/terminal_status/status?query=\${query}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\$(query)* contains the URI address for the terminal as the string value for URI in the data object:

```
{"address":"tel:123"}
```

For example, the operation to get the status for a terminal identified as "tel:123" is:

GET /rest/terminal_status/status?query="%7B%22address%22%3A%22tel%3A123%22%7D" HTTP/1.1

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The status of the specific terminal is returned in the body of the response as the value of the **result** attribute:

Reachable

- unReachable
- **Busy**

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": "String"}
```

Examples

Example 12-1 Get Status Request

```
GET /rest/terminal_status/status?query="%7B%22address%22%3A522tel%3A123%22%7D"
HTTP/1.1
X-Session-ID: app:4130997928482260925
Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
```

Example 12–2 Get Status Response

```
HTTP/1.1 200 OK
Date: Thu, 04 Nov 2101 08:12:43 GMT
Content-Length: 22
Content-Type: application/json
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
{"result": "Reachable"}
```

Get Status For Group

The Get Status for Group operation retrieves the status for a group of terminals.

To retrieve the status of a specific terminals, provide their URIs as the address values of the query object in the Request-URI of the GET method.

If the Get Status for Group operation is successful, the response body contains a JSON data object indicating the status for each terminal (whether the specific terminal is reachable, unreachable or busy).

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/terminal_status/status?queryForGroup=\${query}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\$(query)* contains the URIs for the terminals as an array of string values in the data object:

```
{"addresses":["URI"]}
```

For example,

```
GET /rest/terminal_
status/status?queryForGroup="%7B%22address%22%3A%5B%22tel%3A123%22%2C%22tel%3A456
22tel%3A789%22%5D%7D" HTTP/1.1
```

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains an array of structures as the value for **result**. Each element in the array contains the status for one of the terminals whose address was specified in the Request-URI for **status?queryForGroup**. The following parameters make up the individual terminal's status:

- **address**: String. The URI of a terminal whose status is required.
- **reportStatus**: String. The status of the terminal. It can be one of the following:
 - **Retrieved**. The terminal's status is available. It is provided in this object as the current status of the terminal.
 - **Not Retrieved**. The terminal's status is not available.
 - **Error**: There was an error in the attempt to get the status for this terminal. The error data is provided in this object.
- currentStatus: String. This parameter will be present if the value for reportStatus is **Retrieved**. The current status of the terminal as one of the following:
 - Reachable
 - Unreachable
 - Busy
- errorInformation. a JSON object. This object will be present if the value for reportStatus is Error. It will contain the following error information about the terminal:
 - **messageID**: String. The error message ID.
 - **text**: String. The text for the error message.
 - variables: Array of string values. An Array of variables to substitute into text.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": [{
  "address": "URI",
  "reportStatus": "Retrieved | NotRetrieved | Error",
  "currentStatus": "Reachable | Unreachable | Busy",
  "errorInformation": {
    "messageId": "String",
    "text": "String",
    "variables": ["String"]
}]}
```

Examples

Example 12–3 Get Status for Group Request

```
GET /rest/terminal_
status/status?queryForGroup="%7B%22address%22%3A%5B%22tel%3A123%22%2C%22tel%3A456
22tel%3A789%22%5D%7D" HTTP/1.1
X-Session-ID: app:4130997928482260925
Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
```

Example 12–4 Get Status for Group Response

```
HTTP/1.1 200 OK
Date: Thu, 04 Nov 2101 08:12:43 GMT
Content-Length: 22
Content-Type: application/json
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
{"result":
       [{"address":"tel:123",
           "errorInformation":null,
           "reportStatus": "Retrieved",
           "currentStatus": "Reachable"
          },
          {"address":"tel:456",
           "errorInformation":null,
           "reportStatus": "Retrieved",
           "currentStatus": "Reachable"
          },
          {"address":"tel:789",
           "errorInformation":null,
           "reportStatus": "Retrieved",
           "currentStatus": "Reachable"
}
```

Status Notification

The Status Notification operation initiates requesting for notifications on the status of a specified terminal according to a specified frequency and for a maximum number of notifications over a specified time duration.

To set up for such notifications, provide the URI of the terminal address for which the application must receive notifications, the criteria to trigger notifications, and a reference object for the delivery of the notifications. The reference object (also a JSON object) contains the **correlator** for the notification, the **endpoint** address to which the notifications must be sent and, optionally, the interface name (a string to identify the notification). You can optionally specify the request frequency, the total number of notifications and the duration for the notification and whether or not the check must start immediately.

If the Status Notification request is successful, the **endpoint** address specified in the request body receives a notification when:

- The current status for the terminal status has been retrieved.
- The maximum number of notifications or the specified duration has been reached.
- An error has been encountered in obtaining the status.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/terminal_status/status-notification

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Status Notification operation is a nested JSON object. It contains an array of addresses for the terminals in whose status the application is interested, and the following parameters:

- **address**: String. Required. The URI of a terminal to monitor.
- **checkImmediate**: String. Required. Boolean value:
 - **True**: The application requires the status notification to start immediately and as often as required, thereafter.
 - **False**: The application requires the status notification to start at the end of the time period.

- **criteria**. A set of strings. Required. The required criteria about the terminal. It can be one or more of the following:
 - Reachable
 - UnReachable
 - Busy
- frequency. JSON object. Required. The frequency for checking the status specified by the following:
 - **metric**: String. Required. The unit of time for the check, specified as Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - units: Integer. Required. The number of times the check must be made within the specified metric.
- **reference**: A JSON object. Required. Use this object to provide the following information about the endpoint that is to receive the notification:
 - **correlator**: String. Required. The correlator used to identify the notification.
 - endpoint: String. Required. The URI which represents the endpoint address to which the notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where *appInstanceID* is the client application's application instance account ID.
 - For more information on managing application instances, see Services *Gatekeeper Portal Developer's Guide.*
 - interfaceName: String. Required. A descriptive string to identify the type of notification.
- **count**. Integer. Required. The maximum number of notifications to be sent to the application. If this number is reached, the **statusEnd** notification is delivered to the endpoint address.
- duration. JSON object. Required. The total duration before for the count specified by the following:
 - metric: String. Required. The unit of time for the notifications, specified as Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - units: Integer. Required. The duration in the specified metric.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{
 "addresses": ["URI"],
 "checkImmediate": "Boolean",
 "criteria": ["Reachable | Unreachable | Busy"],
 "frequency": {
    \verb|"metric": "Millisecond| Second| Minute| Hour| Day| Week| Month| Year",
    "units": "Integer"
 },
 "reference": {
   "correlator": "String",
    "endpoint": "URI",
   "interfaceName": "String"
 },
 "count": "Integer",
 "duration": {
    "metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
```

```
"units": "Integer"
 }
}
```

Response Header

The Location header field contains the URI of the publish/subscribe server:

```
http://host:port/rest/terminal_status/notifications
```

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body. The appropriate notifications (described below) are sent to the **endpoint** address provided by the application in the request body of this operation.

Notification Of Current Terminal Status (statusNotification)

When there is a match for the **criteria** value specified in the request body, Services Gatekeeper sends a nested JSON data object to the **endpoint** address.

This nested ISON object contains the following as the value of the attribute name statusNotification:

- correlator: String. The correlator used to identify the notification and provided in the request body of the Status Notification operation.
- terminalStatus. An array of JSON objects. Each element in the array contains the current status of the terminal (based on the criteria) being monitored and defined by the following:
 - address: String. The URI of the terminal being monitored.
 - currentStatus: String. The current status which can be Reachable, unReachable, or Busy.

The notification data object delivered to the **endpoint** address when the criteria is statusNotification is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"statusNotification": {
  "correlator": "String",
  "terminalStatus": [{
    "address": "URI",
    "currentStatus": "Reachable | Unreachable | Busy"
  }]
}}
```

Notification of Error in Retrieving Terminal Status (statusError)

When there is an error in retrieving the status of a terminal, Services Gatekeeper sends a nested JSON data object to the **endpoint** address.

This nested JSON object contains the following as the value of the attribute name statusError:

- correlator: String. The correlator used to identify the notification and provided in the request body of the Status Notification operation.
- **reason**: JSON object. The explanation of the error specified by the following:
 - **messageID**: String. The error message identifier.
 - **text**: String. The error message description.
 - variables: An array of strings. The text to string variables.
- address: String. The URI of a terminal to monitor.

The notification data object delivered to the **endpoint** address when the criteria is statusError is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"statusError": {
  "correlator": "String",
  "reason": {
    "messageId": "String",
    "text": "String",
    "variables": ["String"]
 },
  "address": "URI"
}}
```

Notification Signalling End to Monitoring Terminal (statusEnd)

When the notification count specified as the value for **count** is reached or when the duration specified for units in the duration object is reached, Services Gatekeeper sends a nested JSON data object to the **endpoint** address.

This nested JSON object contains the following as the value of the attribute name statusEnd:

correlator: String. The correlator used to identify the notification and provided in the request body of the Status Notification operation.

This notification is not delivered in the case of an error, or if the application ended the notification using endNotification.

The notification data object delivered to the **endpoint** address when the criteria is **statusEnd** is represented by the following ISON data structure, where the value part of each name/value pair indicates its data type:

```
{"statusEnd": {
  "correlator": "String"
}}
```

Examples

Example 12–5 Status Notification Request

```
PUT /rest/terminal_status/status-notification HTTP/1.1
X-Session-ID: app:4130997928482260925
Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Kevs:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
```

```
Content-Length: 289
Content-Type: application/json
 "duration":null,
 "criteria":["Reachable", "Busy", "Unreachable"],
 "frequency":
         "metric": "Second",
         "units":"5"
       },
 "checkImmediate": "true",
 "addresses":["tel:123","tel:456","tel:789"],
 "reference":
       {"interfaceName":"interfaceName",
         "correlator":"6789",
        "endpoint": "/bayeux/domain-user/ts"
      }
}
```

Example 12-6 Status Notification Response

```
HTTP/1.1 200 OK
Date: Thu, 04 Nov 2101 09:59:05 GMT
Content-Length: 0
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
TerminalStatus: http://terminalloc_host:port/rest/terminal_status/notifications
X-Powered-By: Servlet/2.5 JSP/2.1
```

End Notification

The End Notification operation terminates an application's previously set up notification to get the status of a specified terminal.

To stop a previously set up Status Notification, provide the correlator for the notification passed earlier in the Status Notification request.

There is no request or response body for the End Notification operation. If the request fails, the body of the error response will contain the identifier for the notification and the type of exception.

Authorization

Basic

HTTP Method

DELETE

URI

http://host:port/rest/terminal_status/notification/\${correlator}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- correlator is the correlator for the notification provided in the reference object of the initial Status Notification operation request.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Examples

Example 12–7 End Notification Request

```
DELETE /rest/terminal_status/status-notification/6789 HTTP/1.1
X-Session-ID: app:4130997928482260925
Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Kevs:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
```

Example 12–8 End Notification Response

HTTP/1.1 204 No Content

Connection: close

Date: Thu, 04 Nov 2101 09:59:05 GMT

Content-Length: 0 X-Plugin-Param-Keys: X-Plugin-Param-Values:

X-Powered-By: Servlet/2.5 JSP/2.1

Adding RESTful Terminal Location Support

This chapter describes the operations in the Terminal Location interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Terminal Location Interface

Applications use the RESTful Terminal Location interface to get a location for an individual terminal or a group of terminals; to get the distance of the terminal from a specific location; and to start and stop notifications, based on geographic location or on a periodic interval.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/terminal_location/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Get Location

The Get Location operation retrieves the location of a single terminal. The interface will return an error if the query object contains more than one address.

To retrieve the location of a specific terminal, provide its URI as the address value of the query object in the Request-URI of the GET method.

If the Get Location operation is successful, the response body contains a nested JSON data object containing the physical coordinates of each terminal and the date and time for when such data was last collected.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/terminal_location/location?\${query}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\${query}* is a nested JSON data object.

The parameters accepted by *query* are:

- acceptableAccuracy: Integer. Required. The range that the application considers useful. If the location cannot be determined within this range, the application would prefer not to receive this information.
- address: String. Required. The address of the terminal whose location is required, as a URI.
- **requestedAccuracy:** Integer. Required. The range over which the application wants to receive location information. This may influence the choice of location technology to use (for instance, cell sector location may be suitable for requests specifying 1000 meters, but GPS technology may be required for requests below 100 meters).
- tolerance: String. Required. Enumerated value denoting the priority of response time versus accuracy. Table 13–1 lists the possible values:

Table 13–1 Enumeration Values for Tolerance Attribute

Value	Description
NoDelay	The server should immediately return any location estimate that it currently has. If no estimate is available, the server returns a failure indication. The server may optionally initiate procedures to obtain a location estimate (for example, to be available for a later request).

Table 13–1 (Cont.) Enumeration Values for Tolerar

Value	Description
LowDelay	The response time is more important than the requested accuracy. The server attempts to fulfil any accuracy requirement, but not if it adds delay. A quick response with lower accuracy is more desirable than waiting for a more accurate response.
DelayTolerant	The network is expected to return a location with the requested accuracy even if this means not complying with the requested response time.

- maximumAge: JSON object. Optional. The maximum acceptable age of the location information. This object is defined by the following:
 - metric: String. The unit of time. Required if the maximumAge object is present in the body of the query. Possible entries are Millisecond, Second, Minute, Hour, Day, Week, Month or Year.
 - units: Integer. Required if the maximumAge object is present in the body of the query. The number of units for the metric.
- responseTime: JSON object. Optional. The maximum response time that the application will accept. This object is defined by the following:
 - metric: String. The unit of time. Required if the responseTime object is present in the body of the query. Possible entries are Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - units: Integer. Required if the maximumAge object is present in the body of the query. The number of units for the metric.

The maximum duration and interval is 8916039 seconds, which converts to 99 days, 99 hours, 99 minutes, and 99 seconds. Do not enter a value that exceeds the 8916039 second interval. In other words, do not use the Year time metric, and only about three Months is allowed.

The *\${query}* object in the URI is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"acceptableAccuracy": "Integer",
  "address": "URI",
  "requestedAccuracy": "Integer",
  "tolerance": "NoDelay | LowDelay | DelayTolerant",
  "maximumAge": {
    "metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
    "units": "Integer"
  },
  "responseTime": {
    "metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
    "units": "Integer"
  }
}
```

Example 13-1 Request URI for Get Location

```
GET /rest/terminal_
location/location?query=%7B%22aceptableAccuracy%22%3A%22100%%22%2C%22address%22%3
A%22tel%3A1234%22%2C%22requestAccuracy%22%3A%22100%%22%2C
%22tolerance%22%3A%22NoDelay%22%2C%22maximumAge%22%3Anull%2C%22responseTime%22%3
```

```
Anull%7D HTTP/1.1
```

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The location of the specific terminal is returned in the body of the response as the value of the **result** JSON object. The parameters in this object are:

- accuracy: Integer.
- latitude: Number (floating point).
- longitude: Number (floating point).
- timestamp: String. The date and time when the terminal's geographical coordinates were collected, given in ISO 8601 extended format, yyyy-mm-ddThh-mm-ss.
- altitude: Number (floating point).

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": {
  "accuracy": "Integer",
  "latitude": "Float",
  "longitude": "Float",
  "timestamp": "Calendar",
  "altitude": "Float"
}}
```

Example 13-2 Response Body for Get Location

```
"result":
       {
        "accuracy": "10",
        "latitude": "37.78843",
        "longitude": "-122.4374",
        "timestamp": "2010-11-05T21:56:21+08:00"
}
```

Examples

Example 13-3 Get Location Request

```
GET /rest/terminal_
```

location/location?query=%7B%22aceptableAccuracy%22%3A%22100%%22%2C%22address%22%3 A%22tel%3A1234%22%2C%22requestAccuracy%22%3A%22100%%22%2C %22tolerance%22%3A%22NoDelay%22%2C%22maximumAge%22%3Anull%2C%22responseTime%22%3 Anull%7D HTTP/1.1 X-Session-ID: app:5198750923966743997 Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI= X-Param-Keys: X-Param-Values: User-Agent: Jakarta Commons-HttpClient/3.0 Host:servgtkpr_host.port

Example 13-4 Get Location Response

```
HTTP/1.1 200 OK
Date: Thu, 05 Nov 2101 05:52:41 GMT
Content-Length: 131
Content-Type: application/json
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
   "result":
      {
       "accuracy":"10",
        "latitude":"37.78843",
        "longitude": "-122.4374",
        "timestamp":"2010-11-05T21:56:21+08:00"
        }
}
```

Get Location for Group

The Get Location for Group operation retrieves the location information for a group of terminals.

To retrieve the location information of a specific terminals, provide their URIs as the address values of the query object in the Request-URI of the GET method.

If the Get Location for Group operation is successful, the response body contains a JSON data object indicating the physical location for each terminal (whether or not the specific terminal is reachable, unreachable or busy).

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/terminal_location/location?queryForGroup=\${queryForGroup}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\${queryForGroup}* is a nested JSON data object.

The parameters accepted by *queryForGroup* are:

- acceptableAccuracy: Integer. Required. The range that the application considers useful. If the location cannot be determined within this range, the application would prefer not to receive this information.
- addresses: Array of Strings. Required. The addresses of the terminals whose location is required, as URIs.
- **requestedAccuracy:** Integer. Required. The range over which the application wishes to receive location information. This may influence the choice of location technology to use (for instance, cell sector location may be suitable for requests specifying 1000 meters, but GPS technology may be required for requests below 100 meters).
- tolerance: String. Required. Enumerated value denoting the priority of response time versus accuracy. Table 13–2 lists the possible values:

Value	Description
NoDelay	The server should immediately return any location estimate that it currently has. If no estimate is available, the server return a failure indication. The server may optionally initiate procedures to obtain a location estimate (for example, to be available for a later request).

Table 13–2 (Cont.) Enumeration Values for Tolerance Attrib	es for Tolerance Attribute
------------------------------------------------------------	----------------------------

Value	Description
LowDelay	The response time is more important than the requested accuracy. The server attempts to fulfil any accuracy requirement, but not if it adds delay. A quick response with lower accuracy is more desirable than waiting for a more accurate response.
DelayTolerant	The network is expected to return a location with the requested accuracy even if this means not complying with the requested response time.

- maximumAge: JSON object. Optional. The maximum acceptable age of the location information. This object is defined by the following:
 - metric: String. The unit of time. Required if the maximumAge object is present in the body of the query. Possible entries are Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - units: Integer. Required if the maximumAge object is present in the body of the query. The number of units for the metric.
- responseTime: JSON object. Optional. The maximum response time that the application will accept. This object is defined by the following:
 - metric: String. The unit of time. Required if the responseTime object is present in the body of the query. Possible entries are Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - units: Integer. Required if the maximumAge object is present in the body of the query. The number of units for the metric.

The \${queryForGroup} object in the URI is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"acceptableAccuracy": "Integer",
  "addresses": ["URI"],
  "requestedAccuracy": "Integer",
  "tolerance": "NoDelay | LowDelay | DelayTolerant",
  "maximumAge": {
    "metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
    "units": "Integer"
  },
  "responseTime": {
    "metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
    "units": "Integer"
  }
}
```

Example 13–5 Request URI for Get Location for Group

```
GET /rest/terminal_
```

location/location?queryForGroup=%7B%22aceptableAccuracy%22%3A%22100%%22%2C%22 addresses%22%3A%%5B22tel%3A1234%22%2C%22tel%3A123%22%5D%2C%22requestAccuracy%22 %3A%22100%%22%2C%22tolerance%22%3A%22NoDelay%22%2C%22maximumAge%22%3Anull%2C%22 responseTime%22%3Anull%7D HTTP/1.1

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body is the attribute **result** whose value consists of an array of JSON objects. Each element in the array contain the report status, the location information (if any) and the error information (if any) for the terminals whose addresses were specified in the Request-URI for **status?queryForGroup**.

The following parameters make up the information associated with an individual terminal's location:

- address: String. The address of a terminal whose location is required, as a URI.
- **reportStatus**: String. The status of the terminal. It can be one of the following:
 - **Retrieved:** The terminal's location information is available. It is provided in this object as the current location of the terminal.
 - **Not Retrieved**: The terminal's location information is not available.
 - **Error**: There was an error in the attempt to get the location information for this terminal. The error data is provided in this object.
- currentLocation: String. This parameter will be present if the value for **reportStatus** is **Retrieved**. The current location of the terminal as one of the following:
 - accuracy: Integer.
 - **latitude**: Number (floating point).
 - **longitude**: Number (floating point).
 - altitude: Number (floating point).
 - timestamp: String. The date and time when the terminal's geographical coordinates were collected, in ISO 8601 extended format, yyyy-mm-ddThh-mm-ss.
- errorInformation: JSON object. This object will be present if the value for reportStatus is Error. It will contain the following error information about the terminal:
 - messageID: String. The error message ID.
 - **text**: String. The text for the error message.
 - variables: Array of string values. Variables to substitute into text strings.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": [{
```

```
"address": "URI",
  "reportStatus": "Retrieved | NotRetrieved | Error",
  "currentLocation": {
    "accuracy": "Integer",
   "latitude": "Float",
    "longitude": "Float",
    "timestamp": "Calendar",
    "altitude": "Float"
  },
  "errorInformation": {
   "messageId": "String",
    "text": "String",
    "variables": ["String"]
 }
}]}
```

Examples

Example 13–6 Get Location for Group Request

```
GET /rest/terminal_
location/location?queryForGroup=%7B%22aceptableAccuracy%22%3A%22100%%22%2C%22
addresses%22%3A%%5B22tel%3A1234%22%2C*22tel%3A123%22%5D%2C%22requestAccuracy%22
%3A%22100%%22%2C%22tolerance%22%3A%22NoDelay%22%2C%22maximumAge%22%3Anul1%2C%22
responseTime%22%3Anull%7D HTTP/1.1
X-Session-ID: app:4130997928482260925
Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
```

Example 13–7 Get Location for Group Response

```
HTTP/1.1 200 OK
Date: Thu, 04 Nov 2101 08:12:43 GMT
Content-Length: 438
Content-Type: application/json
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
{"result":
       [{"address":"tel:1234",
           "errorInformation":null,
           "reportStatus": "Retrieved",
           "currentLocation":
                     "accuracy": "10",
                     "latitude":"37.78843",
                     "longitude": "-122.4374",
                     "altitude":"0.0"
                     "timestamp": "2010-11-05T22:13:28+08:00"
          {"address":"tel:123",
           "errorInformation":null,
           "reportStatus": "Retrieved",
           "currentLocation":
```

```
{
                     "accuracy":"10",
                     "latitude":"55.2776",
                     "longitude": "7.012778",
                     "altitude":"20.0"
                     "timestamp":"2010-11-05T22:13:28+08:00"
          }
}
```

Get Terminal Distance

The Get Terminal Distance operation retrieves the distance between a specified terminal and a required location. The terminal distance is calculated in meters.

To retrieve the distance, provide the URI for the terminal and the geographic coordinates of the required location in the Request-URI of the GET method.

If the Get Terminal Distance operation is successful, the response body contains a JSON data object indicating the distance between a specified terminal and a required location, in meters.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/terminal_distance/distance?query=\${query}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\${query}* is a nested JSON data object.

The parameters accepted by the *query* attribute are:

- **address**: String. Required. The address of the terminal, as a URI.
- **latitude:** Number (floating point). Required. The latitude of the location.
- longitude: Number (floating point). Required. The longitude of the location

The *\${query}* object in the URI is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"address": "URI",
"latitude": "Float",
"longitude": "Float"
```

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The distance between the specified terminal and the required location is returned as the value for **result** in a data object. The unit for the distance is meters and the value is an integer.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": "String"}
```

Examples

Example 13-8 Get Terminal Distance Request

```
GET /rest/terminal_
distance/distance?query=%7B%22address%22%3A%22tel%3A1234%22%2C%22longitude%22
%3A%2237.7707%%22%2C %22latittude%22%3A%22122.4177%227D HTTP/1.1
X-Session-ID: app:5198750923966743997
Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
```

Example 13-9 Get Terminal Distance Response

```
HTTP/1.1 200 OK
Date: Thu, 05 Nov 2101 05:52:41 GMT
Content-Length: 131
Content-Type: application/json
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
   "result":"9316351"
}
```

Start Geographical Notification

The Start Geographical Notification operation provides notifications based on whether terminals enter or leave a specified geographic area. The area to be monitored is circular with specified latitude and longitude as the center and having a specified radius.

To set up for such notifications, provide the SIP-formatted URI of the terminal addresses for which the application must receive notifications, the criteria which will trigger notifications and a reference object for the delivery of the notifications. Additionally, you can specify the request frequency, the total number of notifications and the duration for the notification and whether or not the check must start immediately or not. The reference object (also a JSON object) contains the correlator for the notification, the endpoint address (a specific Bayeux channel name) to which the notifications must be sent and, optionally, the interface name (a string to identify the notification).

If the request for the Start Geographical Notification operation is successful, the endpoint address specified in the request body will receive a notification when:

- The terminal location has been successfully retrieved.
- The notification limit or the specified duration has been reached.
- An error has been encountered in obtaining the location of the terminal.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/terminal_location/geographical-notification

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Start Geographical Notification operation is a nested JSON object. It accepts an array of addresses for the terminals in whose geographical information the application is interested, and the parameters for the check:

- addresses: Array of string values. Required. Each element in the array is a SIP-formatted address for a terminal, as a URI.
- **checkImmediate**: String. Required. Set to:
 - **True**: The application requires the geographical notification to start immediately and as often as required thereafter.

- **False**: The application requires the geographical notification to start at the end of the time period.
- count: Integer. Optional. The maximum number of notifications sent to the application. If this number is reached while notification operation is active a **locationEnd** notification is delivered to the endpoint address. If you omit this option, or set it to 0 there is no limit to the number of notifications.
- **criteria**: String. Required. The status of the terminal. It can be one of the following:
 - **Entering**: The notification should be made when the terminal enters the area being monitored.
 - **Leaving**: The notification should be made when the terminal leaves the area being monitored.
- duration: JSON object. Optional. Specifies a time limit for notifications. The maximum duration period can be limited by the underlying network. Omit this option, or set it to **0** to specify no time limit.
 - metric: String. Required. The unit of time for the duration specified as Millisecond, Second, Minute, Hour, Day, Week, Month or Year.
 - **units**: Integer. Required. The number of **metric** units that specify the duration. If this number is reached (and the application has not ended the notification operation), the **locationEnd** notification is delivered to the **endpoint** address.
- frequency: JSON object. Required. Specifies the time between notifications. The value must be in the range of 1-8916039 seconds, which converts to 99 days, 99 hours, 99 minutes, and 99 seconds. Do not enter a value that exceeds the 8916039 second interval. In other words, do not use the Year time metric, and only about three **Month**s is allowed.
 - metric: String. Required. The unit of time for the notification frequency. Can be specified in Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - **units**: Integer. Required. The number of **metric** units between notifications.

For example this entry:

metric=second unik=10

specifies a minimum time between notifications of 10 seconds. However this entry:

```
metric=month
unit=6
```

is invalid because it exceeds the 8916039 second (99 day) limit.

- latitude: Number (floating point). Required. The latitude of the location which will be the center of the area under surveillance.
- longitude: Number (floating point). Required. The longitude of the location which will be the center of the area under surveillance.
- radius: Number (floating point) in meters. Required. The radius of the circle around the location (center point), in meters.
- reference: JSON object. Required. Use this object to provide the following information about the endpoint that is to receive the notification:
 - **correlator**: String. Required. The correlator used to identify the notification.

endpoint: String. Required. The URI which represents the endpoint address to which the notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where *appInstanceID* is the client application's application instance account ID.

For more information on managing application instances, see *Services* Gatekeeper Portal Developer's Guide.

- interfaceName: String. Required. A descriptive string to identify the type of notification.
- trackingAccuracy: Number (floating point). Required. The acceptable error in the tracking, in meters.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{
  "addresses": ["URI"],
  "checkImmediate": "Boolean",
  "criteria": "Entering Leaving",
  "frequency": {
   "metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
    "units": "Integer"
  },
  "latitude": "Float",
  "longitude": "Float",
  "radius": "Float",
  "reference": {
    "correlator": "String",
    "endpoint": "URI",
   "interfaceName": "String"
  },
  "trackingAccuracy": "Float",
  "count": "Integer",
  "duration": {
    "metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
    "units": "Integer"
  }
}
```

Response Header

The Location header field contains the URI of the publish/subscribe server:

```
http://host:port/rest/terminal_location/notifications
```

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body. The appropriate notifications (described below) are sent to the **endpoint** address provided by the application in the request body of this operation.

Notification When Terminal Location is Successfully Retrieved (locationNotification)

When there is a match for the **criteria** value (specified in the request body) and the terminal's location is successfully retrieved, Services Gatekeeper sends a nested JSON data object to the **endpoint** address.

This nested JSON object contains the following as the value of the attribute name locationNotification:

- correlator: String. The correlator used to identify the notification and provided in the request body of the Start Geographical Notification operation.
- **criteria**: String. The state of the terminal. It can be one of the following:
 - **Entering**: The terminal entered the area being monitored.
 - Leaving: The terminal left the area being monitored.
- data: Array of JSON objects. Each element in the array contains the current location information of a terminal being monitored and contains the following parameters:
 - address: String. The URI of the terminal being monitored.
 - reportStatus: String. Retrieval status for this terminal which can be Retrieved, **NotRetrieved**, or **Error**. This allows for partial reports to avoid timeouts, and so on.
 - currentLocation: String. This object will be present only if the reportStatus is Retrieved. It contains the location information for the terminal, as of the date and time specified in this object. Table 13–3 lists the attributes in this object:

Attributes in the currentLocation JSON Object Table 13–3

Attribute	Description
accuracy	Number (floating point). The accuracy error in arriving at the terminal's location, in meters.
latitude	Number (floating point). The latitude for the terminal.
longitude	Number (floating point). The longitude for the terminal.
timestamp	String. The date and time when the terminal's geographical coordinates were collected, given in ISO 9601's extended format.
altitude	Number (floating point). The altitude for the terminal.

errorInformation: JSON object. This object will be present if the value for reportStatus is Error. Table 13–4 lists the attributes in this object.

Table 13-4 Attributes in the errorInformation Object

Attribute	Description
messageID	String. Message identifier for the fault
text	String. The text of the message. If this string contains replacement variables, the variables entry hold the
variables	Array of string values. Optional. An array of variables to substitute into text strings.

The location notification data object delivered to the endpoint address is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"locationNotification": {
  "correlator": "String",
  "data": [{
   "address": "URI",
   "reportStatus": "Retrieved NotRetrieved Error",
    "currentLocation": {
      "accuracy": "Integer",
      "latitude": "Float",
      "longitude": "Float",
      "timestamp": "Calendar",
      "altitude": "Float"
    }.
    "errorInformation": {
     "messageId": "String",
      "text": "String",
     "variables": ["String"]
 }].
  "criteria": "Entering Leaving"
} }
```

Example 13–10 locationNotification Object Delivered to the Application

```
"locationNotification":
               "correlator": "6789",
               "data":
                   [ {
                      "address": "tel:123",
                      "reportStatus": "Retrieved",
                      "errorInformation":null,
                      "currentLocation":
                             {
                                "accuracy": "8",
                               "latitude":"37.80",
                               "longitude": "-122.56",
                               "altitude": "90",
                                "timestamp": "2010-11-08T10:29:38"
                   }],
               "criteria": "Entering"
            }
}
```

Notification of Error in Retrieving Terminal Location (locationError)

When there is an error in retrieving the location for the specified terminal, Services Gatekeeper sends a nested JSON data object to the **endpoint** address.

The nested JSON object contains the following as the value of the attribute name locationError:

- correlator: String. The correlator used to identify the notification and provided in the request body of the Status Notification operation.
- **reason**: JSON object. The explanation of the error specified by the following:
 - messageID: String. The error message identifier.

- **text**: String. The error message description.
- variables. An array of string values. The array of variables to substitute into text strings.
- address: String. The URI of a terminal to monitor.

The location error notification data object delivered to the **endpoint** address is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"locationError": {
  "correlator": "String",
  "reason": {
   "messageId": "String",
   "text": "String",
   "variables": ["String"]
 },
  "address": "URI"
}}
```

Notification Signalling End to Monitoring Terminal's Location (locationEnd)

When the notification count specified as the value for **count** is reached or when the duration specified for units in the **duration** object is reached, Services Gatekeeper sends a nested JSON data object to the **endpoint** address.

The JSON object contains the following as the value of the attribute name **locationEnd**:

correlator: String. The correlator used to identify the notification and provided in the request body of the Status Notification operation.

Here is the structure of this notification:

```
{"locationEnd": {"correlator": "String"}}
```

Note: This notification is not delivered in the case of an error, or if the application ended the notification using **endNotification**.

Examples

Example 13-11 Start Geographic Notification Request

```
PUT /rest/terminal_location/geographical-notification HTTP/1.1
X-Session-ID: app:4130997928482260925
Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Kevs:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
Content-Length: 366
Content-Type: application/json
   "addresses":["tel:123"],
   "checkImmediate: "true",
   "criteria": "Entering",
   "frequency":
        {
```

```
"metric": "Second",
         "units": "5"
       },
   "latitude":"37.7707",
   "longitude": "-122.4177",
   "radius": "5000.0",
   "reference":
          "correlator":"6789",
          "endpoint":"bayeux/app_instance_1/tl",
         "interfaceName": "interfaceName"
       },
   "trackingAccuracy":"10.0",
   "count":"5",
   "duration":
         "metric": "Minutes",
         "units":"30"
      }
}
```

Example 13-12 Status Notification Response

```
HTTP/1.1 200 Created
Date: Fri, 05 Nov 2101 09:59:05 GMT
Location: http://terminalloc_host:port/rest/terminal_location/notifications
Content-Length: 0
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
```

Start Periodic Notification

The Start Periodic Notification operation provides notifications for the locations of a set of terminals at a defined interval.

To set up for such location notifications, provide the SIP-formatted URI of the terminal addresses for which the application must receive notifications, the request frequency, the total number of notifications and the duration for the notification and whether or not the check must start immediately. The reference object (also a JSON object) contains the correlator for the notification, the endpoint address (a specific Bayeux channel name) to which the notifications must be sent and, optionally, the interface name (a string to identify the notification).

If the request for the Start Periodic Notification operation is successful, the endpoint address specified in the request body will receive a notification when:

- The terminal location has been successfully retrieved.
- The notification limit or the specified duration has been reached.
- An error has been encountered in obtaining the location of the terminal.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/terminal_location/periodic-notification

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Start Periodic Notification operation is a nested JSON object. It contains an array of addresses for the terminals in whose information the application is interested, and the parameters for the check provided by the following:

- addresses: Array of string values. Required. Each element in the array is a SIP-formatted address for a terminal, as a URI.
- duration: JSON object. Optional. Specifies the total time for receiving notifications The underlying network sometimes limits this count. Omit this setting or set it to 0 to specify no limit.
 - metric: String. Required. The unit of time for the notifications specified as Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - **units**: Integer. Required. The number of **metric** units that specify the duration. If this number is reached while this operation is still active, the **locationEnd** notification is delivered to the **endpoint** address.

- frequency: JSON object. Required. Specifies a minimum time between notifications:
 - **metric**: String. Required. The unit of time for the frequency specified as Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - **units**: Integer. Required. The frequency of the specified **metric**.
 - metric: String. Required. The unit of time for the frequency specified as Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - units: Integer. Required. The frequency of the specified metric.

This value must be in the range of 1-8916039 seconds, which converts to 99 days, 99 hours, 99 minutes, and 99 seconds. Do not enter a value that exceeds the 8916039 second interval. In other words, do not use the Year time metric, and only about three **Month**s is allowed.

- **reference**: JSON object. Required. Use this object to provide the following information about the endpoint that is to receive the notification:
 - **correlator**: String. Required. The correlator identifies the notification.
 - **endpoint**: String. Required. The URI which represents the endpoint address to which the notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where *appInstanceID* is the client application's application instance account ID.

For more information on managing application instances, see Services Gatekeeper Portal Developer's Guide.

- **interfaceName**: String. Required. A descriptive string to identify the type of notification.
- requestedAccuracy: Number (floating point). Required. The acceptable error in the tracking, in meters.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"addresses": ["URI"],
  "frequency": {
    "metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
    "units": "Integer"
  },
  "reference": {
    "correlator": "String",
    "endpoint": "URI",
    "interfaceName": "String"
  },
  "requestedAccuracy": "Integer",
  "duration": {
    "metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
    "units": "Integer"
  }
}
```

Response Header

The Location header field contains the URI of the publish/subscribe server:

```
http://host:port/rest/terminal_location/notifications
```

If the request fails, the Status-Line header field will contain the status code and the reason for the failure.

Response Body

There is no response body. The appropriate notifications (described below) are sent to the **endpoint** address provided by the application in the request body of this operation.

Examples

Example 13-13 Start Periodic Notification Request

```
PUT /rest/terminal_location/periodic-notification HTTP/1.1
X-Session-ID: app:4130997928482260925
Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
Content-Length: 366
Content-Type: application/json
   "addresses":["tel:123"],
   "frequency":
       {
          "metric": "Second",
          "units": "5"
       },
   "reference":
       {
          "correlator": "6789",
          "endpoint":"bayeux/app_instance_1/tl",
          "interfaceName": "interfaceName"
        },
   "requestedAccuracy": "10.0",
   "duration":
       {
          "metric": "Minutes",
          "units":"30"
}
```

Example 13–14 Start Periodic Notification Response

```
HTTP/1.1 200 Created
Date: Fri, 05 Nov 2101 09:59:05 GMT
Location: http://terminalloc_host:port/rest/terminal_location/notifications
Content-Length: 0
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
```

Notification When Terminal Location is Successfully Retrieved (locationNotification)

See "Notification When Terminal Location is Successfully Retrieved (locationNotification)".

Notification of Error in Retrieving Terminal Location (locationError)

See "Notification of Error in Retrieving Terminal Location (locationError)".

Notification Signalling End to Monitoring Terminal (locationEnd)

See "Notification Signalling End to Monitoring Terminal's Location (locationEnd)".

End Notification

The End Notification operation terminates an application's previously set up notification to get the geographical and periodic information for a specified terminal.

To stop a previously set up Start Geographical Notification or Start Periodic Notification, provide the correlator for the notification passed earlier in the appropriate start request.

There is no request or response body for the End Notification operation. If the request fails, the body of the error response will contain the identifier for the notification and the type of exception.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/terminal_location/notification/\${correlator}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- correlator is the correlator for the notification provided in the **reference** object of the initial request for the Start Geographical Notification or Start Periodic Notification operation.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure.

Response Body

There is no response body.

Examples

Example 13-15 End Notification Request

```
DELETE /rest/terminal_location/status-notification/6789 HTTP/1.1
X-Session-ID: app:4130997928482260925
Authorization: Basic ZG9tYWluX3VzZXI6ZG9tYWluX3VzZXI=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
```

Example 13–16 End Notification Response

HTTP/1.1 204 No Content

Connection: close

Date: Thu, 04 Nov 2101 09:59:05 GMT

Content-Length: 0 X-Plugin-Param-Keys: X-Plugin-Param-Values:

X-Powered-By: Servlet/2.5 JSP/2.1

Adding RESTful Payment Support

This chapter describes the operations in the Payment interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Payment Interface

Applications use the RESTful Payment interface to charge an amount to an end-user's account using Diameter, refund amounts to that account, and split charge amounts among multiple end-users. Applications can also reserve amounts, reserve additional amounts, charge against the reservation or release the reservation.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/payment/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Charge Amount

The Charge Amount operation charges an amount directly to an end-user's application using the Diameter protocol.

To charge an amount for a call, provide the SIP-formatted URI of the address of the end-user, a reference code in case there is any dispute regarding the charges, and the billing information to charge for the call.

There is no response body for the Charge Amount operation.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/charge-amount

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Charge Amount operation accepts the following parameters:

- charging: A JSON object. Optional. This object defines the cost-charging properties for the call. A call with no charging parameters can be entered as "charging": null. If a charge is to be applied, provide values for the following in the **charging** object:
 - **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
 - **amount**. Number (integer, or decimal). Optional. The amount to be charged.
 - **code**: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- endUserIdentifier: String. Required. The address of the end-user's application that is to be charged.
- **referenceCode**: String. Required. A unique identifier in case of disputes with respect to the charges.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"charge": {
  "description": "String",
```

```
"amount": "BigDecimal",
   "code": "String",
   "currency": "String"
  "endUserIdentifier": "URI",
  "referenceCode": "String"
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

Refund Amount

The Refund Amount operation refunds an amount directly to an end-user's application using Diameter.

To refund an amount for a call, provide the SIP-formatted URI of the address of the end-use, a reference code in case there is any dispute regarding the charges, and the billing information to charge for the call. receive the message in the request body.

There is no response body for the Refund Amount operation.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/refund-amount

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Refund Amount operation accepts the following parameters:

- charging. a JSON object. Optional. This object defines the cost-charging properties for the call. A call with no charging parameters can be entered as "charging": null. If a charge is to be applied, provide values for the following in the **charging** object:
 - **description**: String. Required if the charging object is present in the body of the request. The text to be used for information and billing.
 - **amount**. Number (integer, or decimal). Optional. The amount to be refunded.
 - **code**: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- endUserIdentifier: String. Required. The address of the end-user's application that is to receive the refund.
- referenceCode: String. Required. A unique identifier in case of disputes with respect to the refund.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"charging": {
  "description": "String",
```

```
"amount": "BigDecimal",
   "code": "String",
   "currency": "String"
  "endUserIdentifier": "URI",
  "referenceCode": "String"
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

Charge Split Amount

The Charge Split Amount operation charges an amount directly to multiple end-users concurrently (for example, for charging multiple participants in a conference.

To split the charge an amount for a call, provide the billing information to charge for the call, a reference code in case there is any dispute regarding the charges, the address of the end-user, and the percentage of the charges for which the end-user is liable.

There is no response body for the Charge Split Amount operation.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/charge-split-amount

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Charge Split Amount operation accepts the following parameters:

- charge. a JSON object. Required. Use this object to define the cost-charging properties for the call. A call with no charging parameters can be entered as "charging": null. If a charge is to be applied, provide values for the following in the **charging** object:
 - **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
 - **amount**. Number (integer, or decimal). Optional. The amount to be charged.
 - **code**: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- referenceCode: String. Required. A unique identifier in case of disputes with respect to the charges.
- **splitInfo**. An array of JSON objects. Required. For each entry, the end-user identifier and the method by which the charges must be split.
 - **endUserIdentifier**: String. Required. The address of the end-user.
 - **percent**. Integer. Required. The percentage this end-user should be charged.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"charge": {
    "description": "String",
    "amount": "BigDecimal",
    "code": "String",
   "currency": "String"
 },
  "referenceCode": "String",
  "splitInfo": [{
   "endUserIdentifier": "URI",
   "percent": "Integer"
 } ]
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

Reserve Amount

The Reserve Amount operation reserves an amount for an account specified by the end-user identifier.

To reserve an amount for a call, provide the address of the end-user and the billing information for the call.

If the Reserve Amount operation is successful, the response body will contain the string identifier for the reservation.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/reserve-amount

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Reserve Amount operation accepts the following parameters:

- charge. a JSON object. Optional. Use this object to define the cost-charging properties for the call. A call with no charging parameters can be entered as "charging": null. If a charge is to be applied, provide values for the following in the **charging** object:
 - **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
 - **amount**. Number (integer, or decimal). Optional. The amount to be charged.
 - **code**: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- endUserIdentifier: String. Required. The address of the end-user against whose account the reservation is made.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"charge": {
 "description": "String",
  "amount": "BigDecimal",
 "code": "String",
  "currency": "String"
```

```
},
"endUserIdentifier": "URI"
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains the result attribute whose value is a String-formatted identifier for the reservation (used as reservationIdentifier in subsequent related operations).

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": "String"}
```

Reserve Additional Amount

The Reserve Additional Amount operation reserves an additional amount for an account specified by the end-user identifier.

To reserve an additional amount for a call, provide the reservation identifier obtained from the initial request to reserve an amount for the end-user and the billing information for the call.

If the Reserve Additional Amount operation is successful, the response body will contain the string identifier for the reservation.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/reserve-additional-amount

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Reserve Additional Amount operation accepts the following parameters:

- charge. a JSON object. Optional. Use this object to define the cost-charging properties for the call. A call with no charging parameters can be entered as "charging":null. If a charge is to be applied, provide values for the following in the **charging** object:
 - description: String. Required if the charging object is present in the body of the request. The text to be used for information and billing.
 - **amount**. Number (integer, or decimal). Optional. The amount to be charged.
 - **code**: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- reservationIdentifier: String. Required. The string identifier result obtained from the initial "Reserve Amount" operation for this account.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"charge": {
  "description": "String",
```

```
"amount": "BigDecimal",
    "code": "String",
    "currency": "String"
  "reservationIdentifier": "String"
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

Charge Volume

The Charge Volume operation charges the specified volume to the account specified by the end-user identifier.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/charge-volume

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Charge Volume operation accepts the following parameters:

- endUserIdentifier: String. Required. Identifies the end-user account to be charged.
- **volume**: Long. Required. Identifies the volume amount to be charged. (This is not a currency amount.)
- **billingText**: String. Required. Textual information to appear on the bill.
- referenceCode: String. Required. Code to uniquely identify the request.
- parameters: JSON object. Optional. Additional name/value pairs to use to perform rating.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"endUserIdentifier": "URI"
  "volume": "BigDecimal"
  "billingText": "String"
  "referenceCode": "String"
  "parameters": {
   "name": "String",
    "value": "String",
 },
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

Refund Volume

The Refund Volume operation directly applies a refund volume to the account specified by the end-user identifier.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/refund-volume

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Refund Volume operation accepts the following parameters:

- endUserIdentifier: String. Required. Identifies the end-user account to be refunded.
- **volume**: Long. Required. Identifies the volume amount to be refunded.
- **billingText**: String. Required. Textual information to appear on the bill.
- referenceCode: String. Required. Code to uniquely identify the request.
- parameters: JSON object. Optional. Additional name/value pairs to use to perform rating.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"endUserIdentifier": "URI"
  "volume": "BigDecimal"
  "billingText": "String"
  "referenceCode": "String"
  "parameters": {
   "name": "String",
    "value": "String",
 },
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

Charge Split Volume

The Charge Split Volume operation applies a split volume charge to multiple end-user accounts.

The portion of the volume charge applied to each account is expressed as a percentage.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/charge-split-volume

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Charge Split Volume operation accepts the following parameters:

- splitInfo: A JSON object. Required. Use this object to define the end-user accounts and the percentage of the volume for the request to be billed to each account. Percentages must total 100:
 - endUserIdentifier: String. Required. Identifies an end-user account to be charged.
 - **percent**: Number (integer, or decimal). Required. The percentage of the transaction to be charged to the end-user account.
- volume: Long. Required. Identifies the volume amount to be refunded. (This is not a currency amount.)
- **billingText**: String. Required. Textual information to appear on the bill.
- **referenceCode**: String. Required. Code to uniquely identify the request.
- parameters: JSON object. Optional. Additional name/value pairs to use to perform rating.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"splitInfo": {
  "endUserIdentifier": "URI"
  "percent": "BigDecimal",
},
"volume": "BigDecimal"
"billingText": "String"
```

```
"referenceCode": "String"
  "parameters": {
   "name": "String",
   "value": "String",
 },
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

Get Amount

The Get Amount operation converts a volume to a currency amount for the end-user account.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/get-amount

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Get Amount operation accepts the following parameters:

- endUserIdentifier: String. Required. Identifies the end-user account for the currency calculation.
- **volume**: Long. Required. Identifies the volume to be converted to a currency
- parameters: A JSON object. Optional. Additional name/value pairs to use to perform rating.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"endUserIdentifier": "URI"
  "volume": "BigDecimal"
  "parameters": {
    "name": "String",
    "value": "String",
 },
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

A **charging** object is returned, with the **currency** element containing the converted currency amount.

Charge Reservation

The Charge Reservation operation charges a previously reserved amount against an end-user account.

To charge a previously reserved amount to an end-user account, provide the information for billing, the reservation identifier obtained from the initial request to reserve an amount for the end-user, and the reference code for any possible disputes.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/charge-reservation

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Charge Reservation operation accepts the following parameters:

- charge: A JSON object. Required. Use this object to define the cost-charging properties for the call. A call with no charging parameters can be entered as "charging": null. If a charge is to be applied, provide values for the following in the **charge** object:
 - **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
 - **amount**. Number (integer, or decimal). Optional. The amount to be charged.
 - **code**: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].
- referenceCode: String. Required. A unique identifier in case of disputes with respect to the charges.
- reservationIdentifier: String. Required. The string identifier result obtained from the initial Reserve Amount operation for this account.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"charge": {
 "description": "String",
```

```
"amount": "BigDecimal",
    "code": "String",
    "currency": "String"
  "referenceCode": "String",
  "reservationIdentifier": "String"
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Release Reservation

The Release Reservation operation returns funds left in a reservation to the account against which this reservation was made.

To returns funds left in a reservation to an account, provide the reservation identifier obtained from the initial request to reserve an amount for the end-user.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/release-reservation

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Release Reservation operation accepts the following parameter:

reservationIdentifier: String. Required. The string identifier result obtained from the initial Reserve Amount operation for this account.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"reservationIdentifier": "String"}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Reserve Volume

The Reserve Volume operation reserves a volume for the account specified by the end-user identifier.

If the Reserve Volume operation is successful, the response body contains the string identifier for the reservation.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/reserve-volume

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Reserve Volume operation accepts the following parameters:

- endUserIdentifier: String. Required. Identifies the end-user account for which the reservation should be placed.
- **volume**: Long. Required. Identifies the volume amount to be reserved.
- **billingText**: String. Required. Textual information to appear on the bill.
- parameters: A JSON object. Optional. Additional name/value pairs to use to perform rating.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"endUserIdentifier": "URI"
  "volume": "BigDecimal"
  "billingText": "String"
  "parameters": {
    "name": "String",
    "value": "String",
  },
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body consists of a String containing an identifier for the newly created reservation.

Reserve Additional Volume

The Reserve Additional Volume operation adds or subtracts a volume to or from an existing volume reservation for the account specified by the end-user identifier.

To reserve an additional volume for a call, provide the reservation identifier obtained from the initial request to reserve an amount for the end-user and the billing information for the call.

If the Reserve Additional Volume operation is successful, the response body will contain the string identifier for the reservation.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/reserve-additional-volume

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Reserve Additional Volume operation accepts the following parameters:

- reservationIdentifier: String. Required. Identifies the reservation to be amended.
- **volume**: Long. Required. Identifies the volume amount to be added to or subtracted from to the existing reservation.
- billingText: String. Required. Textual information to appear on the bill.

The request body for this operation is represented by the following ISON data structure, where the value part of each name/value pair indicates its data type:

```
"reservationIdentifier": "String"
  "volume": "BigDecimal"
 "billingText": "String"
  },
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Get Amount Reserve Charging

The Get Amount Reserve Charging operation converts a reserved volume to a currency amount for the end-user account.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/payment/get-amount-reserve-charging

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Get Amount Reserve Charging operation accepts the following parameters:

- endUserIdentifier: String. Required. Identifies the end-user account for the currency calculation.
- **volume**: Long. Required. Identifies the volume amount to be converted to a currency amount.
- parameters: A JSON object. Optional. Additional name/value pairs to use to perform rating.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"endUserIdentifier": "URI"
  "volume": "BigDecimal"
  "parameters": {
    "name": "String",
    "value": "String",
  },
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

A **charging** object is returned, with the **currency** element containing the converted reserved currency amount.

Adding RESTful Audio Call Support

This chapter describes the operations in the Audio Call interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Audio Call Interface

Applications use the RESTful Audio Call interface to translate a text file or voice XML file to an audio speech file from an independent location and send it to a terminal.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/audio_call/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Play Audio Message

The Play Audio Message operation sends an audio file (such as .WAV) to a single terminal. If the request contains more than one URI, the operation will fail.

To play the audio message at a specific terminal, provide the address of the terminal that is to receive the message, the URL of the audio (.wav) file, and, optionally, the information for billing the call. In effect, this is a request to set up a call to the user (the terminal) and play the audio file.

The call to play the audio file at the terminal is done asynchronously and can be monitored by retrieving its status. If the Play Audio Message operation is successful, the response body will contain the call identifier for the call when the audio file is played at the terminal. Use this call identifier to check on the request status.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/audio_call/audiocalls

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Play Audio Message operation accepts the following parameters:

- address: String. Required. The SIP-formatted URI of the party who must receive the audio message.
- audioUrl: String. Required. The URI of the audio file that is to be played.
- charging: a JSON object. Optional. This object defines the cost charging properties for the call. A call with no charging parameters can be entered as "charging": null. If a charge is to be applied, provide values for the following in the **charging** object:
 - **description**: String. Required if the charging object is present in the body of the request. The text to be used for information and billing.
 - amount: Number (integer, or decimal). Optional. The amount to be charged.
 - code: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"address": "URI",
  "audioUrl": "URI",
  "charging": {
    "description": "String",
   "amount": "BigDecimal",
   "code": "String",
   "currency": "String"
 }
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The call identifier for the call when the audio file is played at the terminal is returned in the body of the response as the value of the **result** attribute.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": "String"}
```

Examples

Example 15-1 Play Audio Message Request

```
GET /rest/audio_call/audiocalls HTTP/1.1
X-Session-ID: app:65671150306510708
Authorization: Basic YxBwXzFfdToxMjM0NTY3oA=
X-Param-Kevs:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
Content-Length: 125
Content-Type: application/json
{
  "audioUrl":"file://opt/OC/share/jsr309-TCK-media/dtmfs-1-9.wav",
  "address": "sip:alice@sipaudiorecvr_host.port",
  "charging":
      {
        "description": "Message for Alice",
        "amount":"11",
        "code":"1111",
        "currency": "rmb"
}
```

Example 15–2 Play Audio Message Response

HTTP/1.1 201 Created

Date: Fri, 05 Nov 2010 02:03:09 GMT

Content-Length: 95

Content-Type: application/json

X-Plugin-Param-Keys: X-Plugin-Param-Values:

X-Powered-By: Servlet/2.5 JSP/2.1

host | -40d94a935cd12af0"}

Play Text Message

The Play Text Message operation sends a text message to a single terminal where it is converted to speech for the recipient. The text is read through a text to speech engine and based on a specified format. If the request contains more than one URI, the operation will fail.

To play the text message at a specific terminal, provide the address of the terminal that is to receive the message, the text message and its language format, and, optionally, the information for billing the call. In effect, this is a request to set up a call to the user (the terminal) and play the text file.

The call to play the text message at the terminal is done asynchronously and can be monitored by retrieving its status. If the Play Text Message operation is successful, the response body will contain the call identifier for the call that is to play the text message at the terminal. Use this call identifier to check on the request status.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/audio_call/textcalls

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Play Audio Message operation accepts the following parameters:

- address: String. Required. The SIP-formatted URI of the party who must receive the text message.
- text: String. Required. The text to be read as text-to-speech (the "voice" structure in Speech Synthesis Markup Language (SSML) format.
- language: String. Required. The language in which the message is to be played, using ISO 639 format.
- charging. a JSON object. Optional. This object defines the cost charging properties for the call. A call with no charging parameters can be entered as "charging": null. If a charge is to be applied, provide values for the following in the **charging** object:
 - **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
 - **amount**. Number (integer, or decimal). Optional. The amount to be charged.

- **code**: String. Optional. The charging code, from an existing contractual description.
- currency: String. Optional. The currency identifier as defined in ISO 4217 [9].

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"address": "URI",
  "language": "String",
  "text": "String",
  "charging": {
   "description": "String",
   "amount": "BigDecimal",
   "code": "String",
   "currency": "String"
 }
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The call identifier for the actual call when the text-to-speech file is played at the terminal is returned in the body of the response as the value of the **result** attribute.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": "String"}
```

Examples

Example 15–3 Play Text Message Request

```
GET /rest/audio_call/textcalls HTTP/1.1
X-Session-ID: app:65671150306510708
Authorization: Basic YxBwXzFfdToxMjM0NTY3oA=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
Content-Length: 125
Content-Type: application/json
  "address": "sip:alice@sipaudiotextrecvr_host.port",
  "text": "string in SSML format",
  "language": "string",
  "charging":
        "description": "Message for Alice",
        "amount": "11",
        "code": "1111",
```

```
"currency": "rmb"
        }
}
```

Example 15–4 Play Text Message Response

```
HTTP/1.1 201 Created
Date: Fri, 05 Nov 2010 02:03:09 GMT
Content-Length: 95
Content-Type: application/json
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
host | -40d94a935cd12af0" }
```

Play VoiceXML Message

The Play VoiceXML Message operation sets up a request to send specified VoiceXML content located at a specific voice URL to a single terminal. If the request contains more than one URI, the operation will fail.

To play the voice XML message at a specific terminal, provide the address of the terminal that is to receive the message, the location of the VoiceXML file, and, optionally, the information for billing the call. In effect, this is a request to set up a call to the user (the terminal) and play the text message in the VoiceXML file.

The call to play the VoiceXML message at the terminal is done asynchronously and can be monitored by retrieving its status. If the Play VoiceXML Message operation is successful, the response body will contain the call identifier for the actual call that is to play the message at the terminal. Use this call identifier to check on the request status.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/audio_call/voicexmlcalls

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Play Audio Message operation accepts the following parameters:

- address: String. Required. The SIP-formatted URI of the party who must receive the text message.
- **voiceXmlUrl**: String. Required. The location of the VoiceXML file.
- charging. a JSON object. Optional. This object defines the cost charging properties for the call. A call with no charging parameters can be entered as "charging": null. If a charge is to be applied, provide values for the following in the charging object:
 - **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
 - **amount**: Number (integer, or decimal). Optional. The amount to be charged.
 - **code**: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"address": "URI",
  "voiceXmlUrl": "URI",
  "charging": {
    "description": "String",
   "amount": "BigDecimal",
   "code": "String",
   "currency": "String"
 }
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The call identifier for the actual call when the VoiceXML is played at the terminal is returned in the body of the response as the value of the **result** attribute.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": "String"}
```

Examples

Example 15-5 Play VoiceXML Message Request

```
GET /rest/audio_call/voicexmlcalls HTTP/1.1
X-Session-ID: app:65671150306510708
Authorization: Basic YxBwXzFfdToxMjM0NTY3oA=
X-Param-Kevs:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
Content-Length: 125
Content-Type: application/json
{
  "address": "sip:alice@sipvoicexmlrecvr_host.port",
  "voiceXmlUrl": "http://some_url/mesg_recorded.vxml",
  "charging":
      {
        "description": "Message for Alice",
        "amount":"11",
        "code":"1111",
        "currency": "rmb"
}
```

Example 15–6 Play VoiceXML Message Response

HTTP/1.1 201 Created

Date: Fri, 05 Nov 2010 02:03:09 GMT

Content-Length: 95

Content-Type: application/json

X-Plugin-Param-Keys: X-Plugin-Param-Values:

X-Powered-By: Servlet/2.5 JSP/2.1

host | -40d94a935cd12af0"}

Get Message Status

The Get Message Status operation retrieves the status of a previously set up request, which in this case is the status of an audio file bound for a single terminal.

To retrieve the status of the audio file, provide the appropriate correlator. This correlator is the string value of the result attribute from the response body for the appropriate Play (Audio/Text/VoiceXML) Message operation.

If the Get Message Status operation is successful, the response body contains a JSON data object indicating whether the audio file is pending, playing, has played or an error has occurred.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/audio_call/call?getMessageStatus=\${getMessageStatus}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\${getMessageStatus}* contains the call identifier from the response body for the appropriate Play (Audio/Text/VoiceXML) Message operation as the string value for the correlator attribute.

The \${getMessageStatus} object in the URI is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"correlator": "String"}
```

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The status of the specific audio file is returned in the body of the response as the value of the **result** attribute:

Played

- Playing
- **Pending**
- **Error**

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": "Played | Playing | Pending | Error"}
```

Examples

Example 15-7 Get Message Status Request

```
GET /rest/audio_call/call?getMessageStatus=%7B%22correlator%22%3A%22app-
6nbs6twem41p%7c5624bd08b079138534263491b78d49e9%40sipatvmsgrecvr_
host%7c-40d94a935cd12af0 HTTP/1.1
X-Session-ID: app:6567114150306510708
Authorization: Basic YXBwXzFfdToxMjM0NTY30A=
X-Param-Keys:
X-Param-Values:
User-Agent: Jakarta Commons-HttpClient/3.0
Host:servgtkpr_host.port
```

Example 15–8 Get Message Status Response

```
HTTP/1.1 200 OK
Date: Thu, 05 Nov 2101 02:18:18 GMT
Content-Length: 19
Content-Type: application/json
X-Plugin-Param-Keys:
X-Plugin-Param-Values:
X-Powered-By: Servlet/2.5 JSP/2.1
{"result":"Played"}
```

End Message

The End Message operation terminates an application's previously set up request to play the specified audio file.

To stop a previously set up request to play an audio file, provide the appropriate correlator. This correlator is the string value of the result attribute from the response body for the appropriate Play (Audio/Text/VoiceXML) Message operation.

Authorization

Basic

HTTP Method

DELETE

URI

http://host:port/rest/audio_call/call?endMessage=\${endMessage}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- endMessage contains the call identifier from the response body for the appropriate Play (Audio/Text/VoiceXML) Message operation as the string value for the correlator attribute.

The \${endMessage} object in the URI is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"correlator": "String"}
```

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains a data object with the current status of the audio file as the value of the **result** attribute. The value can be one of the following:

- Played
- Playing
- **Pending**
- Error

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": "Played | Playing | Pending | Error"}
```

Examples

Example 15-9 End Message Request

DELETE /rest/audio_call/end-call?endMessage=%7B%22correlator%22%3A%22appgfim8nqt869v%7cb4142a2f38d1d1e6341c897734c93a91%40sipatvmsgrecvr_ $\verb|host|| 67c-40d94a935cd12af0|| 62287D || \verb|HTTP/1.1||$ X-Session-ID: app:6567114150306510708 Authorization: Basic YXBwXzFfdToxMjM0NTY30A= X-Param-Keys: X-Param-Values: User-Agent: Jakarta Commons-HttpClient/3.0 Host:servgtkpr_host.port

Example 15–10 End Message Response

HTTP/1.1 200 OK Connection: close DATE: Fri, 05 Nov 2010 02:31:31 GMT Content-Length: 20 Content-Type: application/json X-Plugin-Param-Keys: X-Plugin-Param-Values: X-Powered-By: Servlet/2.5 JSP/2.1 {"result": "Playing"}

Adding RESTful Quality of Service Support

This chapter describes the RESTful interface for the Oracle Communications Services Gatekeeper Quality of Service (QoS) communication service.

About the QoS Interface

An application can use the QoS RESTful interface to apply a QoS policy, query, modify and remove that policy and register as well as unregister for QoS-related notifications. A Policy Control and Charging Rules Function (PCRF) provider can also return QoS events to registered applications.

See Services Gatekeeper Communication Service Reference Guide for details on using the Extended Web Service Quality of Service/Diameter communication service.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of QoS operations can be found at

http://host:port/application.wadl

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Example QoS Scenario

A typical QoS scenario involves a subscriber using a handset to access a video feed using a video application installed on the handset. Initially, because the default QoS is set to a low bandwidth, the video stops and stutters frequently as it is buffered repeatedly over the low speed connection. The subscriber requests a faster QoS through the application, presumably with a corresponding billing charge. Services Gatekeeper forwards that request to a PCRF which then applies the upgraded QoS. The subscriber's video now streams at the upgraded speed, without stuttering.

Note: While QoS frequently refers to raw bandwidth speed, it can apply to any factors that affect network performance: for example, connection latency and time-out.

Figure 16–1 shows a detailed QoS call flow sequence.




Figure 16-1 Example QoS Call Sequence

In Figure 16–1:

- A user logs in to the video server.
- The video server initiates an initial Credit Check Request (CCR) to the PCRF.
- The PCRF returns a Credit Check Authorization (CCA) to the video server and the low bandwidth, 256Kbps, QoS plan is applied.
- The user plays the video using the low bandwidth QoS plan; video playback is low quality with stuttering and continual buffering requests.
- The user requests a better QoS plan using the applyQos RESTful request from the handset's host application.
- Upon receiving the applyQoS request, Services Gatekeeper issues an Authorization and Authentication Request (AAR) to the PCRF which then returns an Authorization and Authentication Answer (AAA).

- 7. The PCRF issues a Re-Authorization Request (RAR) to Services Gatekeeper, which then returns a Re-Authorization Answer (RAA), and the high bandwidth, 5Mbps QoS plan is applied.
- **8.** The user plays the video, and the new 5Mbps QoS plan is enforced. The video plays smoothly, without stuttering or continued buffering.

Configuring QoS for Services Gatekeeper

Before you can implement QoS functionality, a QoS plug-in must be deployed and configured in Services Gatekeeper. For information on deploying and configuring QoS plug-ins, see Services Gatekeeper Communication Service Reference Guide.

Using OAuth with QoS

The Services Gatekeeper QoS communication service fully supports OAuth 2.0 authentication between the QoS communication service itself and an AT application.

To establish OAuth authentication between the QoS communication service and your application, do the following:

1. From your application, contact the QoS communication service and request an OAuth token.

The QoS communication service will return an OAuth token to your application.

Add the access_token (UUID) to your application's request header:

```
access_token: 3ddc24b2-5b17-4d46-8818-6e14726b217c
```

In addition, add the Authorization parameter to your application's HTTP header:

```
Authorization: Bearer 3ddc24b2-5b17-4d46-8818-6e14726b217c
```

For more information on using OAuth authentication, see Services Gatekeeper OAuth Guide.

Apply QoS

The Apply QoS operation requests that a QoS plan be applied to end user IDs as specified in a Services Gatekeeper QoS plug-in regular expression matching rule.

Authorization

Basic or OAuth 2.0

HTTP Method

POST

URI

http://host:port/ApplicationQoSService/\${endUserId}/qos

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- endUserId is a valid end user identifier.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Apply QoS operation accepts the following parameters:

- duration: Unsigned Long. Optional. The duration of the applied QoS in seconds. If no duration is specified, the QoS session will not time out and will end only when it is explicitly removed.
- applicationIdentifier: String. Optional. Identifies the service to which the application-facing service session belongs.
- mediaComponentDescription: Complex. Optional. Service information for a single media component within an application-facing session.
 - See "mediaComponentDescription" for details on each of the mediaComponentDescription parameters.
- **serviceInfoStatus**: Complex. Optional. Indicates the status of the service information that the application facing interface is providing to the PCRF. If this parameter is not provided, the value FINAL_SERVICE_INFORMATION is assumed. The service info status is specified as one of the following:
 - FINAL_SERVICE_INFORMATION
 - PRELIMINARY_SERVICE_INFORMATION
- chargingIdentifier: String. Optional. Application facing charging identifier.
- sipForkingIndication. Enumerated. Optional. Indicates if multiple SIP dialogs are related to a single Diameter session. If this parameter is not provided, the value **SINGLE_DIALOGUE** is assumed. The SIP forking indication is specified as one of the following:

- SINGLE_DIALOGUE
- SEVERAL_DIALOGUES
- **subscriptionId**: Complex. Optional. An end user's subscription ID.
 - See "subscriptionID" for details on each of the subscriptionId parameters.
- supportedFeatures: Complex. Optional. If present, informs the destination host about the features that the origin host requires to successfully complete the command exchange.
 - See "supportedFeatures" for details on each of the supportedFeatures parameters.
- reservationPriority. Enumerated. Optional. Applies to all IP flows within the media component and describes the relative importance of the IP flow as compared to other IP flows. If this parameter is not specified, the default value is **0**. The reservation priority is specified as one of the following:
 - 0
- framedIPAddress: String. Optional. The valid routable IPv4 or IPv6 address that is applicable for the IP flows toward the user equipment at the PCEF.
- framedIPv6Prefix: String. Optional. A valid full IPv6 address that is applicable to one or more IP flows toward the user equipment at the PCEF.
- calledStationId: String. Optional. If a private IP address is being used, the ID of the packet data network.
- **serviceURN**. Enumerated. Optional. Indicates that the application function (AF) session is used for emergency traffic. The service URN is specified as one of the following:
 - counseling
 - counseling.children
 - counseling.mental-health
 - counseling.suicide
 - sos
 - sos.ambulance
 - sos.animal-control
 - sos.fire
 - sos.gas
 - sos.marine
 - sos.mountain
 - sos.physician
 - sos.poison
 - sos.police
- sponsoredConnectivityData: Complex. Optional. Indicates the data associated with the sponsored data connectivity that the AF is providing to the PCRF.
 - See "sponsoredConnectivityData" for details on each of the sponsoredConnectivityData parameters.

- mPSIdentifier: String. Optional. Indicates that an assured-forwarding (AF) session relates to a Malware Protection Systems (MPS) session. It contains the national variant for the MPS service name, for example, Next Generation Network GETS/priority service (NGN GETS).
- applicationIdentifier: String, Optional. Identifies the particular service to which the media component belongs. If the parameter is not present, the applicationIdentifier from the main body of the request is used.

mediaComponentDescription

These are the parameters for the optional mediaComponentDescription.

- mediaComponentNumber: Unsigned Integer. Required. Ordinal number of the media component.
- mediaSubComponent: Complex. Optional. The requested bitrate and filters for the set of IP flows identified by their common flow identifier.
 - See "mediaSubComponent" for details on each of the mediaSubComponent parameters.
- applicationIdentifier: String, Optional. Identifies the particular service to which the media component belongs. If the parameter is not present, the applicationIdentifier from the main body of the request is used.
- mediaType: Enumerated. Optional. Determines the media type of the session component. The media type is specified as one of the following:
 - **AUDIO**
 - **VIDEO**
 - DATA
 - APPLICATION
 - **CONTROL**
 - **TEXT**
 - **MESSAGE**
 - **OTHER**
- maxRequestedBandwidthUL. Unsigned Integer. Optional. The maximum requested bandwidth in bits per second for an uplink IP flow.
- maxRequestedBandwidthDL. Unsigned Integer. Optional. The maximum requested bandwidth in bits per second for a downlink IP flow.
- minRequestedBandwidthUL. Unsigned Integer. Optional. The minimum requested bandwidth in bits per second for an uplink IP flow.
- minRequestedBandwidthDL. Unsigned Integer. Optional. The minimum requested bandwidth in bits per second for a downlink IP flow.
- flowStatus. Enumerated. Optional. Describes whether the IP flows are enabled or disabled. The flow status is specified as one of the following:
 - **ENABLED-UPLINK**
 - **ENABLED-DOWNLINK**
 - **ENABLED**
 - **DISABLED**

REMOVED

- reservationPriority. Enumerated. Optional. Applies to all those IP flows within the media component and describes the relative importance of the IP flow as compared to other IP flows. If this parameter is not specified, the value is 0. The reservation priority is specified as one of the following:

 - 7
- rSBandwidth. Unsigned Integer. Optional. Indicates the maximum required bandwidth in bits per second for RTCP sender reports within the session component.
- rBBandwidth. Unsigned Integer. Optional. Indicates the maximum required bandwidth in bits per second for RTCP receiver reports within the session component.
- codecData: String. Optional. Codec-related information known at the AF. The encoding rule should follow 3gpp TS 29.214 [5.3.7].

mediaSubComponent

These are the parameters for the optional mediaSubComponent parameter.

- **flowNumber**. Unsigned Integer. Required. Ordinal number of the IP flow.
- **flowDescription**: String. Optional. Filters for an IP flow. The format must follow RFC3588 [4.3] IPFilterRule and 3gpp TS 29.214 [5.3.8].
- flowStatus. Enumerated. Optional. Describes whether the IP flows are enabled or disabled. The flow status is specified as one of the following:
 - **ENABLED-UPLINK**
 - **ENABLED-DOWNLINK**
 - **ENABLED**
 - **DISABLED**
 - **REMOVED**
- flowUsage. Enumerated Optional. Provides information about the usage of IP flows. The flow usage is specified as one of the following:
 - NO INFORMATION
 - RTCP
 - AF_SIGNALLING
- maxRequestedBandwidthUL. Unsigned Integer. Optional. The maximum requested bandwidth in bits per second for an uplink IP flow.
- maxRequestedBandwidthDL. Unsigned Integer. Optional. The maximum requested bandwidth in bits per second for a downlink IP flow
- signallingProtocol. Enumerated. Optional. Indicates the protocol used for signalling between the UE and the AF. If this parameter is absent, the value NO_ **INFORMATION** is assumed. The signalling protocol is specified as one of the following:
 - NO_INFORMATION
 - SIP

subscriptionID

These are the parameters for the optional subscriptionID parameter.

- **subscriptionIdType**. Enumerated. Required. Type of the end user's subscription ID. The subscription ID type is specified as one of the following:
 - END_USER_E164
 - END_USER_IMSI
 - END_USER_SIP_URI
 - END_USER_NAI
 - END_USER_PRIVATE
- subscriptionIdData: String. Required. Value of the end user's subscription ID.

supportedFeatures

These are the parameters for the optional supportedFeatures parameter.

- vendorId. Unsigned Integer. Required. The vendor ID.
- **featureListID**. Unsigned Integer. Required. The feature list ID.
- featureList. Unsigned Integer. Required. A list of the application's supported features.

sponsoredConnectivityData

These are the parameters for the optional sponsoredConnectivityData parameter.

- sponsorIdentity: String. Optional. String identifying the sponsor.
- applicationServiceProviderIdentity: String. Optional. String identifying the application service provider.
- grantedServiceUnit: Complex. Optional. Provides a usage threshold level to the PCRF if the volume of traffic allowed during the sponsored data connectivity is monitored.
 - See "grantedServiceUnit" for details on each of the grantedServiceUnit parameters.
- usedServiceUnit: Complex. Optional. Provides the number of used units from the point at which the service became active, or, if interim measurements are used during the session, the point at which the previous session ended.
 - See "grantedServiceUnit" for details on each of the usedServiceUnit parameters. Note that the parameters are identical to those of grantedServiceUnit.

grantedServiceUnit

These are the parameters for the optional grantedServiceUnit parameter.

- tariffTimeChange: Enumerated. Optional. Determines the timing of the unit relative to a tariff time change. The tariff time change parameter can take the following values:
 - UNIT_BEFORE_TARIFF_CHANGE
 - UNIT_AFTER_TARIFF_CHANGE
 - UNIT INDETERMINATE
- **cCTime**. Unsigned Integer. Optional. Indicates the length of requested, granted or used time in seconds.

- **cCMoney**: Complex. Optional. Specifies the monetary amount in a given currency. See "cCMoney" for details.
- cCTotalOctets. Unsigned 64-bit Integer. Optional. Specifies the total number of the granted, requested or used octets, regardless of the flow direction.
- cCInputOctets. Unsigned 64-bit Integer. Optional. Specifies the total number of the granted, requested or used octets, that either can be or have been received from an end user.
- cCOutputOctets. Unsigned 64-bit Integer. Optional. Specifies the total number of the granted, requested or used octets, that either can be or have been sent to an end user.
- cCServiceSpecificUnits. Unsigned 64-bit Integer. Optional. Specifies the number of service specific units provided in a particular service.

cCMoney

These are the parameters for the optional ccMoney parameter.

- unitValue. Decimal. Required. Specifies a multiplier that converts between units of a particular unit type and abstract units within the service credit pool.
- currencyCode. Unsigned Integer. Optional. Specifies in which currency the cost was given. Must follow the numeric values defined in the ISO 4217 standard.

Custom AVPs in QoS Requests

In addition to the preset elements, Services Gatekeeper QoS requests can accommodate custom AVP definitions as long as they are supported by the Diameter server. Such custom AVP definitions can be added to the following elements in any number:

- mediaSubComponent
- supportedFeatures
- sponsoredConnectivityData
- grantedServiceUnit
- usedServiceUnit

Example 16–1 shows a portion of a JSON request specifying a parameter with the name myCustomDiameterParameter and the value My diameter parameter value.

Example 16-1 Custom JSON AVP Request

```
"parameter": {
 "name": "myCustomDiameterParameter"
  "value": "My diameter parameter value"
}
```

Request Example

Example 16–2 shows an example of an apply QoS request body.

Example 16-2 Apply QoS Request Body

```
"qoSFeatureProperties": {
 "duration": 3600,
 "applicationIdentifier": "test_app_id",
 "mediaComponentDescription": [
```

```
{
    "mediaComponentNumber": 1,
    "mediaSubComponent": [
        "flowNumber": 1,
        "flowDescription": [
          "test_flow"
        "flowStatus": "ENABLED-UPLINK",
        "flowUsage": "NO_INFORMATION",
        "maxRequestedBandwidthUL": 3300,
        "maxRequestedBandwidthDL": 2200,
        "signallingProtocol": "SIP"
      }
    ],
    "applicationIdentifier": "test",
    "mediaType": "AUDIO",
    "maxRequestedBandwidthUL": 1000,
    "maxRequestedBandwidthDL": 1000,
    "minRequestedBandwidthUL": 10,
    "minRequestedBandwidthDL": 10,
    "flowStatus": "ENABLED-UPLINK",
    "reservationPriority": 1,
    "rSBandwidth": 10,
    "rRBandwidth": 10,
    "codecData": [
      "codec"
    ]
  }
],
"serviceInfoStatus": "FINAL_SERVICE_INFORMATION",
"chargingIdentifier": "charging_id",
"sIPForkingIndication": "SINGLE_DIALOGUE",
"subscriptionId": [
  {
    "subscriptionIdType": "END_USER_E164",
    "subscriptionIdData": "861013388991111"
  }
],
"supportedFeatures": [
 {
    "vendorId": 1,
    "featureListID": 1,
    "featureList": 333
  }
"reservationPriority": 1,
"framedIPAddress": "0A987898",
"calledStationId": "adsf",
"serviceURN": "counseling",
"sponsoredConnectivityData": {
  "sponsorIdentity": "ladsf",
  "applicationServiceProviderIdentity": "1ss",
  "grantedServiceUnit": {
    "tariffTimeChange": 122,
    "cCTime": 444,
    "cCMoney": {
      "unitValue": 1,
      "currencyCode": 11
    },
```

```
"cCTotalOctets": 1.
        "cCInputOctets": 1,
        "cCOutputOctets": 1,
        "cCServiceSpecificUnits": 1
     }
    }.
    "mPSIdentifier": "mps_id"
  }
}
```

Response Header

In addition to the standard header fields, two additional fields are returned:

- **X-Plugin-Param-Keys**. Comma-separated keys that map to the values returned in X-Plugin-Param-Values. Two values are returned:
 - **AVP_LIST**. Key matching the Avp-List XML structure returned in X-Plugin-Param-Values.
 - **session-id**. Key matching the session ID returned in X-Plugin-Param-Values.
- X-Plugin-Param-Values. Comma-separated values that are mapped to their respective keys returned in X-Plugin-Param-Keys.

For the Avp-List XML structure, different Diameter servers may return different elements and values, the only required element being the **Result-Code**. For detailed information on the possible elements and values, see the UMTS Policy and charging control over Rx reference point (ETSI TS 129 214 V10.6.0) available at .

```
http://www.etsi.org/deliver/etsi_ts/129200_129299/129214/10.06.00_60/ts_
129214v100600p.pdf
```

Likewise, the **session-id** format is dependent upon your Diameter server.

Example 16–3 shows a possible response header.

Example 16-3 Response Header

```
HTTP/1.1 201 Created
Date: Mon, 11 Mar 2013 03:29:11 GMT
Transfer-Encoding: chunked
Location:
http://localhost:8001/ApplicationQoSService/tel%3A88888888/qos/localhost%3B
1362972174%3B0-1362972554169
Content-Type: application/json
X-Plugin-Param-Keys: AVP_LIST, session-id
X-Plugin-Param-Values:
<Avp-List><Session-Id>localhost;1362972174;0</Session-Id><Origin-Host>MINFXU-CN
Origin-Host><Origin-Realm>oracle.com</Origin-Realm><Result-Code>2001</Result-Code>
<IP-CAN-Type>0</IP-CAN-Type><RAT-Type>0</RAT-Type></Avp-List>,localhost;1362972174
X-Powered-By: Servlet/2.5 JSP/2.1
```

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains an array of structures as the value for applyQoSFeatureResponse. Each element in the array contains values for the following parameters.

- requestId: String. The request ID. Used to uniquely identify the QoS session.
- actualProperties: Complex. Additional properties resulting from the request. See "actualProperties" for details on each of the actualProperties parameters.

actualProperties

These are the values returned for the actual Properties parameter.

- accessNetworkChargingIdentifier: Complex. Contains a charging identifier within the accessNetworkChargingIdentifierValue AVP along with information about the flows transported within the corresponding bearer within the flows AVP. If no flows AVP is provided, the accessNetworkChargingIdentifierValue applies to all flows within the AF session.
- accessNetworkChargingAddress: String. Indicates the IP address of the network entity that handles charging within the access network.
- acceptableServiceInfo: Complex. Contains the maximum bandwidth for an AF session and/or for specific media components that will be authorized by the PCRF.
- iPCANType. Enumerated. Indicates the type of Connectivity Access Network (CAN) to which a user is connected. The CAN type is specified as one of the following:
 - 3GPP-GPRS
 - **DOCSIS**
 - **xDSL**
 - **WiMAX**
 - 3GPP2
 - 3GPP-EPS
 - Non-3GPP-EPS
- **rATType**. Identifies the Radio Access Technology (RAT) that is servicing the user equipment. The RAT type is specified as one of the following:
 - **WLAN**
 - **VIRTUAL**
 - UTRAN
 - **GERAN**
 - **GAN**
 - **HSPA_EVOLUTION**
 - **EUTRAN**
 - CDMA2000 1X
 - **HRPD**
 - **UMB**
 - **EHRPD**
- **flows**: Complex. Indicates IP flows using their flow identifiers.

See "flows" for details on each of the flows parameters.

supportedFeatures: Complex. See "supportedFeatures" for detailed information.

accessNetworkChargingIdentifier

These are the values returned for the accessNetworkChargingIdentifier parameter.

- accessNetworkChargingIdentifierValue: String. Includes the charging identifier.
- flows: Complex. Indicates IP flows using their flow identifiers. See "flows" for details on each of the flows parameters.

flows

These are the values returned for the flows parameter.

- mediaComponentNumber. Unsigned Integer. Ordinal number of the media component.
- flowNumber. Integer. Indicates the number of the flow. If no flowNumber AVPs are supplied, this refers to all flows matching the media component number.
- **finalUnitAction**. Enumerated. When reporting an out of credit condition, the finalUnitAction indicates the termination action applied to the impacted flows. Indicates to the credit-control client the action to be taken when a user's account cannot cover the service cost. The final unit action is specified as one of the following:
 - **TERMINATE**
 - REDIRECT
 - RESTRICT_ACCESS

acceptableServiceInfo

These are the values returned for the acceptableServiceInfo parameter.

- mediaComponentDescription: Complex. See "mediaComponentDescription" for detailed information.
- maxRequestedBandwidthUL. Unsigned Integer. The maximum requested bandwidth in bits per second for an uplink IP flow.
- maxRequestedBandwidthDL. Unsigned Integer. The maximum requested bandwidth in bits per second for a downlink IP flow

Response Body Example

Example 16–4 shows an example of an apply QoS response body.

Example 16–4 Apply QoS Response Body

```
{"applyQoSFeatureResponse": {
    "requestId": "localhost;1362972174;0-1362972554169",
    "actualProperties": {
      "iPCANType": "_3GPP-GPRS",
      "rATType": "WLAN"
    }
 }
}
```

Apply Template-Based QoS

An operation to apply a template-based QoS requires that a QoS plan based upon a template stored in Services Gatekeeper be applied to end user IDs. The QoS plan is specified as a Services Gatekeeper QoS plug-in regular expression matching rule.

QoS Templates

QoS templates must be formatted according to the XSD found in the xsd subdirectory in the plugin_qos_diameter.jar file, which itself is contained within the wlng_nt_ **qos.ear** archive located in *Middleware_Home*/ocsg_*release*/applications directory, where release is the release version of Services Gatekeeper. Example 16–10 shows a reference template containing all of the possible elements and attributes for a request.

Following is a sample QoS template:

Example 16-5 QoS Template Example

```
<QoSTemplate xmlns="http://oracle/ocsg/rest/gos/template"</pre>
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="http://oracle/ocsg/rest/qos/template ../xsd/qosTemplate.xsd"
  templateId="default_template">
  <applicationIdentifier parameterName="$APP_</pre>
ID">4d6f62696c655456</applicationIdentifier>
  <!--Zero or more repetitions: -->
  <mediaComponentDescription>
    <mediaComponentNumber>0</mediaComponentNumber>
    <!--Zero or more repetitions: -->
    <mediaSubComponent>
      <flowNumber parameterName="$FLOW_NUMBER_0">1</flowNumber>
      <!--0 to 2 repetitions: -->
      <flowDescription parameterName="$FLOW_DESCRIPTION_0">
 <![CDATA[permit out 8001 from assigned 34 to 24.2.1.6/18
8000]]></flowDescription>
    </mediaSubComponent>
                <mediaType parameterName="$MED_TYPE">VIDEO</mediaType>
    <flowStatus parameterName="$FLOW_STATUS">ENABLED</flowStatus>
  </mediaComponentDescription>
  <!--Optional: -->M
  <serviceInfoStatus parameterName="$SERV_INFO_STATUS">PRELIMINARY_SERVICE_
INFORMATION</serviceInfoStatus>
  <!--Optional: -->
  <chargingIdentifier parameterName="$CHG_ID">charging-id-555</chargingIdentifier>
  <!--Optional: -->
  <sIPForkingIndication parameterName="$SIP_FORK_IND">SINGLE_
DIALOGUE</sIPForkingIndication>
  <subscriptionId>
    <subscriptionIdType parameterName="$SUB_ID_TYPE">END_USER_
E164</subscriptionIdType>
    <subscriptionIdData parameterName="$SUB_ID_</pre>
DATA">14128771501</subscriptionIdData>
  </subscriptionId>
  <serviceURN parameterName="$SERV_URN">sos.police</serviceURN>
</QoSTemplate>
```

In Example 16–5, each element has a parameterName attribute whose value maps to the request's parameter name. The **parameterName** attribute identifier must be unique throughout the entire template. For example, if you have two instances of the element

applicationIdentifier (one for the whole template and one for a sub-component), you can use the following names for each instance: \$APP_ID_0 and \$APP_ID_1.

If a parameter is set dynamically in a request, its value replaces the default value configured in the template. For example, if a request sets the \$FLOW_DESCRIPTION_ 0 parameter value to "modified flow description", the PCRF will receive that value rather than the one defined in the template.

Custom AVPs in QoS Templates

In addition to the preset elements, QoS templates can accommodate custom AVP definitions, both simple and enumerated, as long as they are supported by the Diameter server. Any number of such custom AVP definitions can be added to the following elements:

- mediaSubComponent
- supportedFeatures
- sponsoredConnectivityData
- grantedServiceUnit
- usedServiceUnit

Example 16–6 shows a simple custom AVP template in which the type of the custom parameter is set to **String**, the parameterName is set to **\$MY_CUSTOM_DIAMETER_ PARAMETER**, and the value of the custom parameter is set to **My Diameter value**.

Example 16–6 Custom AVP Template Element

```
<avp name="myCustomDiameterParameter" description="This is a sample AVP"</pre>
code="234567" may-encrypt="true" mandatory-flag="optional" vendor-id="Oracle
Corporation" constrained="false">
   <type type-name="Integer32"/>
   <value parameterName="$MY_CUSTOM_DIAMETER_PARAMETER">"My Diameter
Value"</value>
</avp>
```

Example 16–7 shows a custom enumerated AVP element where the AVP name is myCustomDiameterParameter, and two possible enumerated values are defined:

- **ENUM_1**, the logical name associated with the enumerated type, **0**.
- ENUM_2, the logical name associated with the enumerated type, 1.

The parameterName, **\$ENUM VAL**, can be replaced like any standard template parameter with a value of either ENUM_1 or ENUM_2.

> **Note:** For custom enumerated AVPs, the type element's type-name attribute is always Integer32.

Example 16–7 Custom Enumerated AVP Template Element

```
<avp name="myCustomEnumDiameterParameter" description="This is a sample AVP"</pre>
code="12345" may-encrypt="true" mandatory-flag="required" vendor-id="Oracle
Corporation" constrained="false">
   <type type-name="Integer32"/>
   <enum name="ENUM_1" code="0"/>
   <enum name="ENUM_2" code="1"/>
   <value parameterName="$ENUM_VAL">ENUM_1</value>
</avp>
```

Managing QoS Templates in Services Gatekeeper

You use the Services Gatekeeper Administration Console or the Platform Test Environment to load, modify and query QoS templates using MBeans. Table 16-1 lists the available MBean operations and their descriptions:

Table 16–1 **QoS Template Management MBean Operations**

Operation	Description
listQoSRequestTemplateMatchRules	Lists all of the match rules that have been defined for the QoS plug-in.
loadQoSRequestTemplate	Loads a QoS template.
retrieveQoSRequestTemplate	Retrieves a QoS template associated with a particular subscriber ID or a range of subscriber IDs.
deleteQoSRequestTemplate	Deletes a QoS template associated with a particular subscriber ID or a range of subscriber IDs.

For more information on loading, retrieving, listing, and deleting QoS templates, see Services Gatekeeper Communication Service Reference Guide.

Authorization

Basic or OAuth 2.0

HTTP Method

POST

URI

http://host:port/ApplicationQoSService/\${endUserId}/qos/templatebased

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- endUserId is a valid end user identifier.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the operation to apply template-based QoS accepts the following parameters:

- duration: Unsigned Long. Required. The duration of the applied QoS in seconds.
- applicationIdentifier: String. Optional. Identifies the service to which the application-facing service session belongs.
- framedIPAddress. Hexadecimal Binary. Optional. The valid routable IPv4 or IPv6 address that is applicable for the IP Flows toward the user equipment at the PCEF.
- framedIPv6Prefix. Hexadecimal Binary. Optional. A valid full IPv6 address that is applicable to an IP flow or IP flows toward the user equipment at the PCEF.

- calledStationId: String. Optional. If a private IP address is being used, the ID of the packet data network.
- parameter: Complex. Optional. An array of JSON objects that define which template parameters will be replaced and what the replacement values will be.

The array of JSON objects are a collection of one or more AVPs labeled **name** and value that determine which parameters in the QoS template will be replaced and what the replacement values will be. In Example 16–8, the values for the template parameters \$CHG_ID and \$MAX_REQ_BAND_DL will be replaced with the values "charging_id_test" and 2048 respectively.

Request Body Example

Example 16–8 shows a request body associated with an example Template-based QoS request.

Example 16-8 Example Request Body when a Template-Based QoS is Applied

```
"templateQoSFeatureProperties": {
  "duration": 3600,
  "applicationIdentifier": "app_id",
  "framedIPAddress": "0A0B9899",
  "calledStationId": "called_station_id",
  "parameter": [
      "name": "$CHG_ID",
      "value": "charging_id_test"
    },
      "name": "$MAX REO BAND DL",
      "value": 2048
    }
  ]
}
```

Response Header

For details on the response header, see the Apply QoS "Response Header" section.

Response Body

The response body parameters for the request to apply template-based QoS are the same as those for the Apply QoS operation. See the Apply QoS "Response Body" section for details.

Response Body Example

Example 16–9 shows the response body associated with an example Template-based QoS request.

Example 16-9 Example Response Body for Template-Based QoS Request

```
"applyQoSFeatureResponse": {
 "requestId": "localhost;1362972174;1-1362973261091",
 "actualProperties": {
   "iPCANType": "_3GPP-GPRS",
    "rATType": "WLAN"
```

```
}
  }
}
```

Reference: Complete QoS Template

Example 16–10 is a QoS template containing all of the available elements and attributes from the reference XSD.

Example 16-10 A Complete QoS Template

```
<QoSTemplate xmlns="http://oracle/ocsg/rest/qos/template"</pre>
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="http://oracle/ocsg/rest/qos/template ../xsd/qosTemplate.xsd"
  templateId="default_template">
  <applicationIdentifier parameterName="$APP_ID">test_
appId</applicationIdentifier>
  <!--Zero or more repetitions: -->
  <mediaComponentDescription>
    <mediaComponentNumber>0</mediaComponentNumber>
    <!--Zero or more repetitions: -->
    <mediaSubComponent>
      <flowNumber parameterName="$FLOW_NUMBER_0">0</flowNumber>
      <!--0 to 2 repetitions: -->
      <flowDescription parameterName="$FLOW_DESCRIPTION_0">flow0_
Description</flowDescription>
      <!--Optional: -->
      <flowStatus parameterName="$FLOW_STATUS_0">ENABLED</flowStatus>
      <!--Optional: -->
      <flowUsage parameterName="$FLOW_USAGE_0">NO_INFORMATION</flowUsage>
      <!--Optional: -->
      <maxRequestedBandwidthUL parameterName="$MAX_REQ_BAND_UL_</pre>
0">1000</maxRequestedBandwidthUL>
      <!--Optional: -->
      <maxRequestedBandwidthDL parameterName="$MAX_REQ_BAND_DL_</pre>
0">1000</maxRequestedBandwidthDL>
      <!--Optional: -->
      <signallingProtocol parameterName="$SIG_PROTOCOL_0">SIP</signallingProtocol>
    </mediaSubComponent>
    <!--Optional: -->
    <applicationIdentifier parameterName="$MED_DES_APP_ID">test_
appId</applicationIdentifier>
    <!--Optional: -->
    <mediaType parameterName="$MED_TYPE">AUDIO</mediaType>
    <!--Optional: -->
    <maxRequestedBandwidthUL parameterName="$MAX_REQ_BAND_</pre>
UL">1000</maxRequestedBandwidthUL>
    <!--Optional: -->
    <maxRequestedBandwidthDL parameterName="$MAX_REQ_BAND_</pre>
DL">1000</maxRequestedBandwidthDL>
    <!--Optional: -->
    <minRequestedBandwidthUL parameterName="$MIN_REQ_BAND_</pre>
UL">10</minRequestedBandwidthUL>
    <!--Optional: -->
    <minRequestedBandwidthDL parameterName="$MIN_REQ_BAND_</pre>
UL">10</minRequestedBandwidthDL>
    <!--Optional: -->
    <flowStatus parameterName="$FLOW_STATUS">ENABLED</flowStatus>
    <!--Optional: -->
    <reservationPriority parameterName="$RES_PRI">0</reservationPriority>
```

```
<!--Optional: -->
    <rsBandwidth parameterName="$RS_BAND">1000</rsBandwidth>
    <!--Optional: -->
    <rRBandwidth parameterName="$RR_BAND">1000</rRBandwidth>
    <!--0 to 2 repetitions: -->
    <codecData parameterName="$CODEC_DATA">CODEC</codecData>
  </mediaComponentDescription>
  <!--Optional: -->
  <serviceInfoStatus parameterName="$SERV_INFO_STATUS">FINAL_SERVICE_
INFORMATION</serviceInfoStatus>
  <!--Optional: -->
  <chargingIdentifier parameterName="$CHG_ID">test_charging</chargingIdentifier>
 <!--Optional: -->
  <sIPForkingIndication parameterName="$SIP_FORK_IND">SINGLE_
DIALOGUE</sIPForkingIndication>
 <!--Zero or more repetitions: -->
 <subscriptionId>
    <subscriptionIdType parameterName="$SUB_ID_TYPE">END_USER_
E164</subscriptionIdType>
    <subscriptionIdData parameterName="$SUB_ID_</pre>
DATA">13693312888</subscriptionIdData>
  </subscriptionId>
  <!--Zero or more repetitions: -->
  <supportedFeatures>
    <vendorId parameterName="$VENDOR_ID">654321
    <featureListID parameterName="$FEATURE_LIST_ID">654320</featureListID>
    <featureList parameterName="$FEATURE_LIST">654322</featureList>
    <!--Zero or more repetitions: -->
    <avp name="test_supported_feature" description="test supported feature avp"</pre>
      code="688788" may-encrypt="true" mandatory-flag="required" vendor-id="87349"
     constrained="false">
      <grouped>
        <!--1 or more repetitions: -->
        <gavp name="grouped_avp" />
      </grouped>
      <avps name="avps_name" code="96785">
        <type type-name="String"/>
        <value parameterName="$customer_avps_name">xmf</value>
      </avps>
    </avp>
  </supportedFeatures>
  <!--Optional: -->
  <reservationPriority parameterName="$RESV_PRI">0</reservationPriority>
 <!--Optional: -->
  <framedIPAddress></framedIPAddress>
  <!--Optional: -->
  <framedIPv6Prefix></framedIPv6Prefix>
  <!--Optional: -->
  <calledStationId></calledStationId>
  <!--Optional: -->
  <serviceURN parameterName="$SERV_URN">sos.fire</serviceURN>
  <!--Optional: -->
  <sponsoredConnectivityData>
    <!--Optional: -->
    <sponsorIdentity parameterName="$SPON_ID">spon_id/sponsorIdentity>
    <!--Optional: -->
    <applicationServiceProviderIdentity</pre>
      parameterName="$SPON_APP_SERV_PROV_ID">spon_serv_prov_
id</applicationServiceProviderIdentity>
    <!--Optional: -->
```

```
<grantedServiceUnit>
      <!--Optional: -->
      <tariffTimeChange parameterName="$TARIF_TIME_CHG">1</tariffTimeChange>
      <!--Optional: -->
      <cCTime parameterName="$CC_TIME">60</cCTime>
      <!--Optional: -->
      <cCMoney>
        <unitValue parameterName="$UNIT_VAL">6.28</unitValue>
        <!--Optional: -->
        <currencyCode parameterName="$CUR_CODE">80</currencyCode>
      </cCMoney>
      <!--Optional: -->
      <cCTotalOctets parameterName="$CC_TOTAL_OCTS">1000000</cCTotalOctets>
      <!--Optional: -->
      <cCInputOctets parameterName="$CC_INPUT_OCTS">500000</cCInputOctets>
      <!--Optional: -->
      <cCOutputOctets parameterName="$CC_OUTPUT_OCTS">500000</cCOutputOctets>
      <!--Optional: -->
      <cCServiceSpecificUnits parameterName="$CC_SERV_SPEC_</pre>
UNIT">1</cCServiceSpecificUnits>
    </grantedServiceUnit>
  </sponsoredConnectivityData>
  <!--Optional: -->
  <mPSIdentifier parameterName="$MPS_ID">mps_id</mPSIdentifier>
  <!--Zero or more repetitions: -->
  <avp name="myRandomAVP" description="This is a sample AVP" code="93222"</pre>
may-encrypt="true" mandatory-flag="required" vendor-id="Oracle Corporation"
constrained="false">
    <type type-name="Integer32"/>
    <enum name="ENUM 1" code="0"/>
    <enum name="ENUM_2" code="1"/>
    <value parameterName="$ENUM_VAL">ENUM_1</value>
  </avp>
</QoSTemplate>
```

Modify QoS

The Modify QoS operation lets you modify the parameters of an existing QoS plan.

Authorization

Basic or OAuth 2.0

HTTP Method

PUT

URI

http://host:port/ApplicationQoSService/qos/\${requestId}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- requestId is a valid QoS request ID.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

To modify a QoS session, create a request body with the parameters you want changed. See the Apply QoS "Request Body" section for a complete listing of request body parameters.

Request Body Example

Example 16–11 shows an example of a modify QoS request body.

Example 16–11 Modify QoS Request Body

```
"qoSFeatureProperties": {
   "applicationIdentifier": "654321"
}
```

Response Header

For details on the response header, see the Apply QoS "Response Header" section.

Response Body

The response body contains an array of structures as the value for **actualProperties**. See "actualProperties" for complete details.

Response Body Example

Example 16–12 shows an example of a modify QoS response body.

Example 16–12 Modify QoS Response Body

```
"actualProperties": {
   "iPCANType": "_3GPP-GPRS",
   "rATType": "WLAN"
 }
}
```

Template-Based Modify QoS

The Template-based Modify QoS operation requests a modification to an existing template-based QoS plan.

Authorization

Basic or OAuth 2.0

HTTP Method

POST

URI

http://host:port/ApplicationQoSService/qos/\${requestId}/templatebased

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- requestId is a valid QoS request ID.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

To modify a template-based QoS session, create a request body with the parameters you want changed. See the Apply Template-based QoS "Request Body" section for a complete listing of request body parameters.

Request Body Example

Example 16–13 shows an example of a modify template-based QoS request body.

Example 16–13 Modify Template-Based QoS Request Body

```
"templateQoSFeatureProperties": {
 "parameter": [
      "name": "$FLOW_DESCRIPTION_0",
      "value": "permit out 8001 from assigned 34 to 24.2.1.6/18 8000"
 ]
}
```

Response Header

For details on the response header, see the Apply QoS "Response Header" section.

Response Body

See "actualProperties" for details on the response body parameters for a Modify Template-based QoS requests.

Response Body Example

Example 16–14 shows an example of a Modify Template-based QoS response body.

Example 16–14 Modify Template-Based QoS Response Body

```
"actualProperties": {
   "iPCANType": "_3GPP-GPRS",
   "rATType": "WLAN"
}
```

Get QoS Status

The Get QoS Status operation returns detailed information on the currently applied QoS plan.

Authorization

Basic or OAuth 2.0

HTTP Method

GET

URI

http://host:port/ApplicationQoSService/qos/\${requestId}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- requestId is a valid QoS session identifier.

Request Header

Standard header fields.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains an array of structures as the value for **qoSStatus**. Each element in the array contains values for the following parameters.

- userIsConnected. Boolean. True indicates a user is connected. False indicates a user is disconnected.
- actualProperties: Complex. Additional properties resulting from the request. See "actualProperties" for details on each of the actualProperties parameters.
- **qosFeatureProperties**: Complex. Additional properties resulting from the request. See the "Request Body" section of the "Apply QoS" operation for details on each of the qosFeatureProperties parameters.

Response Body Example

Example 16–15 shows an example of a QoS status response body.

Example 16-15 QoS Status Response Body

```
"qoSStatus": {
 "userIsConnected": true,
 "actualProperties": {
   "iPCANType": "_3GPP-GPRS",
   "rATType": "WLAN"
 },
  "gosFeatureProperties": {
    "duration": 3600,
    "applicationIdentifier": "654321",
    "mediaComponentDescription": [
        "mediaComponentNumber": 0,
        "mediaSubComponent": [
            "flowNumber": 1,
            "flowDescription": [
              "flow_1"
            ],
            "flowStatus": "ENABLED-UPLINK",
            "flowUsage": "NO_INFORMATION",
            "maxRequestedBandwidthUL": 100,
            "maxRequestedBandwidthDL": 500,
            "signallingProtocol": "NO_INFORMATION"
        ],
        "applicationIdentifier": "test_app_id",
        "mediaType": "VIDEO",
        "maxRequestedBandwidthUL": 200,
        "maxRequestedBandwidthDL": 1000,
        "minRequestedBandwidthUL": 10,
        "minRequestedBandwidthDL": 100,
        "flowStatus": "ENABLED",
        "reservationPriority": 1
      }
    ],
    "serviceInfoStatus": "FINAL_SERVICE_INFORMATION",
    "chargingIdentifier": "charging_id",
    "subscriptionId": [
     {
        "subscriptionIdType": "END_USER_E164",
        "subscriptionIdData": "88888888"
      }
   ],
    "framedIPAddress": "0A999899",
    "calledStationId": "EE-AA-CD-AF-09"
 }
```

Remove QoS

The Remove QoS operation removes a current QoS plan identified by a request ID.

Authorization

Basic or OAuth 2.0

HTTP Method

DELETE

URI

http://host:port/ApplicationQoSService/qos/\${requestId}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- requestId is a valid QoS session identifier.

Request Header

The MIME-type for the Content-Type header field is application/x-www-form-urlencoded.

Request Body

There is no request body.

Response Header

For details on the response header, see the Apply QoS "Response Header" section.

Response Body

There is no response body.

Register for QoS Notifications

The Register for QoS Notifications operation lets an application to register to receive QoS events. A QoS event notification is generated by a PCRF when an event is triggered for which an application has registered to receive notifications.

Table 16–2 shows the events an application can register to receive.

Table 16–2 QoS Event Types

Event Type	Trigger Condition
QOS_FEATURE_RELEASED	Triggered when the AF session times out. Controlled by the duration parameter in the QoS session request.
CHARGING_CORRELATION_EXCHANGE	If different Access Network Charging Information is applicable to the IP-CAN session, the PCRF will notify the AF about the Access Network Charging Information that applies to each authorized flow.
INDICATION_OF_LOSS_OF_BEARER	The server reports a loss of a bearer to the AF.
INDICATION_OF_RECOVERY_OF_ BEARER	The server reports a recovery of a bearer to the AF.
INDICATION_OF_RELEASE_OF_ BEARER	The server reports the release of a bearer to the AF.
IP_CAN_CHANGE	The server indicates a change in the IP-CAN type or RAT type (if the IP-CAN type is GPRS).
INDICATION_OF_OUT_OF_CREDIT	The PCRF reports to the AF that the SDFs have run out of credit and that the termination action determined by the finalUnitAction AVP applies.
INDICATION_OF_SUCCESSFUL_ RESOURCES_ALLOCATION	The PCRF reports that the requested resources have been successfully allocated.
INDICATION_OF_FAILED_ RESOURCES_ALLOCATION	The PCRF reports that the requested resources could not be successfully allocated.
INDICATION_OF_LIMITED_PCC_ DEPLOYMENT	The server reports limited PCC deployment—dynamically allocated resources are not available.
USAGE_REPORT	The PCRF reports accumulated usage volume when the usage threshold provided by the AF has been reached.

Authorization

Basic or OAuth 2.0

HTTP Method

POST

URI

http://host:port/ApplicationQoSNotification/registration

where:

host and port are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Apply QoS operation accepts the following parameters:

- reference: Complex. Required. Defines the application endpoint, interfaceName and correlator used to notify the application.
- endUserIdentities. Array. Required. Network end users to be monitored for events. An array of one or more end user IDs.
- eventCriteria. Array. Required. One or more events to be monitored. Events are specified by their numeric event ID. Table 16–3 shows the mapping of numeric event IDs to logical event IDs. For definitions of these events, see Table 16–2.

Table 16–3 Numeric to Logical QoS Event Mappin	Table 16–3	Numeric to Logical QoS Event Mapping
------------------------------------------------	------------	--------------------------------------

Numeric Event	Logical Event Name
1	CHARGING_CORRELATION_EXCHANGE
2	INDICATION_OF_LOSS_OF_BEARER
3	INDICATION_OF_RECOVERY_OF_BEARER
4	INDICATION_OF_RELEASE_OF_BEARER
6	IP-CAN_CHANGE
7	INDICATION_OF_OUT_OF_CREDIT
8	INDICATION_OF_SUCCESSFUL_RESOURCES_ALLOCATION
9	INDICATION_OF_FAILED_RESOURCES_ALLOCATION
10	INDICATION_OF_LIMITED_PCC_DEPLOYMENT
11	USAGE_REPORT
12	QOS_FEATURE_RELEASED

reference

These are the parameters for the reference parameter.

- **endpoint**: String. Required. The notification end point expected by the AF.
- **interfaceName**: String. Required. The interface name. Rarely used.
- **correlator**: String. Required. A unique ID for the message.

Request Body Example

Example 16–16 shows an example of a Register for QoS Notifications request body.

Example 16–16 Register for QoS Notifications Request Body

```
"startQoSNotification": {
 "reference": {
   "endpoint": "http://endpt_host:port/jaxrs/QoSNotification",
   "interfaceName": "interfaceName",
    "correlator": "987654321"
  "endUserIdentities": [
```

```
"tel:88888888", "tel:123456", "tel:234567"
   ],
   "eventCriteria": [
     "1", "2", "6", "7"
 }
}
```

Response header

For details on the response header, see the Apply QoS "Response Header" section.

Response Body

There is no response body.

Unregister for QoS Notifications

The Unregister for QoS Notifications operation requests that the server cease sending an application QoS notifications.

Authorization

Basic or OAuth 2.0

HTTP Method

DELETE

URI

http://host:port/ApplicationQoSNotification/registration/\${correlator}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- correlator is the unique identifier of the original notification request.

Request Header

The MIME-type for the Content-Type header field is application/x-www-form-urlencoded.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

QoS Event Notification

A QoS event notification is generated by a PCRF when an event is triggered for which an application has registered to receive notifications.

Authorization

Basic or OAuth 2.0

HTTP Method

POST

URI

http://host:port/QoSNotification

where:

host and port are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the QoS Event Notification operation accepts the following parameters:

- **correlator**: String. Required. The duration of the applied QoS in seconds.
- endUserIdentities. URI. Required. Identifies the service to which the application-facing service session belongs.
- eventType: Complex. Required. The valid routable IPv4 address that is applicable for the IP Flows toward the user equipment at the PCEF.
- subscriptionId: Complex. Optional. A valid full IPv6 address that is applicable to an IP flow or IP flows toward the user equipment at the PCEF.
- accessNetworkChargingIdentifier: Complex. Optional. Contains a charging identifier within the accessNetworkChargingIdentifierValue AVP along with information about the flows transported within the corresponding bearer within the flows AVP. If no flows AVP is provided, the accessNetworkChargingIdentifierValue applies to all flows within the AF session.

See "accessNetworkChargingIdentifier" for details on each of the accessNetworkChargingIdentifier parameters.

- accessNetworkChargingAddress: String. Optional. Indicates the IP address of the network entity that handles charging within the access network.
- iPCANType. Enumerated. Optional. Indicates the type of Connectivity Access Network (CAN) to which a user is connected. The CAN type is specified as one of the following:
 - 3GPP-GPRS
 - **DOCSIS**

- xDSL
- **WiMAX**
- 3GPP2
- 3GPP-EPS
- Non-3GPP-EPS
- rATType. Enumerated. Optional. Identifies the Radio Access Technology (RAT) that is servicing the user equipment. The RAT type is specified as one of the following:
 - **WLAN**
 - **VIRTUAL**
 - **UTRAN**
 - GERAN
 - **GAN**
 - HSPA_EVOLUTION
 - **EUTRAN**
 - CDMA2000_1X
 - **HRPD**
 - **UMB**
 - **EHRPD**
- flows: Complex. Indicates IP flows using their flow identifiers.

See "flows" for details on each of the flows parameters.

- abortCause. Enumerated. Optional. Determines the cause of an Abort Session Request (ASR) or of a Resource Access Restriction (RAR) indicating a bearer release. The abort cause is specified as one of the following:
 - BEARER_RELEASED
 - INSUFFICIENT_SERVER_RESOURCES
 - INSUFFICIENT_BEARER_RESOURCES
 - PS_TO_CS_HANDOVER
 - SPONSORED_DATA_CONNECTIVITY_DISALLOWED
- sponsoredConnectivityData: Complex. Optional. A set of AVPs that define which template parameters will be replaced and what the replacement values will be.

See "sponsoredConnectivityData" for details on each of the sponsoredConnectivityData parameters.

Request Example

Example 16–17 shows an example of a QoS Event Notification request body.

Example 16-17 Notify QoS Event Request Body

```
"notifyQoSEvent": {
 "correlator": "987654321",
 "eventType": 6,
```

```
"accessNetworkChargingAddress": "127.0.0.1",
   "iPCANType": "WiMAX",
   "rATType": "WLAN"
 }
}
```

Response header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

List QoS Event Notifications

The List QoS Event Notifications operation returns a list of QoS events that are registered either to a single correlator, if a correlator is specified in the request, or a complete list of registered events for all correlators if no correlator is specified.

Authorization

Basic or OAuth 2.0

HTTP Method

GET

URI

http://host:port/ApplicationQoSNotification/registration/[\${correlator}]

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- correlator is the optional unique identifier of the original notification request.

Request Header

Standard request headers.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body with No Correlator

The response body for the List QoS Event Notifications operation when an optional correlator parameter is specified, returns the following parameters:

correlators. Array. An array of correlators that are registered to receive QoS events.

Response Body Example

Example 16-18 shows an example of a List QoS Notifications response body when no correlator is specified in the request.

Example 16–18 List QoS Notifications Response Body Without a Correlator

```
"correlators": {
  "correlator": [
    "987654321", "12345676", "1272638"
}
```

}

Response Body with Optional Correlator

The response body for the List QoS Event operation when an optional correlator parameter is specified, returns the following parameters:

- reference: Complex. Defines the application endpoint, interfaceName and correlator used to notify the application. See "reference" for detailed information on the reference parameters.
- endUserIdentities: Array. Network end users to be monitored for events. An array of one or more end user IDs.
- eventCriteria: Array. One or more events to be monitored. Events are specified by their numeric event ID. Table 16–3 shows the mapping of numeric event IDs to logical event IDs. Table 16–2 lists these event IDs.

Table 16–4 Nu	ımeric to Logical	QoS Event	Mapping
---------------	-------------------	-----------	---------

Numeric Event	Logical Event Name
1	CHARGING_CORRELATION_EXCHANGE
2	INDICATION_OF_LOSS_OF_BEARER
3	INDICATION_OF_RECOVERY_OF_BEARER
4	INDICATION_OF_RELEASE_OF_BEARER
6	IP-CAN_CHANGE
7	INDICATION_OF_OUT_OF_CREDIT
8	INDICATION_OF_SUCCESSFUL_RESOURCES_ALLOCATION
9	INDICATION_OF_FAILED_RESOURCES_ALLOCATION
10	INDICATION_OF_LIMITED_PCC_DEPLOYMENT
11	USAGE_REPORT
12	QOS_FEATURE_RELEASED

reference

These are the parameters for the reference parameter.

- **endpoint**: String. The notification end point expected by the AF.
- **interfaceName**: String. The interface name. Rarely used.
- **correlator**: String. A unique ID for the message.

Response Body Example

Example 16–19 shows an example of a List QoS Notifications response body when a correlator is specified in the request.

Example 16–19 List QoS Notifications Response Body with Correlator

```
"startQoSNotification": {
 "reference": {
   "endpoint": "http://endpt_host:port/jaxrs/QoSNotification",
    "correlator": "987654321"
 },
  "endUserIdentities": [
```

```
"tel:8888888"
   ],
   "eventCriteria": [
     "6", "7", "1", "2"
 }
}
```

Adding RESTful Presence Support

This chapter describes the operations in the Presence interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Presence Interface

Applications use the RESTful Presence interface to act as either of two different parties to a presence interaction: as a presentity or as a watcher.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/presence/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

About Presentities and Watchers

A presentity agrees to have certain data (called attributes) such as current activity, available communication means, and contact addresses made available to others. As a presentity, an application can publish presence data about itself, check to see if any new watchers wish to subscribe to its presence data, authorize those watchers it chooses to authorize, block those it wishes not to have access, and get a list of currently subscribed watchers.

A watcher is the consumer of current activity, available communication means, and contact addresses made available by a presentity. As a watcher, an application can request to subscribe to all or a subset of a presentity's data, poll for that data, and start and end presence notifications.

Data Common to Operations in RESTful Presence Interface

This section describes the following parameters that are commonly used in the JSON data structures in RESTful Presence interface operations.

attributes

The attributes parameter is used to describe the current attributes of a presentity. It specifies the single Presence attribute or the set of Presence attributes that a watcher might wish to view for a specified presentity. It is used in the request body for

Subscribe Presence and Start Presence Notifications, the Request-URI query for Get User Presence and the response body for Get Open Subscriptions,

The following structure is used to specify the array of values for **attributes**:

```
"attributes": ["Activity|Place|Privacy|Sphere|Communication|Other"]
```

Each element of the array denotes a single Presence attribute and in turn, represented by a JSON attribute-value pair (or a JSON data object). An empty array indicates that the watcher is interested in all of the Presence attributes associated with a presentity.

presenceAttribute

The **presenceAttribute** parameter indicates the type of presentity data that must be updated or changed for the watcher. It is used in the request body for Update Subscription Authorization and in subscription notifications.

The values **presenceAttribute** accepts are specified in the following name/value pair structure:

"presenceAttribute": ["Activity|Place|Privacy|Sphere|Communication|Other"

unionElement

The unionElement parameter indicates the type of presentity data that is presented. It is used in the request body for Publish, the response body for Get User Presence and in notifications for a change in status.

The values **unionElement** accepts are specified in the following name/value pair structure:

"unionElement": ["Activity|Place|Privacy|Sphere|Communication|Other"

activity

The activity parameter specifies the presentity's current activity. It is one of the values accepted by attributes. The values activity accepts are specified in the following name/value pair structure:

```
"activity":
```

"ActivityNone | Available | Busy | DoNotDisturb | OnThePhone | Steering | Meeting | Away | Meal | PermanentAbsence | Holiday | Performance | InTransit | Travel | Sleeping | ActivityOther

where:

- **ActivityNone** indicates that the value has not been set.
- **ActivityOther** refers to any non-listed activity type.

place

The place parameter specifies the current type of location for a presentity. It is one of the values accepted by the **attributes** parameter. The values **place** accepts are specified in the following name/value pair structure:

```
"place":
```

"PlaceNone | Home | Office | PublicTransport | Street | Outdoors | PublicPlace | Hotel | Theatre | Restaurant | School | Industrial | Quiet | Noisy | Aircraft | Ship | Bus | Station | Mall | Airport | Train | PlaceOther"

where:

- **PlaceNone** indicates that the value has not been set.
- **PlaceOther** refers to any other type of place not listed here.

privacy

The **privacy** parameter specifies the level of privacy in the presentity's current environment. It is one of the values accepted by the attributes parameter. The values **privacy** accepts are specified in the following name/value pair structure:

"privacy": "PrivacyNone|PrivacyPublic|PrivacyPrivate|PrivacyQuiet|PrivacyOther"

where:

- **PrivacyNone** indicates that the value has not been set.
- **PrivacyOther** refers to any other level of privacy not listed here.

sphere

The **sphere** parameter specifies the sphere within which the presentity is currently acting. It is one of the values accepted by the attributes parameter. The values sphere accepts are specified in the following name/value pair structure:

```
"sphere": "SphereNone | SphereWork | SphereHome | SphereOther"
```

where:

- **SphereNone** indicates that the sphere has not been set.)
- **SphereOther** is used to refer to any other type of sphere not listed here.

type

The **type** parameter specifies the type of contact client for a specified or preferred form of communication. It is one of the values accepted by the means JSON data object. The values **type** accepts are specified in the following name/value pair structure:

```
"type": "Phone | Chat | Sms | Video | Web | Email | Mms | Means Other"
```

communication

The **communication** parameter specifies the connection information for a presentity's preferred form of communication. It is one of the values accepted by attributes, presenceAttribute and unionElement. It accepts only one value, means, specified in the following structure:

```
"communication": { "means": [{
      "contact": "URI",
      "priority": "Float",
       "type": "Phone | Chat | Sms | Video | Web | Email | Mms | MeansOther"
    }]
}
```

means

The **means** object specifies the parameters for the preferred form of communication. It accepts the following parameters:

- **contact**: String. Required. The contact address for this particular means or form of communications, as a URI.
- priority: Number (floating point). required parameter. The priority of this particular means. Valid entries start at 0.0 for the lowest priority and range in increasing order to 1.0 as the value for highest priority.
- type: Described earlier. See "type".

The following structure is used to specify the array of values for **means**:

```
"means": [{
      "contact": "URI",
      "priority": "Float"
      "type": "Phone | Chat | Sms | Video | Web | Email | Mms | MeansOther"
    }]
```

typeAndValue

The **typeAndValue** JSON object contains the presence information for a presentity. It is used in **Get User Presence** and **Publish** operations and in the Presence notifications. It is made up of the following parameters (each of which has been described earlier):

- unionElement: String. Required. See "unionElement".
- activity: String. Optional. Present if the value for unionElement is Activity. See "activity".
- place: String. Optional. Present if the value for unionElement is Place. See "place".
- privacy: String. Optional. Present if the value for unionElement is Privacy. See 'privacy".
- **sphere**: String. Optional. Present if the value for **unionElement** is **Sphere**. See "sphere".
- communication: JSON object. Optional. Present if the value for unionElement is Communication. See "communication".
- other: JSON object. Optional. See "other".

The following structure is used to specify the values for **typeAndValue**:

```
"typeAndValue": {
    "unionElement": "Activity | Place | Privacy | Sphere | Communication | Other",
"ActivityNone | Available | Busy | DoNotDisturb | OnThePhone | Steering | Meeting | Away | Meal |
PermanentAbsence | Holiday | Performance | InTransit | Travel | Sleeping | ActivityOther",
    "communication": {"means": [{
      "contact": "URI",
      "priority": "Float"
       "type": "Phone|Chat|Sms|Video|Web|Email|Mms|MeansOther"
    }]
}
```

other

The other JSON object specifies the parameters for arbitrary information. It has the following parameters:

- name: String. Required. The name for this specific information.
- value: String. Required. The specific value to be matched for the name.

The following structure is used to specify the values for **typeAndValue**:

```
"other": {
      "name": "String",
      "value": "String"
```

Get Open Subscriptions

The Get Open Subscription operation polls for any watchers who wish to subscribe to this presentity's data.

To retrieve the information on the applications, the **subscription?status=open** query string is included in the Request-URI of the GET method.

If the Get Open Subscription operation is successful, the response body contains the **result** JSON data object with the information on the watchers.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/presence/subscription?status=open

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- the subscription?status=open query string is used to retrieve any watchers who wish to subscribe to this presentity's data.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The information on the watchers is returned as an array of values for the **result** attribute. Each element in the array contains the following attribute-value pairs.

- application: String. Information only. A descriptive name for the application that operates on behalf of the watcher.
- attributes: String. The array of Presence attributes that the watcher wishes to see. See "attributes".
- watcher: String. The address (as a URI) of the watcher making the request.

The response body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"result": [{
 "application": "String",
 "attributes": ["Activity|Place|Privacy|Sphere|Communication|Other"],
 "watcher": "URI"
}]}
```

Get My Watchers

The Get My Watchers operation retrieves an array of current watchers.

To retrieve the information on the current watchers, include the subscription?filter=watcher query string in the Request-URI of the GET method.

If the Get My Watchers operation is successful, the response body contains the result JSON data object with the list of current watchers.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/presence/subscription?filter=watcher

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- the subscription?filter=watcher query string is used to retrieve the array of current watchers.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body contains a JSON data object as the value for the **result** entry. The value for result is an array of URIs which represent the addresses of the set of current watchers:

```
{"result": ["URI"]}
```

Update Subscription Authorization

The Update Subscription Authorization operation is used to add watchers who have recently asked for subscriptions or to change permissions for any current watchers.

To add watchers or change permissions, provide the address of the watcher along with the decision on whether permission must be granted, and the Presence attribute for which such permission must be granted (or revoked).

If the request fails, the Status-Line header field will contain the status code and the reason for the failure.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/presence/subscription/authorization

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Update Subscription Authorization operation accepts the following parameters:

- watcher: String. Required. The URI of the watcher.
- **decisions**: Array of JSON objects. Required. Each JSON object in the array contains the following parameters:
 - presence Attribute: String. Required. The specific Presence attribute for which permission is to be granted (to a new watcher) or permission must be changed (for the current watcher). See "presenceAttribute".
 - decision: Boolean. Required. If the value is true, permission is granted (to a new watcher) or permission is changed (for the current watcher).

The request body is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"decisions": [{
    "decision": "Boolean",
    "presenceAttribute": "Activity | Place | Privacy | Sphere | Communication | Other"
  }],
  "watcher": "URI"
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Subscribe Presence

The Subscribe Presence operation requests a subscription to a presentity's data. No data will be available until the presentity authorizes the watcher using Update Subscription Authorization.

To request a subscription to a presentity's data, provide the address of the presentity or group whose data is being requested, the Presence attributes this watcher wishes to see. Because the actual data depends on whether the subscription is authorized, a reference data object must also be provided in the request body. The reference object (also a JSON object) contains the correlator for the notification, the **endpoint** address (a specific Bayeux channel name) to which the notifications must be sent and, optionally, the interface name (a string to identify the notification).

If the request fails, the Status-Line header field will contain the status code and the reason for the failure.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/presence/subscription

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Subscribe Presence operation accepts the following parameters:

- **application**: String. Required. A descriptive name for the application whose data the watcher wishes to access. Informational only.
- presentity: a JSON object. Required. The address of the presentity whose data is requested (as a URI).
- attributes. An array of string values. Optional. The set of Presence attributes the watcher wishes to see. An empty array (or if this attribute is not present) indicates the watcher wishes to view all the attributes. For a description of the attributes, see "attributes".
- **reference**: JSON object. Required. Use this object to provide the following information about the endpoint that is to receive the notification:
 - **correlator**: String. Required. The correlator used to identify the notification.
 - **endpoint**: String. Required. The URI which represents the endpoint address to which the notification should be delivered. This string should be a Bayeux

protocol channel name that begins with /bayeux/appInstanceID where *appInstanceID* is the client application's application instance account ID.

For more information on managing application instances, see Services Gatekeeper Portal Developer's Guide.

interfaceName: String. Required. A descriptive string to identify the type of notification.

The request body is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"application": "String",
 "presentity": "URI",
 "reference": {
   "correlator": "String",
   "endpoint": "URI",
   "interfaceName": "String"
 "attributes": ["Activity|Place|Privacy|Sphere|Communication|Other"]
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Block Subscription

The Block Subscription operation allows a presentity to block a watcher's access to the presentity's data. The watcher is notified with a Subscription Ended notification.

To block a watcher's subscription to a presentity's data, provide the address of the watcher as a URI in the Request-URI of the DELETE method.

If the request fails, the Status-Line header field will contain the status code and the reason for the failure.

Authorization

Basic

HTTP Method

DELETE

URI

http://host:port/rest/presence/subscription/\${watcher}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- the *{{watcher}}* is the URI of the watcher who must be blocked from viewing this presentity's data.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Start Presence Notification

The Start Presence Notification operation begins delivering presence data to the endpoint defined in the reference attribute. This operation is only functional if the presentity has approved the watcher.

To set up for such notifications, provide the SIP-formatted URI of the presentity for which the watcher must receive notifications, the Presence attributes which will trigger the notifications and a reference object for the delivery of the notifications. The reference object (also a JSON object) contains the correlator for the notification, the endpoint address (a specific Bayeux channel name) to which the notifications must be sent and, optionally, the interface name (a string to identify the notification). Additionally, you can specify the request frequency, the total number of notifications and the duration for the notification and whether the check must start immediately.

If the Start Presence Notification request is successful, the endpoint address specified in the request body will receive a notification when:

- the presentity has authorized the watcher. See "Notification of Subscription to a Presentity's Data".
- the presentity's status changes. See "Notification of a Status Change for a Presentity".
- the notification limit or the specified duration has been reached. See "Notification Signalling End to Monitoring of Presentity".
- the subscription has been terminated or blocked by the presentity. See "Notification of End to a Subscription".

The application accesses the **endpoint** address to retrieve the specific notifications.

If there is any issue with subscriptions, the response body will contain the address(es) of the presentity (or presentities) to whose attributes the watcher did not successfully subscribe.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/presence/notification

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Start Presence Notification operation accepts following parameters:

- **presentity**: String. Required. The URI of a presentity or group whose data is being accessed.
- **checkImmediate**: String. Required. Boolean value ("true" or "false"). Set to:
 - **True**: The application requires the status notification to start immediately and as often as required thereafter.
 - False: The application requires the status notification to start at the end of the time period.
- **criteria**: String. Required. The status of the terminal. It can be one or all of the following:
 - Reachable
 - UnReachable
 - **Busy**
- frequency: JSON object. Required. This object specifies the frequency for checking the status (can also be considered minimum time between notifications). In the case of a group subscription, the service must make sure this frequency is not violated by notifications for various members of the group, especially in combination with **checkImmediate**. It takes the following parameters:
 - **metric**: String. Required. The unit of time for the check specified as Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - units. Integer. Required. The number of times the check must be made within the specified metric.
- reference. A ISON object. Required. Use this object to provide the following information about the endpoint that is to receive the notification:
 - **correlator**: String. Required. The correlator used to identify the notification.
 - endpoint: String. Required. The URI which represents the endpoint address to which the notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where *appInstanceID* is the client application's application instance account ID.
 - For more information on managing application instances, see Services Gatekeeper Portal Developer's Guide.
 - **interfaceName**: String. Required. A descriptive string to identify the type of notification.
- count. Integer. Required. The maximum number of notifications to be sent to the watcher. If this number is reached the statusEnd notification is delivered to the endpoint address.
- duration. A JSON object. Required. The total duration before for the count, specified by the following:
 - **metric**: String. Required. The unit of time for the notifications specified as Millisecond, Second, Minute, Hour, Day, Week, Month, or Year.
 - **units**. Integer. Required. The duration in the specified metric.

The request body is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"checkImmediate": "Boolean",
"frequency": {
```

```
"metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
    "units": "Integer"
 },
  "presentity": "URI",
  "reference": {
   "correlator": "String",
   "endpoint": "URI",
   "interfaceName": "String"
  "attributes": ["Activity|Place|Privacy|Sphere|Communication|Other"],
  "count": "Integer",
  "duration": {
    "metric": "Millisecond | Second | Minute | Hour | Day | Week | Month | Year",
   "units": "Integer"
 }
}
```

Response Header

The Location header field contains the URI of the publish/subscribe server:

```
http://host:port/rest/presence/notifications
```

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The requested information is returned in a JSON object as the value for the result attribute. It is an array of URIs which represent the addresses of the presentities to whose attributes the watcher did not successfully subscribe:

```
{"result": ["URI"]}
```

The actual notifications delivered to the **endpoint** address are described below.

Notification of Subscription to a Presentity's Data

The **notifySubscription** notification indicates whether the presentity has (or has not) authorized the watcher and the attributes that are permitted to be viewed.

The **notifySubscription** is a JSON object containing the following:

- presentity: String. The URI of the presentity who has (or has not) authorized the watcher to whom the notification is sent.
- decisions: Array of JSON objects. Required. Each JSON object in the array contains the following parameters:
 - presenceAttribute: String. Required. The specific Presence attribute for which permission is to be granted. See "presenceAttribute".
 - **decision**. Boolean. Required. If the value is **true**, permission is granted or permission is denied.

The subscription notification is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"notifySubscription": {
 "presentity": "URI",
 "decisions": [{
   "decision": "Boolean",
```

```
"presenceAttribute": "Activity | Place | Privacy | Sphere | Communication | Other"
  }]
}}
```

Notification of a Status Change for a Presentity

The **statusChanged** JSON object is delivered when there is a change to a specified attribute.

This object is sent to the Bayeux channel name associated with the application instance and specified in the request body as the endpoint attribute value.

The **statusChanged** is a nested JSON object containing the following:

- correlator: String. The correlator used to identify the notification and provided in the request body of the Start Presence Notification operation.
- **presentity**: String. The URI of the presentity associated with this data.
- changedAttributes. JSON object. Its value is an array of nested JSON objects and attributes which represent the aggregated presence data of the presentity. It contains the following:
 - lastChange: String. The date and time when this attribute was last changed in ISO 8601 extended format.
 - typeAndValue. JSON object. The presence information of the presentity. See "typeAndValue".
 - **note**: String. This optional entry is an explanatory note.

The notification for a status change is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"statusChanged": {
  "changedAttributes": [{
    "lastChange": "Calendar",
    "typeAndValue": {
       "unionElement": "Activity | Place | Privacy | Sphere | Communication | Other",
       "activity": "ActivityNone | Available | Busy | DoNotDisturb | OnThe Phone | Steering |
Meeting | Away | Meal | PermanentAbsence | Holiday | Performance | InTransit | Travel | Sleeping |
ActivityOther",
       "communication": {"means": [{
         "contact": "URI",
         "priority": "Float",
         "type": "Phone | Chat | Sms | Video | Web | Email | Mms | MeansOther"
      }]},
       "other": {
         "name": "String",
         "value": "String"
      },
       "place": "PlaceNone | Home | Office | PublicTransport | Street | Outdoors |
PublicPlace | Hotel | Theatre | Restaurant | School | Industrial | Quiet | Noisy | Aircraft | Ship |
Bus | Station | Mall | Airport | Train | PlaceOther",
       "privacy":
"PrivacyNone|PrivacyPublic|PrivacyPrivate|PrivacyQuiet|PrivacyOther",
      "sphere": "SphereNone | SphereWork | SphereHome | SphereOther"
    },
    "note": "String"
  }],
  "correlator": "String",
  "presentity": "URI"
```

}}

Notification Signalling End to Monitoring of Presentity

The statusEnd JSON object is delivered when the notification count specified as the value for **count** is reached or when the duration specified for **units** in the **duration** object is reached.

It is sent to the Bayeux channel name associated with the application instance and specified in the request body as the **endpoint** attribute value.

The **statusEnd** is a JSON object containing the following:

correlator: String. The correlator used to identify the notification and provided in the request body of the Start Presence Notification operation.

This notification is not delivered in the case of an error, or if the application ended the notification using **endNotification**.

The notification signalling the end of the monitoring of a presentity is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"statusEnd": {"correlator": "String"}}
```

Notification of End to a Subscription

The subscriptionEnded JSON object is delivered when the subscription has been terminated, either blocked by the presentity or because of a timeout or connection failure.

It is sent to the Bayeux channel name associated with the application instance and specified in the request body as the **endpoint** attribute value.

The **subscriptionEnded** is a JSON object containing the following:

- **presentity**: String. The URI of the presentity.
- reason: String. Required. The string indicates whether there was a timeout or the presentity blocked the watcher.

The notification signalling the end of the subscription to a presentity is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"subscriptionEnded": {
  "presentity": "URI",
  "reason": "String"
}}
```

End Presence Notification

The End Presence Notification operation stops a Presence notification.

To stop a previously set up Presence notification, provide the correlator for the notification passed earlier in the Start Presence Notification request.

There is no request or response body for the End Presence Notification operation. If the request fails, the body of the error response will contain the identifier for the notification and the type of exception.

Authorization

Basic

HTTP Method

DELETE

URI

http://host:port/rest/presence/notification/\${correlator}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- correlator is a string. It is the correlator for the notification provided in the reference object within the request body of the initial Start Presence Notification operation.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Get User Presence

The Get User Presence operation retrieves the aggregated presence data of a presentity to whose data the watcher has previously successfully subscribed. Only the attributes that the watcher is authorized to see are returned.

To retrieve the information, include the URI of the presentity and the required attributes as a data object in the query string of the Request-URI of the GET method.

If the Get User Presence operation is successful, the response body contains the result JSON data object with the aggregated presence data of the specified presentity.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/presence/data?filter=\${query}

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed. *\${query}* is a data object with the following parameters:

- presentity: String. Required. The URI of the presentity to whose data the watcher has previously successfully subscribed.
- attributes: Array of string values. Optional. The set of Presence attributes the watcher wishes to see. An empty array (or if this attribute is not present) indicates the watcher wishes to view all the attributes. For a description of the attributes, see "attributes".

The following JSON data structure represents this data object in the URI. The value part of each name/value pair indicates its data type:

```
"presentity": "URI",
  "attributes": ["Activity|Place|Privacy|Sphere|Communication|Other"]
}
```

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The requested information is returned in a JSON object as the value for the **result** attribute. It is an array of nested JSON objects and attributes which represent the aggregated presence data of a presentity. It contains the following:

- lastChange: String. The time and date the data last changed in ISO 8601 extended format.
- typeAndValue: JSON object. The presence information for a presentity (described earlier). See "typeAndValue".
- **note**: String. This optional entry is an explanatory note.

The response body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"result": [{
  "lastChange": "Calendar",
  "typeAndValue": {
    "unionElement": "Activity | Place | Privacy | Sphere | Communication | Other",
    "activity": "ActivityNone | Available | Busy | DoNotDisturb | OnThePhone | Steering
Meeting | Away | Meal | PermanentAbsence | Holiday | Performance | InTransit | Travel | Sleeping |
ActivityOther",
    "communication": {"means": [{
      "contact": "URI",
      "priority": "Float",
      "type": "Phone | Chat | Sms | Video | Web | Email | Mms | MeansOther"
    }]},
    "other": {
      "name": "String",
       "value": "String"
    },
    "place":
"PlaceNone | Home | Office | PublicTransport | Street | Outdoors | PublicPlace | Hotel | Theatre | R
estaurant | School | Industrial | Quiet | Noisy | Aircraft | Ship | Bus | Station | Mall | Airport | Tra
in PlaceOther",
    "privacy":
"PrivacyNone | PrivacyPublic | PrivacyPrivate | PrivacyQuiet | PrivacyOther",
    "sphere": "SphereNone | SphereWork | SphereHome | SphereOther"
  },
  "note": "String"
}]}
```

Publish

The Publish operation allows the presentity to publish presence information.

To publish the information, the request body contains the presence JSON data object with the aggregated presence data of the specified presentity.

If the request fails, the body of the error response will contain the identifier for the notification and the type of exception.

Authorization

Basic

HTTP Method

ייוזק

URI

http://host:port/rest/presence/data

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Publish operation is a nested data object. The value for presence attribute is an array of nested JSON structures which represent the aggregated presence data of a presentity. It accepts the following parameters:

- lastChange: String. The time and date the data last changed in ISO 8601 extended format.
- typeAndValue. JSON object. The presence information for a presentity (described earlier). See "typeAndValue".
- note: String. This optional entry is an explanatory note.

The request body for this operation is represented by the following ISON data structure, where the value part of each name/value pair indicates its data type:

```
{"presence": [{
  "lastChange": "Calendar",
  "typeAndValue": {
    "unionElement": "Activity | Place | Privacy | Sphere | Communication | Other",
    "activity": "ActivityNone | Available | Busy | DoNotDisturb | OnThePhone | Steering |
Meeting | Away | Meal | PermanentAbsence | Holiday | Performance | InTransit | Travel | Sleeping |
ActivityOther",
    "communication": {"means": [{
       "contact": "URI",
       "priority": "Float",
       "type": "Phone | Chat | Sms | Video | Web | Email | Mms | Means Other"
    }]},
     "other": {
       "name": "String",
```

```
"value": "String"
    },
    "place": "PlaceNone | Home | Office | PublicTransport | Street | Outdoors | PublicPlace |
Hotel | Theatre | Restaurant | School | Industrial | Quiet | Noisy | Aircraft | Ship | Bus | Station |
Mall | Airport | Train | PlaceOther",
    "privacy":
"PrivacyNone | PrivacyPublic | PrivacyPrivate | PrivacyQuiet | PrivacyOther",
    \verb"sphere": "SphereNone" | SphereWork | SphereHome | SphereOther"
  "note": "String"
}]}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Adding RESTful Device Capabilities Support

This chapter describes the operations in the Device Capabilities interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Device Capabilities Interface

Applications use the RESTful Device Capabilities interface to request and receive the a terminal's device ID (such as the IMEI) using **getDeviceID**, or receive the devices device ID type, name of the device/model, and a link to the User Agent Profile XML file using **getCapabilities**.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/device_capabilities/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Get Capabilities

The Get Capabilities operation retrieves the unique ID for the device type, name of the device/model, and a link to the User Agent Profile XML file.

The request includes the device ID of the device, usually a phone number.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/device_capabilities/device_ capabilities?capabilities=\${capabilities}

where:

- *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.
- *\${capabilities}* is a data object which contains the URI (usually, phone number) as the value of the **address** attribute.

The following JSON data structure represents this data object in the URI. The value part of each name/value pair indicates its data type:

```
{"address": "URI"}
```

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The requested device information is returned in a JSON object as the value for the result attribute. It contains the following name-value pairs.

- **deviceID**: String. The device/model number for the URI provided in the request.
- **name**: String. The name of the device.
- **userAgentProfileReference**: String. The link to the User Agent Profile XML file.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": {
  "deviceId": "String",
  "name": "String",
  "userAgentProfileReference": "URI"
}}
```

Examples

Example 18-1 Get Capabilities Request

```
GET rest/device_capabilities/device_capabilities?capabilities=%7B%22address%22
%3A%22tel%3A%221234%22%7D HTTP/1.1
X-Session-ID: app:5198750923966743997
Authorization: Basic YXBwX2luc3RhbmNlXzE6d2VibG9naWM=
User-Agent: Jakarta Commons-HttpClient/3.0
Host: servgtkpr_host.port
```

Example 18-2 Get Capabilities Response

```
HTTP/1.1 200 OK
Date: Fri, Nov 05 2010 05:23:27 GMT
Content-Length=124
Content-Type=application/json
X-Powered-By: Servlet/2.5 JSP/2.1
Host: servgtkpr_host.port
{"result":
     {
        "name": "alice.smith.uiii",
       "deviceId":"0998",
       "userAgentProfileReference": "#1234897897987867gihuyuijlkjlkjllk"
}
```

Example 18-3 Error Response

```
HTTP/1.1 500 Internal Server Error
Date: Fri, Nov 05 2010 05:32:27 GMT
Content-Length=131
Content-Type=application/json
X-Powered-By: Servlet/2.5 JSP/2.1
{"error":
        "message": "Invalid input for message part Address",
        "type": "org.csapi.schema.parlayx.common.v3_1.ServiceException",
}
```

Get Device Id

The Get Device Id operation retrieves the equipment identifier device/name (for example the IMEI number) for a given device. The request includes the device ID, usually a phone number.

The request includes the device ID of the device.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/device_capabilities/device_capabilities?deviceId=\${deviceId}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\${deviceId}* is a data object which contains the URI (usually, phone number) as the value of the **address** attribute.

The following JSON data structure represents this data object in the URI. The value part of each name/value pair indicates its data type:

```
{"result": "String"}
```

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The required equipment identifier device/name is returned as the value for the **result** attribute. The structure for the response body is

```
{"result": "String"}
```

Examples

Example 18-4 Get Device Id Request

```
GET rest/device_capabilities/device_capabilities?deviceId=%7B%22address%22%3A
%22tel%3A%221234%22%7D HTTP/1.1
X-Session-ID: app:5198750923966743997
Authorization: Basic YXBwX2luc3RhbmNlXzE6d2VibG9naWM=
User-Agent: Jakarta Commons-HttpClient/3.0
Host: servgtkpr_host.port
```

Example 18–5 Get Device Id Response

```
HTTP/1.1 200 OK
Date: Fri, Nov 05 2010 05:34:51 GMT
Content-Length=17
Content-Type=application/json
X-Powered-By: Servlet/2.5 JSP/2.1
Host: servgtkpr_host.port
{"result":"0998"}
```

Example 18-6 Error Response

```
HTTP/1.1 500 Internal Server Error
Date: Fri, Nov 05 2010 05:37:08 GMT
Content-Length=131
Content-Type=application/json
X-Powered-By: Servlet/2.5 JSP/2.1
{"error":
        "message": "Invalid input for message part Address",
        "type": "org.csapi.schema.parlayx.common.v3_1.ServiceException"
       }
}
```

Adding RESTful Binary Short Messaging Support

This chapter describes the operations in the Binary Short Messaging (Binary SMS) interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Binary Short Messaging Interface

Applications use the RESTful Binary Short Messaging interface to send any generic binary object attachments to the network using SMS. The supported binary content is broader than the logos and ringtones specified by the Parlay X SMS Web service, extending to other types of binary content such as vCards (a file format standard for electronic business cards).

These interfaces also provide operations to start and stop notifications for SMS messages with binary content.

REST Service Descriptions Available at Runtime

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at:

http://host:port/rest/binary_sms/index.html

Where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

RESTful Binary SMS Interface Reference

The RESTful Third Party Call interface includes these operations:

- Send Binary Sms
- Start Binary Sms Notification
- Stop Binary Sms Notification

Send Binary Sms

The Send Binary Sms operation sends an SMS that includes content in binary format.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/binary_sms/messages

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Send Binary Sms operation accepts the following parameters:

- addresses: String. Required. The set of end-user terminal addresses of the recipients as an array of SIP-formatted URIs.
- binaryMessage. An array of JSON objects. Required. The message to be sent as an array of User Data Header (UDH) elements and message elements. Note that the entire array must be less than of equal to 141 bytes.

Each element in the array contains:

- message. String in base64Binary. Binary Message data formatted as TP-User Data (TP-UD) excluding the TP-User-Data-Indicator (TP UDHI).
- udh. String in base64Binary. Specifies if the TP-User Data (TP-UD) field contains only the short message, or if it also contains the header formatted as the TP-User-Data-Indicator (TP UDHI).
- dcs: Byte. Required. The data-encoding scheme for the binaryMessage parameter.
- protocolId. Byte. Required. TP-Protocol-Identifier according to 3GPP 23.040 6.5.0
- charging. A JSON object. Optional. This object defines the cost charging properties for the operation. The entry "charging": null indicates no charge. If a charge is to be applied, provide values for the following in the **charging** object:
 - **description**: String. Required if the **charging** object is present in the body of the request. The text to be used for information and billing.
 - **amount**. Number (integer, or decimal). Optional. The amount to be charged.
 - **code**: String. Optional. The charging code, from an existing contractual description.
 - currency: String. Optional. The currency identifier as defined in ISO 4217 [9].

receiptRequest. a JSON object. Optional. Used to notify the application that the message has been delivered to the terminal, or that delivery is impossible.

If a delivery receipt is required, provide values for each of the following parameters which define this object:

- **correlator**: String. Used to correlate the receipt with the initial message.
- endpoint: String. The endpoint address (URI) to which the receipt must be delivered.
- **interfaceName**: String. A description provided to identify the type of receipt.
- **senderName**: String. Optional. The sender's name.
- validityPeriod: String. The validity period of the short message, formatted as a validity-period parameter as described in SMPP v3.4.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"addresses":["URI"],
  "binaryMessage":[{
   "message": "base64Binary"
   "udh": "base64Binary"
 }],
  "dcs": "Byte",
  "charging": {
   "description": "String",
   "amount": "BigDecimal",
    "code": "String",
    "currency": "String"
  "protocolId": "Byte",
  "receiptRequest": {
    "correlator": "String",
    "endpoint": "URI",
    "interfaceName": "String"
  },
  "senderName": "String",
  "validityPeriod": "String",
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body is a JSON object which contains the **result** attribute. The identifier for the delivery request is the string value for **result**.

```
{"result": "String"}
```

Start Binary Sms Notification

The Start Binary SMS Notification operation starts a notification for short messages that contain binary content.

Authorization

Basic

HTTP Method

PUT

URI

http://host:port/rest/binary_sms/notification

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

The request body for the Start Binary SMS Notification operation accepts the following parameters:

- smsServiceActivationNumber: String. Required. The destination address, as URI, of the short message.
- **reference.** JSON object. Required. Use this object to provide the following information about the endpoint that is to receive the notification:
 - **correlator**: String. Required. The correlator used to identify the notification.
 - endpoint: String. Required. The URI which represents the endpoint address to which the notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where *appInstanceID* is the client application's application instance account ID.
 - For more information on managing application instances, see Services *Gatekeeper Portal Developer's Guide.*
 - **interfaceName**: String. Required. A descriptive string to identify the type of notification.

The request body for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{
  "reference": {
   "correlator": "String",
   "endpoint": "URI",
   "interfaceName": "String"
  "smsServiceActivationNumber": "String",
}
```

Response Header

The Location header field contains the URI of the publish/subscribe server:

```
http://host:port/rest/binary_sms/notifications
```

If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body. The appropriate notifications (described below) are sent to the **endpoint** address provided by the application in the request body of this operation.

Notification of Binary SMS Reception

When a Binary SMS has been received for an application, its designated endpoint address on the publish/subscribe server receives a nested JSON object.

This nested JSON object contains the following as the value for the attribute notifyBinarySmsReception:

- **correlator**: String. The correlator used in the request body for this operation.
- message. a nested JSON object. It contains the data-encoding scheme for the set of messages in the notification, and the messages as an array of User Data Header (UDH) elements and message elements.
 - dcs. Byte. The data-encoding scheme for the binary messages included in this object.
 - message: Array of JSON objects. Table 19–1 lists the contents of each message object:

Table 19–1 Attributes of Message Object

Attribute	Description
message	Message data as a string base64Binary format
udh	Information specifying the message data format

- **senderAddress**: String. The sender's address, as a URI.
- smsServiceActivationNumber: String. The destination address for the binary message, as a URI.
- dateTime: String. The date and time the message was received in ISO 8601 extended format, yyyy-mm-ddThh-mm-ss.
- protocolId. Byte. The TP-Protocol-Identifier according to 3GPP 23.040 6.5.0.

The notification data object delivered to the **endpoint** address is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{"notifyBinarySmsReception": {
  "correlator": "String",
  "message":{
   "dcs": "Byte",
    "message":[{
        "message": "base64Binary"
        "udh": "base64Binary"
```

```
}],
  "senderAddress":"URI",
  "smsServiceActivationNumber": "URI",
  "dateTime": "Calendar"
  "protocolId": "Byte"
  }
}}
```

Stop Binary Sms Notification

The Stop Binary Sms Notification operation terminates a previously-started notification for messages that contain binary content.

To stop a previously set up binary Sms notification, provide the correlator for the notification passed earlier in the Start Binary Sms Notification request.

There is no request or response body for Stop Binary Sms Notification. If the request fails, the body of the error response will contain the identifier for the notification and the type of exception.

Authorization

Basic

HTTP Method

DELETE

URI

The Request-URI used in the DELETE method for Stop Sms Notification is:

http://host:port/rest/binary_sms/notification/\${correlator}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- correlator is the correlator for the notification provided in the **reference** object of the initial Start Binary Sms Notification request.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

There is no response body.

Adding RESTful Session Manager Support

This chapter describes the operations in the Session Manager interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Session Manager Interface

Applications use the RESTful Session Manager interface to get a unique session ID. Each application then adds this session ID to the header of all its requests. Services Gatekeeper uses this value to keep track of all the traffic that an application sends for the duration of the session, and to destroy a session.

The General Exception error will be thrown when any operation in the RESTful Session Manager interface fails.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/session_manager/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Get Session

The Get Session operation creates a session with an ID.

If the Get Session operation is successful, the response body will contain the session ID. This string value is used by the application in the X-Session-ID header of all subsequent traffic requests.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/session_manager/sessions

where *host* and *port* are the hostname and port of the system on which Services Gatekeeper is installed.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body is a JSON object containing the getSession Return attribute whose value is the session Id, returned as a string.

{ "getSessionReturn": "String" }

Get Session Remaining Lifetime

The Get Session Remaining Lifetime operation retrieves the time remaining in this session, in milliseconds.

The Request-URI for the GET method contains the session ID.

If the Get Session Remaining Lifetime operation is successful, the response body will contain the time remaining in this session, in milliseconds.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/session_manager/session/\${sessionId}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\${sessionID}* is the session ID obtained from the response to the Get Session request.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body is a JSON object containing the getSessionRemainingLifeTimeReturn attribute whose value is an integer representing the time remaining in this session, in milliseconds.

{ "getSessionRemainingLifeTimeReturn": "Integer" }

Destroy Session

The Destroy Session operation destroys this session.

To destroy a session, provide the appropriate session in the Request-URI for this operation. This identifier should have been obtained by the initial setup for this session.

There is no request or response body for Destroy Session. If the request fails, the body of the error response will contain the call identifier and the type of exception.

Authorization

Basic

HTTP Method

DELETE

URI

http://host:port/rest/session_manager/session/\${sessionId}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- sessionId is the session ID obtained from the response to the Get Session request.

Request Header

The MIME-type for the Content-Type header field is **application/json**.

Request Body

There is no request body.

Response Body

The response body is a JSON object containing the **destroySessionReturn** attribute whose value is a boolean.

```
{"destroySessionReturn": "Boolean"}
```

If the value for **destroySessionReturn** is **true**, the session was destroyed.

Adding RESTful Subscriber Profile Support

This chapter describes the operations in the Subscriber Profile interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the Subscriber Profile Interface

Applications use the RESTful Subscriber Profile interface to query an operator's database for individual subscriber profile attributes (such as a user's terminal type) or entire subscriber profiles.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/subscriber_profile/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Get

The GET operation retrieves specific subscriber profile properties. The properties that can be accessed are defined in the service provider and application SLAs associated with the application.

To retrieve specific subscriber profile properties, provide the address the subscriber and the required subscriber profile properties within the query object in the Request-URI of the GET method.

If this operation is successful, the response body contains a JSON data object with the required pathnames and values for the required profile properties associated with the specified subscriber.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/subscriber_profile/profile?query=\${query}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\${query}* is a JSON object.

The parameters accepted in the *\${query}* object are:

- address: String. Required. The address associated with the subscriber whose data is being accessed. The supported schemes are:
 - tel id
 - imsi (International Mobile Subscriber Identity)
 - IPv4
- pathNames: Array of String values. Required. The requested subscriber profile properties expressed as a relative UNIX path. For example, serviceName/accessControlId/accessControlId

The *\${query}* object in the URI is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"address": "URI",
"pathNames":["String"]
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body is a JSON object which contains the requested properties as an array value for the **properties** attribute. Each element in the array contains the following:

- pathName: String. The pathname for the requested property.
- **propertyValue**: String. The value associated with the requested property.

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"properties": [{
  "pathName": "String",
  "propertyValue": "String"
}]}
```

Get Profile

The GET Profile operation retrieves the entire profile for a specific subscriber.

To retrieve the entire profile for a specific subscriber, provide the associated subscriber Id and profile ID within the query object in the Request-URI of the GET method.

If Get Profile is successful, the response body contains a JSON data object with the required pathnames and values for all the profile properties associated with the specified subscriber.

Authorization

Basic

HTTP Method

GET

URI

http://host:port/rest/subscriber_profile/profile?id=\${id}

where:

- host and port are the host name and port of the system on which Services Gatekeeper is installed.
- *\${id}* is a JSON object.

The parameters accepted by \${id} object are:

- **profileID**: String. Required. The ID of the profile which acts as a set of filters limiting the attributes that can be accessed based on the SLAs associated with the application. This entry may be ignored if Services Gatekeeper connects to the network using certain protocols.
- **subscriberID**: String. Required. The ID that uniquely identifies the subscriber whose profile is being accessed.

The \$\{id\}\) object in the URI is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
"profileID": "a_profileId", }
   "subscriberID": "a_subsc_id"
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body is a JSON object which contains the requested properties as an array value for the **result** attribute. Each element in the array contains the following:

- pathName: String. The pathname for the requested property.
- propertyValue: String. The value associated with the requested property.

Here is the structure:

```
{"result": [{
 "pathName": "String",
  "propertyValue": "String"
}]}
```

Adding RESTful WAP Push Support

This chapter describes the operations in the WAP Push interface of the RESTful facade provided in Oracle Communications Services Gatekeeper.

About the WAP Push Interface

Applications use the RESTful WAP Push interface to send a Wireless Application Protocol (WAP) Push message. The content of the message is coded as a Password Authentication Protocol (PAP) message.

The message payload must adhere to the following:

- WAP Service Indication Specification, as specified in Service Indication Version 31-July-2001, Wireless Application Protocol WAP-167-ServiceInd-20010731-a.
- WAP Service Loading Specification, as specified in Service Loading Version 31-Jul-2001, Wireless Application Protocol WAP-168-ServiceLoad-20010731-a.
- WAP Cache Operation Specification, as specified in Cache Operation Version 31-Jul-2001, Wireless Application Protocol WAP-175-CacheOp-20010731-a.

For links to the specifications, see:

http://www.openmobilealliance.org/tech/affiliates/wap/wapindex.html.

The actual message is sent as an HTTP attachment. See "Headers for Multipart Messages with Attachments" for more information.

REST Service Descriptions Available at Run-time

When the Administration Server for your Services Gatekeeper domain is in the running state, the REST service descriptions of these operations can be found at

http://host:port/rest/push_message/index.html

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Send Push Message

The Send Push Message operation sends a WAP Push message.

Authorization

Basic

HTTP Method

POST

URI

http://host:port/rest/push_message/messages

where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Request Header

The request headers depend on the type of message:

- If the message content is in the form of an attachment, the request will be multipart and the request header must contain the header fields that describe the parts of the message.
- If the message does not contain an attachment, the special headers associated with the multipart messaged are not used.

Message Part Content

The message part content for this operation accepts the following parameters:

- **destinationAddresses**: String. Required. An array of terminal addresses.
 - Each of the addresses in this array should be formatted according to the Push Proxy Gateway Service Specification (WAP-249-PPGService-20010713-a).
- **pushId**: String. Required. A unique identifier provided by the application. Supported types are PLMN and USER.
- replaceMethod: String. Required. Valid entries are:

 - pendingOnly

replaceMethod is used in conjunction with the **pushId** parameter and defines how to replace a previously sent message. This entry will be ignored if replacePushId is NULL.

- **requesterId**: String. Required. The application ID as given by the operator.
- **serviceCode**: String. Required. A code for charging purposes.
- additionalProperties. An array of JSON objects. Optional.

Each element in the array is a JSON object used to add additional properties with the following parameters:

- name: String. Required if the additional Properties object is present. Valid entries include pap.priority, pap.delivery-method, pap.network-required, pap.bearer, and pap.bearer-required.
- value: String. Required if the additional Properties object is present. The value associated with the property.
- deliverAfterTimeStamp: String. Optional. The date and time after which the content should be delivered to the wireless device. This entry is in ISO 8601 extended format, as yyyy-mm-ddThh-mm-ss.
 - If the network does not support this parameter, this entry will be rejected.
- **deliverBeforeTimeStamp**: String. Optional. The date and time by when the content should be delivered to the wireless device. This entry is in ISO 8601 extended format, as yyyy-mm-ddThh-mm-ss.
 - If the network does not support this parameter, this entry will be rejected.
- **progressNoteRequested**. Boolean. Optional. If **true**, the application wishes to receive progress notes at the address specified by the **resultNotificationEndpoint**.
- **replacePushId**: String. Optional. The Push Id of the message that is to be replaced. If it is set to NULL, the message is treated as a new message. If it is set to a valid ID, message replacement will occur for all currently pending messages. Messages that have already been delivered cannot be canceled, and therefore cannot.
 - Messages that have already been delivered cannot be canceled, and therefore cannot be replaced
- resultNotificationEndpoint: String. Optional. The URI which represents the endpoint address to which the notification should be delivered. This string should be a Bayeux protocol channel name that begins with /bayeux/appInstanceID where *applnstanceID* is the client application's application instance account ID.
 - If the application does not wish to receive notifications, this value should be NULL.
- **sourceReference**: String. Optional. The name of the service provider.

The message part content for this operation is represented by the following JSON data structure, where the value part of each name/value pair indicates its data type:

```
{
  "destinationAddresses": ["String"],
  "pushId": "String",
  "replaceMethod": "all pending-only",
  "requesterID": "String",
  "serviceCode": "String",
  "additionalProperties": [{
   "name": "String",
    "value": "String"
  "deliverAfterTimestamp": "Calendar",
  "deliverBeforeTimestamp": "Calendar",
  "progressNotesRequested": "Boolean",
  "replacePushId": "String",
  "resultNotificationEndpoint": "URI",
  "sourceReference": "String"
}
```

Response Header

Standard header fields. If the request fails, the Status-Line header field will contain the status code and the reason for the failure. See "Understanding RESTful Errors and Exceptions".

Response Body

The response body is a nested JSON object. It contains the **result** attribute with the following attributes and data objects:

- pushId: String. Required. A unique identifier provided by the application. Supported types are PLMN and USER.
- result: JSON object. This object contains the outcome code. It contains the following two entries:
 - **code**: String. The outcome code generated by the network node. Table 22–1 lists the possible values.
 - description: String. The textual description for the code.
- additionalProperties: An array of JSON objects used to add additional properties.

Each element in the array is a JSON object with the following parameters:

- name: String. The name of an additional property. One of: pap.stage, pap.note, pap.time.
- **value**: String. The value associated with the property.
- replyTime: String. The date and time for the reply in ISO 8601 extended format, as yyyy-mm-ddThh-mm-ss.
- senderAddress: String. Optional. The sender's address.
- **senderName**: String. Optional. The sender's name.

Table 22-1 Possible Outcome Codes

Code	Description		
1000	OK		
1001	Accepted for processing		
2000	Bad request		
2001	Forbidden		
2002	Address error		
2003	Address not found		
2004	Push ID not found		
2005	Capabilities mismatch		
2006	Required capabilities not supported		
2007	Duplicate Push ID		
2008	Cancellation not possible		
3000	Internal server error		
3001	Not implemented		
3002	Version not supported		
3003	Not possible		

Table 22-1 (Cont.) Possible Outcome Codes

Code	Description
3004	Capability matching not possible
3005	Multiple addresses not supported
3006	Transformation failure
3007	Specified delivery method not possible
3008	Capabilities not available
3009	Required network not available
3010	Required bearer not available
3011	Replacement not supported
4000	Service failure
4001	Service unavailable

The response body for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"result": {
  "pushId": "String",
  "result": {
   "code": "String",
   "description": "String"
  "additionalProperties": [{
   "name": "String",
   "value": "String"
  "replyTime": "Calendar",
  "senderAddress": "String",
  "senderName": "String"
```

Result Notification Message Object

The resultNotificationMessage object delivered to the resultNotificationEndpoint address is a nested JSON object containing the following entries:

- address: String. The address of the terminal to which this message is sent.
- code: String. The final state of the message, one of the values listed in Table 22–1.
- messageState: String. The state of the message. One of:
 - rejected
 - pending
 - delivered
 - undelivered
 - expired
 - aborted
 - timeout
 - cancelled

- unknown
- pushId: String. The unique identifier defined in the initial request, used for
- additional Properties. An array of JSON objects used to add additional properties. Each element in the array is a JSON object with the following parameters:
 - name: String. The name of an additional property, dependent on the network
 - node. One of: pap.priority, pap.delivery-method, pap.network-required, pap.bearer, and pap.bearer-required.
 - **value**: String. The value associated with the property.
- **description**: String. A description of the notification provided by the network. (May not be provided).
- eventTime: String. The date and time the message reached the destination in ISO 8601 extended format, as yyyy-mm-ddThh-mm-ss.
- receivedTime: String. The date and time the message was received at the network node in ISO 8601 extended format, as yyyy-mm-ddThh-mm-ss.
- senderAddress: String. Optional. The sender's address.
- **senderName**: String. Optional. The sender's name.

The notification of the result for this operation is represented by the following JSON data structure, where the value part of the name/value pair indicates its data type:

```
{"resultNotificationMessage": {
  "address": "String",
  "code": "String",
  "messageState":
"rejected|pending|delivered|undeliverable|expired|aborted|timeout|cancelled|unknow
  "pushId": "String",
  "additionalProperties": [{
   "name": "String",
    "value": "String"
  "description": "String",
  "eventTime": "Calendar",
  "receivedTime": "Calendar",
  "senderAddress": "String",
  "senderName": "String"
}}
```

Part III

Creating Applications Using the OneAPI RESTful Interfaces

Part III describes how to use the interfaces in the OneAPI facade to create applications that interact with Oracle Communications Services Gatekeeper.

Part III contains the following chapters:

Using the OneAPI RESTful Interfaces

Also see these chapters in *Services Gatekeeper Communication Service Reference Guide* for details on using the OneAPI-based interfaces:

- OneAPI Multimedia Messaging/MM7
- OneAPI Payment/Diameter
- OneAPI Terminal Location/MLP
- OneAPI Short Messaging/SMPP

Using the OneAPI RESTful Interfaces

This chapter provides an overview of how the Oracle Communications Services Gatekeeper RESTful Web services work with OneAPI operations, and how you can use this functionality to interact with Services Gatekeeper.

About the OneAPI Facade Architecture

OneAPI operations are processed by the same network-facing interfaces that are used by the Services Gatekeeper RESTful facade for supported services.

For more information on communication services, see Services Gatekeeper Communication Service Reference Guide.

Services Gatekeeper supports OneAPI operations by complying with industry specifications published by the GSMA and the Parlay Group. Services Gatekeeper uses an implementation of Oracle's JSR 311 Jersey Java API for RESTful Web services (JAX-RS) to facilitate communication between applications and network nodes.

See the discussion on OneAPI service facades in Services Gatekeeper Statement of *Compliance* for the specifications supported.

For information about Oracle JAX-RS, see the Oracle Fusion Middleware documentation website:

http://docs.oracle.com/middleware/1213/index.html

For information about JSR 311, see the GlassFish website:

http://jsr311.java.net

The supported OneAPI services include:

- Multimedia messaging support
- Payment support
- Short Messaging support
- Terminal location support

Support for Anonymous Customer References


Services Gatekeeper supports the use of Anonymous Customer References (ACRs) for all of the supported OneAPI services it supports. See "Adding RESTful Anonymous Customer Reference Support" for more information on the RESTFUL APIs.

Also see Services Gatekeeper Statement of Compliance for a link to the supported specification.

Components of the RESTful Facade

Figure 23–1 shows the multiple components of the Services Gatekeeper Access Tier (AT) RESTful facade.

Figure 23-1 RESTful Facade



Network-facing (application-initiated) requests are received by the RESTful Servlet and then directed to the RESTful handler chain in preparation for delivery by the JAX-RS. The JAX-RS communicates the RESTful requests to the appropriate service enabler for execution at the network tier by the correct Service Enabler Enterprise JavaBean (EJB). Communication between the network-triggered traffic and applications is handled by the same modules in reverse.

See Services Gatekeeper Communication Service Reference Guide for information on service enablers.

A Web Application Description Language (WADL) file generates the JAX-RS resource classes used by a communication service to translate between the RESTful request for delivery and the appropriate EJB. For information on WADL, see:

http://wadl.java.net

For information on creating communication services from WADL files, see the discussion on Using Services Gatekeeper with REST Services in Services Gatekeeper Extension Developer's Guide.

Supported OneAPI Interfaces

Services Gatekeeper supports the following OneAPI Interfaces:

- **SMS**
- **MMS**
- Terminal Location
- **Payment**

There are a number of communication services for which OneAPI does not provide a standard interface. Services Gatekeeper supports these services using the proprietary RESTful interface. See "Creating Applications Using the RESTful Interfaces" for a complete list of supported services is available

The GSMA provides application developers OneAPI specifications for using these services when interacting with a OneAPI server. Services Gatekeeper, acting as a OneAPI server, provides response messages to operations as specified by the OneAPI specification.

SMS

Applications use the OneAPI RESTful Short Messaging interface (wlng_nt_sms_ px21.ear) over SMPP to send and receive SMS messages, to fetch SMSs and delivery status reports, and to start and stop a notification.

When the request body for an SMS operation contains a request for a delivery receipt, the application provides a correlator for the message being sent and includes an endpoint address for returning the delivery notification.

See "OneAPI Short Messaging/SMPP" for a complete description of the OneAPI RESTful SMS interface.

MMS

Applications use the OneAPI RESTful Multimedia Messaging interface over MM7 (wlng_nt_multimedia_messaging_px21.ear) to send a multimedia message (MMS message) and to fetch information on MMS messages that have been received for the applications and stored by Services Gatekeeper.

Applications use the interface to fetch those messages, get delivery status on sent messages, and start and stop a notification.

See "OneAPI Multimedia Messaging/MLP" for a complete description of the OneAPI RESTful MMS interface, including example operations.

Terminal Location

Applications use the OneAPI RESTful Terminal Location interface over MLP (wlng_ **nt_terminal_location_px21.ear**) to get a location for an individual terminal or a group of terminals.

See "OneAPI Terminal Location/MLP" for a complete description of the OneAPI RESTful Location interface, including example operations.

Payment

Applications use the OneAPI RESTful Payment interface over Diameter Ro (wlng_nt_ sms_px21.ear) to charge an amount to an end-user's account, refund amounts to that account, query charge amount status and list charge amount transactions. Applications can also reserve amounts, reserve additional amounts, charge against the reservation and release the reservation.

See "OneAPI Payment/Diameter" for a complete description of the OneAPI RESTful Location interfaces.

About Configuring OneAPI Server Functionality

The Services Gatekeeper OneAPI server functionality is embedded in the Parlay X plug-in, which is installed and deployed by default. No additional OneAPI configuration is necessary.

General Format of an Operation

The following basic elements are present in the requests that an application makes to the OneAPI RESTful interfaces facade, to the responses it receives from the interfaces facade, or to both:

- Request-URI and HTTP Methods in requests and Status-Line in responses
- Headers
- Message Body
- Attachments

Request-URI and HTTP Methods

Applications use one of four methods, "GET", "POST", "PUT", or "DELETE", to request that a required action be performed on an abstract or physical resource, which is identified by a Uniform Resource Identifier (URI). The Request-URI is therefore the most important part of any request that an application makes to the RESTful interfaces.

Here is an example of the OneAPI POST method used to send an SMS message. The request URI is contained in the first line of the example.

```
POST http://example.com/oneapi/1/smsmessaging/outbound/tel%3A%2B5550100/requests
HTTP/1.1
Host: example.com:80
Content-Type: application/x-www-form-urlencoded
Accept: application/json
address=tel%3A%2B15415550100&
address=tel%3A %2B15415550101&
senderAddress=tel: %2B5550100&
message=Hello%20World&
clientCorrelator=123456&
notifyURL=http://application.example.com/notifications/DeliveryInfoNotification&
callbackData=some-data-useful-to-the-requester&
senderName=ACME%20Inc.
```

See "OneAPI Short Messaging/SMPP" for information on the parameters used in this example request.

General Format of a Request-URI

A fully qualified OneAPI Request-URI is made up of a sequence of sections, concatenated as:

http://host:port/oneapi/api_version/service/service_specific_sections

where.

- host:port: The hostname and port number of your Services Gatekeeper OneAPI installation; for example, 127.0.0.1 and 8001.
- *api_version*: The version of the OneAPI interface deployed. In Services Gatekeeper, the current api version is always 1.
- service: The communication service required by the method. For example, smsmessaging.

service_specific_sections: One or more sections required by the OneAPI specification for the method called. See the examples provided in subsequent OneAPI chapters about specific services.

POST

The POST method accesses a resource factory to create a resource that does not yet have a URI. Multiple requests to a resource factory can create multiple new resources.

The following statement sets up a subscription to SMS delivery notifications:

POST http://example.com/oneapi/1/smsmessaging/outbound/tel%3A%2B5550100/ subscriptions HTTP/1.1

For the POST method:

- The URI in the request represents the factory resource that is accessed to create a resource. In the above example, /smsmessaging/outbound/tel%3A%2B5550100/subscriptions is the factory resource accessed to create a resource.
- The request body contains the information required to create the resource.
- If the resource is created, the response body will contain the identifier for the new resource. If the operation fails, the response body will contain the error response.

PUT

The PUT method creates a resource that has a predetermined URI. This method can be used to update a resource or to start a stateful process. For example, an application uses the following statement to release a payment reservation:

PUT http://example.com/oneapi/1/payment/tel%3A%2B5550100/transactions/ amountReservation/abc123

For the PUT method:

- The URI in the request represents the resource to update or to start a stateful process on. In the example,
 - /tel%3A%2B5550100/transactions/amountReservation/abc123 represents the resource accessed to release the payment reservation.
- The request body for this operation contains the required information. The JSON object will contain, for example, information on the description and amount of the reservation to release.
- If the operation fails, the response body contains the error response.

GET

The GET method retrieves the state of a specific resource that has been previously created. The specific resource is identified in the query string. For example, this statement can be used by an application to retrieve the location of a terminal whose address is "tel&3A%2B15415550100"::

GET http://example.com/oneapi/1/location/queries/location?&address=tel& 3A%2B15415550100&requestedAccuracy=1000

For the GET method:

The URI in the request represents the query string that uniquely identifies the resource whose status the application wishes to retrieve. In the example, the value for (location?&address) is the unique address of the terminal. (It is the address of the terminal, {"address": "tel:15415550100", } in JSON representation).

- The request body for this operation is empty.
- The response provides information on the location of the resource with an accuracy of 1000 meters. If the operation fails, it contain the error response.

In order to complete the operation, the application must access the specified location and use the correlator to retrieve the notification.

DELETE

The DELETE method removes a specified resource. The application provides the correlator or the identifier for the resource to be removed in the Request-URI. An application stops SMS delivery notifications with the following request:

DELETE http://example.com/oneapi/1/smsmessaging/outbound/subscriptions/abc123

For the DELETE method:

- The URI in the request contains the correlator, which is a value that uniquely identifies the resource the application wishes to remove. In the example, abc123 is the value which the application provided as the correlator when it requested notifications on a terminal's status.
- The request body for this operation is empty.
- The response body is either empty, or contains the error response if the operation fails.

Headers

The requests and responses for RESTful operations include the following header fields:

Authorization: The Authorization header field is a required field and is found in all requests. It indicates the type of authentication and security. For example:

```
Authorization: Basic QWxhZGRpbjpvcGVuIHNlc2FtZQ==
```

See "Authentication and Security" for more information.

Accept: OneAPI only supports JSON as the response format. For example:

```
Accept: application/json
```

- Location: Certain requests include location headers. They identify a new resource or redirect the recipient to a location other than the Request-URI to complete the request.
- Content-Length: Specifies the length of the request (or response) body.
- Content-Type: The MIME-type value for the Content-Type header field may be multipart/form-data, application/json, application/x-www-form-urlencoded or application/xml.

The **multipart/form-data** value for the Content-Type header field is described in the next section.

X-Session-ID: A session ID is required if transaction sessions are used.

Headers for Multipart Messages with Attachments

The OneAPI RESTful-based communication services for Multimedia Messaging use HTTP attachments to transport their content. The OneAPI MMS interface supports multipart/form-data POST requests. When you use RESTful interfaces with the base Services Gatekeeper product, multiple attachments are supported in both application-initiated and network-triggered messages.

When a request message contains one or more messages embedded within it, a specified boundary is placed between the parts of the message and at the beginning and end of the message. For multipart message requests:

- The MIME-type value for the Content-Type header field may be multipart/form-data or application/json. If the MIME-type value for the Content-Type header field is **multipart/form-data**, the **boundary** entry is used to provide a value for the boundary between the message parts.
- Each message part contains the following:
 - Content-Disposition header field whose value is form-data and contains a **name** attribute with the appropriate value. For example, the message part name is **messagePart**. For Multimedia Messages the attribute is **attachments**. Multimedia messages contain an additional filename attribute and value.
 - Content-Type header field whose value describes the data format included in the message part.
 - Content-Transfer-Encoding field with the appropriate value, if needed.
- If the content of the message is pure ASCII, the response body contains the message. Otherwise, the response body contains an identifier that is used to fetch the message.

Example 23-1 Example of a Multipart Message Request

```
POST http://example.com/oneapi/1/messaging/outbound/ tel%3A%2B5550100/requests
HTTP/1.1
Content-Length: 12345
Content-Type: multipart/form-data;
boundary="========123456==";
MIME-Version: 1.0
Host: www.example.com
Date: Thu, 04 Jun 2009 02:51:59 GMT
--========123456==
Content-Disposition: form-data; name="root-fields"
Content-Type: application/x-www-form-urlencoded;
address=tel%3A%2B15415550100&
address=tel%3A%2B15415550101&
senderAddress=tel:%2B5550100&
&senderName=ExampleSender
Subject=My%20message&
notifyURL=http://example-application.com/notifications/DeliveryInfoNotification
/54311
&callbackData=
&clientCorrelator=123456
--==========123456==
Content-Disposition: form-data; name="attachments"; filename="picture.jpg"
Content-Type: image/gif
GIF89a...binary image data...
```

--===========123456==-

Status Line

The Status Line is the first line in any response that an application receives when it interacts with the OneAPI RESTful services interface in Services Gatekeeper. It takes the form:

HTTP/1.1 status_code reason_phrase

where:

- status_code is a three-digit number that indicates the success or failure to fulfill the
- reason_phrase is a brief description of the successful action performed; or the reason for the failure.

For example:

HTTP/1.1 201 Created

Table 23–1 lists some of the status codes and reason-phrases commonly encountered when interacting with the Services Gatekeeper OneAPI RESTful interfaces:

Table 23-1 A Sampling of Status Codes and Reason Phrases

Status Code	Reason Phrase	Description		
200	OK	Success		
201	Created	Success: The requested resource was created.		
204	No Content	Success		
400	Bad Request	The request cannot be processed. Check the error message for details.		
401	Authentication failure	The authentication to the protected resource failed. Check your Services Gatekeeper OneAPI authentication requirements.		
403	Forbidden	The authentication credentials provided in the request are not valid.		
404	Not found	The resource specified in the URI cannot be found.		
405	Method not supported	The method requested is not supported by the service.		
501	Internal Server Error	Failure: An unexpected condition prevented the server from fulfilling the request.		
503	Server busy and service unavailable. Please retry the request.	The server hosting Services Gatekeeper OneAPI RESTful interface is busy.		

The Status-Codes used by OneAPI and supported by Services Gatekeeper conform to Internet Engineering Task Force (IETF) standards. For a complete listing of the HTTP status codes and their definitions, see RFC 2616 on the IETF website:

http://www.ietf.org/rfc/rfc2616.txt

Message Body

Request or response message bodies are only present if required. A message body is a ISON object.

Request Body

When present, the request body provides additional data required to complete the specific request. The following request body for an example Send SMS operation provides the addresses of the recipients and sending party, and the message text:

Example 23-2 Send SMS Request

```
address=tel%3A%2B15415550100&
address=tel%3A %2B15415550101&
senderAddress=tel:%2B5550100&
message=Hello%20World&
```

Response Body

When present, the response body provides data that the application needs for later action. Example 23–3 shows a response body for the Send SMS operation; it provides the application with the URI for the sent message.

Example 23-3 Response Body for Send SMS Request

```
{"resourceReference": {"resourceURL": "
http://example.com/1/smsmessaging/outbound/ tel%3A%2B5415550100/requests/abc123"}}
```

Example of a Request and Response

Example 23–4 shows an application's request to query the location of a mobile terminal in the Service Gatekeeper OneAPI RESTful interface.

Example 23–4 Request Associated with Get Terminal Location

```
GET
http://example.com/oneapi/1/location/queries/location?&address=tel&3A%2B1541555010
0&requestedAccuracy=1000 HTTP/1.1
Host: example.com:80
Accept: application/json
```

Example 23–5 shows the response which the application receives containing the terminal location information for the requested subscriber.

Example 23–5 Response Associated with a Get Terminal Location Operation

```
HTTP/1.1 200 OKContent-Type: application/json
Content-Type: application/json
Content-Length: 1234
Date: Thu, 04 Jun 2009 02:51:59 GMT
{"terminalLocationList": {"terminalLocation": {
    "address": "tel:15415550100",
    "currentLocation": {
       "accuracy": "100",
       "altitude": "1001.0",
       "latitude": "-80.86302",
        "longitude": "41.277306",
        "timestamp": "2009-06-03T00:27:23.000Z"
```

```
},
    "locationRetrievalStatus": "Retrieved"
}}}
```

Authentication and Security

The OneAPI RESTful interfaces in Services Gatekeeper use HTTP basic authentication, using username and password. SSL is required. For example:

```
Authorization: Basic QWxhZGRpbjpvcGVuIHNlc2FtZQ==
```

For more information on HTTP basic authentication, see RFC 2617 on the IETF website:

```
http://www.ietf.org/rfc/rfc2617.txt
```

Services Gatekeeper supports sessionID security with use of the **X-SessionID** header.

Services Gatekeeper also supports subscriber authentication and authorization for access to protected resources by supporting OAuth 2.0. For information on using OAuth 2.0, see Services Gatekeeper OAuth Guide.

Notifications

When an application needs to receive a notification, for example about a message delivery receipt, the application posts a subscription request containing a **notificationURL** location where Services Gatekeeper delivers the notification.

Example 23–6 shows a POST operation subscribing to SMS delivery notifications for a **senderAddress**. The notificationURL is included in the message body.

Example 23–6 SMS Delivery Notification Subscription POST Request

```
POST http://example.com/oneapi/1/smsmessaging/outbound/
tel%3A%2B5550100/subscriptions HTTP/1.1
Host: example.com:80
Content-Type: application/x-www-form-urlencoded
Accept: application/json
notifyURL=http://www.yourURL.here&
criteria="SampleCriteria"&
callbackData=doSomething()
```

An application can only subscribe to its own notifications (that is, to the notifications associated with its start notification requests). Any attempt to subscribe to notifications for other applications is rejected.

Errors and Exceptions

The Status-Line in the response message indicates the protocol version, the three-digit status code, and the reason for the failure of the request.

In addition, service exception and policy exception objects are represented in the response body as JSON objects of the following form:

```
{ "requestError":
           "policyException": "class name of the error object"
              "messageID": "System Generated ID:
```

```
"text":"error message"
             "variables"""relevant string"
          }
}
```

For service exceptions, the value for **type** is:

"type": "org.csapi.schema.parlayx.common.v2_1.ServiceException"

For Policy Exceptions, the value for **type** is:

"type": "org.csapi.schema.parlayx.common.v2_1.PolicyException"

Part IV

Creating Applications Using the SOAP Interfaces

Part IV describes how to use the interfaces in the SOAP facade and provides details on the interfaces that it supports to create applications that interact with Oracle Communications Services Gatekeeper.

Part IV contains the following chapters:

- Using the SOAP Interfaces
- Adding a SOAP2SOAP Communication Services
- Adding SOAP-Based Quality of Service Support
- About the Supported SOAP Parlay X 2.1 Facades
- About the Supported SOAP Parlay X 3.0 Facades
- About the Supported SOAP Parlay X 4.0 Facades
- About the Supported SOAP Native Facade

Using the SOAP Interfaces

This chapter presents a high-level description of the SOAP mechanisms and explains how to use this functionality to create services that interact with Oracle Communications Services Gatekeeper (Services Gatekeeper.)

Understanding the SOAP Interfaces

The SOAP-based interfaces are based on the Parlay X standards, and additional Extended Web Services interfaces that cover functionality which is not supported by Parlay X.

See Services Gatekeeper Concepts for a complete list of the SOAP-based interfaces supported by Services Gatekeeper. These interfaces are explained in detail in the chapters that follow.

Applications using SOAP-based interfaces must manipulate the SOAP messages that they use to make requests in certain specialized ways. They must add specific information to the SOAP header, and, if they are using for example Multimedia Messaging, they must send their message payload as a SOAP attachment. Applications using the native interfaces use the normal native interface mechanisms, which are not covered in this document. See "Understanding the Extended Web Services Common Definitions" for details.

The mechanisms for dealing with these requirements programmatically depend on the environment in which the application is being developed.

Note: Clients created using Axis 1.2 or older do not work with some communication services. Developers should use Axis 1.4 or newer if they wish to use Axis.

For examples using the Oracle WebLogic Server environment to accomplish these sorts of tasks, see "Managing SOAP Headers and Attachments Programmatically".

See "Adding a SOAP2SOAP Communication Services" for information on how to create and deploy a SOAP2SOAP communication service.

Requirements for Using the SOAP-Based Interfaces

If your application is using the SOAP-based interfaces to interact with Services Gatekeeper, there are four types of elements you may need to add to your application's SOAP messages to Services Gatekeeper.

Understanding SOAP-Based Authentication

In order to secure Services Gatekeeper and the telecom networks to which it provides access, applications are usually required to provide authentication information in every SOAP request which the application submits. Services Gatekeeper leverages the WebLogic Server Web services Security (WS-Security) framework to process this information.

Note: WS-Security provides three modes of providing security between a Web service client application and the Web service itself for message level security: Authentication, Digital Signatures, and Encryption. See "Securing and Administering Web Services" in see Oracle Fusion Middleware Security and Administrator's Guide for Web Services for an overview

Services Gatekeeper supports three authentication types:

- Username/Password Authentication (Username Token)
- Digital Signatures (X.509 Certificate Token)
- Encryption (SAML Token)

The type of token that the particular Services Gatekeeper operator requires is indicated in the Policy section of the WSDL files that the operator makes available for each application-facing interface it supports. In the following WSDL fragment, for example, the required form of authentication, indicated by the <wssp:Identity> element, is Username Token.

Example 24-1 WSDL fragment showing Policy

```
<s0:Policy s1:Id="Auth.xml">
<wssp:Identity>
<wssp:SupportedTokens>
<wssp:SecurityToken</pre>
TokenType="http://docs.example.com/wss/2004/01/oasis200401wssusernametoken
profile1.0#UsernameToken">
<wssp:UsePassword</pre>
Type="http://docs.oasisopen.org/wss/2004/01/oasis200401wssusernametoken
profile1.0#PasswordText"/>
</wssp:SecurityToken>
<wssp:SecurityToken</pre>
TokenType="http://docs.oasisopen.org/wss/2004/01/oasis200401wssx509token
profile1.0#X509v3"/>
</wssp:SupportedTokens>
</wssp:Identity>
</s0:Policy>
<wsp:UsingPolicy n1:Required="true"/>
```

Note: If the WSDL also has a <wssp: Integrity> element, digital signing is required (WebLogic Server provides WS-Policy: sign.xml). If it has a <wssp:Confidentiality> element, encryption is required (WebLogic Server provides WS-Policy: encrypt.xml).

SOAP Header Element for Authentication

Below are examples of the three types of authentication that can be used with Services Gatekeeper.

Username/Password Authentication (Username Token) In the Username Token mechanism, which is specified by the use of the <wsse:UsernameToken> element in the header, authentication is based on a user name, specified in the <wsse:Username> element and a password, specified in the <wsse:Password> element.

Two types of passwords are possible, indicated by the Type attribute in the Password element:

- PasswordText indicates the password is in clear text format.
- PasswordDigest indicates that the sent value is a Base64-encoded, SHA-1 hash of the UTF8 encoded password.

There are two more optional elements in Username Token, introduced to provide a countermeasure for replay attacks:

- <wsse:Nonce>, a random value that the application creates.
- <wsu:Created>, a timestamp.

If either or both the Nonce and Created elements are present, the Password Digest is computed as: Password_Digest = Base64(SHA-1(nonce+created+password))

When the application sends a SOAP message using Username Token, the WSEE implementation in Services Gatekeeper evaluates the username using the associated authentication provider. The authentication provider connects to the Services Gatekeeper database and authenticates the username and the password. In the database, passwords are stored as MD5 hashed representations of the actual password.

Example 24–2 Example of a WSSE: Username Token SOAP header element

```
<wsse:UsernameToken wsu:Id="Example-1">
 <wsse:Username> myUsername </wsse:Username>
 <wsse:Password Type="PasswordText">myPassword</wsse:Password>
 <wsse:Nonce EncodingType="..."> ... </wsse:Nonce>
 <wsu:Created> ... </wsu:Created>
</wsse:UsernameToken>
```

The UserName is equivalent to the application instance ID. The Password part is the password associated with this UserName when the application credentials was provisioned in Services Gatekeeper.

For more information on Username Token, see:

```
http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-username-token-pro
file-1.0.pdf
```

Digital Signatures (X.509 Certificate Token) In the X.509 Token mechanism, the application's identity is authenticated by the use of an X.509 digital certificate.

Typically a certificate binds the certificate holder's public key with a set of attributes linked to the holder's real world identity – for example the individual's name, organization and so on. The certificate also contains a validity period in the form of two date and time fields, specifying the beginning and end of the interval during which the certificate is recognized.

The entire certificate is (digitally) signed with the key of the issuing authority. Verifying this signature guarantees

- that the certificate was indeed issued by the authority in question
- that the contents of the certificate have not been forged, or tampered with in any way since it was issued

For more information on X.509 Token, see:

http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-x509-token-profile

The default identity assertion provider in Services Gatekeeper verifies the authenticity of X.509 tokens and maps them to valid Services Gatekeeper users.

Note: While it is possible to use the out-of-the-box keystore configuration in Services Gatekeeper for testing purposes, these should not be used for production systems. The digital certificates in these out-of-the-box keystores are only signed by a demonstration certificate authority For information on configuring keystores for production systems, see the discussion on configuring identity and trust in *Oracle Fusion Middleware Securing Oracle WebLogic Server* at:

```
http://download.oracle.com/docs/cd/E15523
01/web.1111/e13707/identity trust.htm
```

The x.509 certificate common name (CN) for an application must be the same as the account user name, which is the string that was referred to as the **applicationInstanceGroupId** in previous versions of Services Gatekeeper. This is provided by the operator when the account is provisioned.

To authenticate using x.509 certificates:

1. Create a web service security configuration.

For details, see "Create a Web service security configuration" in Oracle WebLogic Server Administration Console Online Help.

2. Generate key pair for the client :

```
% keytool -genkey -alias client_cert_x509 -keyalg RSA -keysize 1024 -keypass
ClientKey -keystore client_Identity.jks -storepass ClientKey
```

3. Export the self-signed certificate:

```
% keytool -genkey -alias server_cert_x509 -keyalg RSA -keysize 1024 -keypass
ServerKey -keystore ServerIdentity.jks -storepass ServerKey
```

4. Generate the key pair for the server:

```
keytool -genkey -alias server_cert_x509 -keyalg RSA -keysize 1024 -keypass
ServerKey -keystore ServerIdentity.jks -storepass ServerKey
```

5. Export the self-signed certificate:

```
% keytool -export -rfc -alias server_cert_x509 -file ServerCert.cer -keystore
ServerIdentity.jks -storepass ServerKey
```

6. Import the trust certificates:

```
% keytool -import -v -trustcacerts -alias client_cert_x509 -file ClientCert.cer
-keystore C:\ocsg510ga\JDK160~1\jre\lib\security\cacerts -storepass changeit
keytool -import -v -trustcacerts -alias server_cert_x509 -file ServerCert.cer .
-keystore C:\ocsqversion\JDKversion\jre\lib\security\cacerts -storepass
changeit
```

7. Configure the certificates in the Administration Console by pointing the server to the certificates you created in Step 5:

C:\ocsgversion\JDKversion\jre\lib\security\ServerCert.cer

You can use x.509 certificates to establish identity.

For details, see "Use X.509 certificates to establish identity" in Oracle WebLogic Server Administration Console Online Help.

Example 24–3 Example of a WSSE: X.509 Certificate SOAP header element

```
<wsse:Security xmlns:wsse="..." xmlns:wsu="...">
  <wsse:BinarySecurityToken wsu:Id="binarytoken"</pre>
   ValueType="wsse:X509v3"
   EncodingType="wsse:Base64Binary">
     MIIEZzCCA9CgAwIBAgIQEmtJZc0...
  </wsse:BinarySecurityToken>
  <ds:Signature xmlns:ds="http://www.w3.org/2000/09/xmldsig#">
  <ds:SignedInfo>
   <ds:Reference URI="#body">...</ds:Reference>
    <ds:Reference URI="#binarytoken">...</ds:Reference>
  </ds:SignedInfo>
  <ds:SignatureValue>HFLP...</ds:SignatureValue>
   <ds:KeyInfo>
      <wsse:SecurityTokenReference>
        <wsse:Reference URI="#binarytoken" />
      </wsse:SecurityTokenReference>
   </ds:KeyInfo>
  </ds:Signature>
</wsse:Security>
```

Encryption (SAML Token) Using WebLogic Server's WSSE implementation, Services Gatekeeper supports SAML versions 1.0, 1.1, and 2.0. The versions are similar.

See "Using SAML Assertions to Access Resources" in Services Gatekeeper OAuth Guide for more information on using SAML with OAuth.

For an overview of the differences between versions 1.0 and 1.1, see:

http://www.oasis-open.org/committees/download.php/3412/sstc-saml-diff-1.1draft-01.pdf

In SAML, a third party, the Asserting Party, provides the identity information for a Subject that wishes to access the services of a Relying Party. This information is carried in an Assertion. In the SAML Token type of Authentication, the Assertion (or a reference to an Assertion) is provided inside the <WSSE:Security> header in the SOAP message. The Relying Party (which in this case is Services Gatekeeper, using the WebLogic Security framework) then evaluates the trustworthiness of the assertion, using one of two confirmation methods.

- Holder-of-Key
- Sender-Voucher

For more information on these confirmation methods, see the discussion on SAML token profile support in Oracle Fusion Middleware Understanding Security for Oracle WebLogic Server at:

http://download.oracle.com/docs/cd/E15523 01/web.1111/e13710/archtect.htm

Example 24-4 Example of a WSSE: SAML Token SOAP header element

```
<wsse:Security>
<saml:Assertion MajorVersion="1" MinorVersion="0"</pre>
```

```
AssertionID="186CB370-5C81-4716-8F65-F0B4FC4B4A0B"
    Issuer="www.test.com" IssueInstant="2001-05-31T13:20:00-05:00">
  <saml:Conditions NotBefore="2001-05-31T13:20:00-05:00"</pre>
    NotAfter="2001-05-31T13:25:00-05:00"/>
  <saml:AuthenticationStatement AuthenticationMethod="password"</pre>
    AuthenticationInstant="2001-05-31T13:21:00-05:00">
    <saml:Subject>
      <saml:NameIdentifier>
        <SecurityDomain>"www.bea.com"</SecurityDomain>
        <Name>"cn=localhost,co=bea,ou=sales"</Name>
      </saml:NameIdentifier>
    </saml:Subject>
  </saml:AuthenticationStatement>
</saml:Assertion>
</wsse:Security>
```

Setting Callback Timeout Limits

By default Services Gatekeeper AT server waits 3 seconds to establish a connection with an application endpoint before giving up on the connection, and 30 seconds after establishing the connection before deciding that a reply will never come. The **-Dwlng.ws.callback.connect_timeout** java property setting controls the time limit for requesting a connection and -Dwlng.ws.callback.read_timeout controls the reply time limit. Change these settings if your Services Gatekeeper implementation requires different time limits by adding these Java arguments to your *Middleware Home*/user projects/domains/domain_name/bin/startWebLogic.sh script:

```
-Dwlng.ws.callback.connect_timeout=time_in_miliseconds
-Dwlng.ws.callback.read timeout=time in miliseconds
```

Understanding How Service Correlation Orchestrates Services

In some cases the service that an application provides to its end-users may involve accessing multiple Services Gatekeeper communication services. For example, a mobile user might send an SMS to an application asking for the pizza restaurant nearest to his current location. The application then makes a Terminal Location request to find the user's current location, looks up the address of the closest pizza restaurant, and then sends the user an MMS with all the appropriate information. Three Services Gatekeeper communication services are involved in executing what for the application is a single service. In order to be able to correlate the three communication service requests, Services Gatekeeper uses a service correlation ID, or SCID. This is a string that is captured in all the CDRs and EDRs generated by Services Gatekeeper. The CDRs and EDRs can then be orchestrated in order to provide special treatment for a given chain of service invocations, by, for example, applying charging to the chain as a whole rather than to the individual invocations.

The SCID is not provided by Services Gatekeeper. When the chain of services is initiated by an application-initiated request, the application must provide, and ensure the uniqueness of, the SCID within the chain of service invocations.

Note: In certain circumstances, it is also possible for a custom service correlation service to supply the SCID, in which case it is the custom service's responsibility to ensure the uniqueness of the SCID.

When the chain of services is initiated by a network-triggered request, Services Gatekeeper calls an external interface to get the SCID. This interface must be

implemented by an external system. No utility or integration is provided out-of-the box; this must be a part of a system integration project. It is the responsibility of the external system to provide, and ensure the uniqueness of, the SCID.

The SCID is passed between Services Gatekeeper and the application through an additional SOAP header element, the SCID element. Because not every application requires the service correlation facility, this is an optional element.

When the scid element is used, it should be on the same level as the session element in the SOAP header.

Example 24-5 Example of a SCID SOAP header element

```
<env:Header>
   <wsse:Security</pre>
    </wsse:Security>
    <session
    . . .
    </session>
    <scid
    </scid>
</env:Header>
```

Understanding Parameter Tunneling

Parameter tunneling is a feature that allows an application to send additional parameters to Services Gatekeeper and lets a plug-in use these parameters. This feature makes it possible for an application to tunnel parameters that are not defined in the application-facing interface and can be seen as an extension to it.

See the discussion on using SOAP parameter tunneling in Services Gatekeeper Extension *Developer's Guide* for more information parameter tunneling.

See the appropriate sections in Services Gatekeeper Communication Service Reference Guide for descriptions of the tunneled parameters that are applicable to your communication service.

Understanding SOAP Payload Attachments

In some communication services request payloads are sent as SOAP attachments. Example 24–6 below shows a Multimedia Messaging sendMessage operation that contains an attachment carrying a jpeg image.

Example 24-6 Example of a SOAP message with attachment (full content is not shown)

```
POST /parlayx21/multimedia_messaging/SendMessage HTTP/1.1
Content-Type: multipart/related; type="text/xml"; start="<1A07DC767BC3E4791AF25A04F17179EE>";
boundary="---=_Part_0_2633821.1170785251635"
Accept: application/soap+xml, application/dime, multipart/related, text/*
User-Agent: Axis/1.4
Host: localhost:8000
Cache-Control: no-cache
Pragma: no-cache
SOAPAction: ""
Content-Length: 4652
Connection: close
----=_Part_0_2633821.1170785251635
Content-Type: text/xml; charset=UTF-8
```

```
Content-Transfer-Encoding: binary
Content-Id: <1A07DC767BC3E4791AF25A04F17179EE>
 <?xml version="1.0" encoding="UTF-8"?>
   <soapenv:Envelope xmlns:soapenv="http://schemas.xmlsoap.org/soap/envelope/"</pre>
     xmlns:xsd="http://www.w3.org/2001/XMLSchema"
     xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
     <soapenv:Header>
       <ns1:Security ns1:Username="app:-4206293882665579772"</pre>
        ns1:Password="app:-4206293882665579772"
        soapenv:actor="wsse:PasswordToken"
        soapenv:mustUnderstand="1" xmlns:ns1="/parlayx21/multimedia_
messaging/SendMessage">
      </ns1:Security>
     </soapenv:Header>
     <soapenv:Body>
       <sendMessage xmlns=</pre>
        "http://www.csapi.org/schema/parlayx/multimedia_messaging/send/v2_4/local">
        <addresses>tel:234</addresses>
        <senderAddress>tel:567</senderAddress>
        <subject>Default Subject Text
        <priority>Normal</priority>
        <charging>
          <description xmlns="">Default</description>
          <currency xmlns="">USD</currency>
          <amount xmlns="">1.99</amount>
          <code xmlns="">Example_Contract_Code_1234</code>
        </charging>
       </sendMessage>
     </soapenv:Body>
   </soapenv:Envelope>
-----Part_0_2633821.1170785251635
Content-Type: image/jpeg
Content-Transfer-Encoding: binary
Content-Id:
 !1AQ"aq2???#?BRr?3Cb????? ?? '!1"AQ2Raq???? ? ??{?????>?"7B?7!1??????Z
e{????ax??5??CC??-Du?
??X?)Y!??=R@??g????T??c????f?Wc??eCi?l?????5s??\E???6I??(?x?^???=??d?#?itoi?{;? ??G......
----=_Part_0_2633821.1170785251635--
```

Managing SOAP Headers and Attachments Programmatically

This section illustrates how to manage the Services Gatekeeper required SOAP headers and SOAP attachments when you are using WebLogic Server and WebLogic Server tools to generate stubs for your Web services clients. If you are using a different environment, these steps probably do not apply.

For an overview of using Oracle Fusion Middleware to create Web service clients, see the discussion on Oracle Fusion Middleware in Oracle Fusion Middleware Introducing Web Services at:

http://download.oracle.com/docs/cd/E15523 01/web.1111/e14294/toc.htm

These examples show how to use a single message handler to add both SOAP Headers and SOAP attachments.

The WebLogic Server environment relies heavily on using supplied Ant tasks. Example 24–7 shows the clientgen Ant task added to the standard build.xml file.

Example 24–7 Snippet from build.xml

```
<cli>entgen
 wsdl="${wsdl-file}"
 destDir="${class-dir}"
 handlerChainFile="SOAPHandlerConfig.xml"
 packageName="com.bea.wlcp.wlng.test"
 autoDetectWrapped="false"
 generatePolicyMethods="true"
/>
```

A handler configuration file, SOAPHandlerConfig.xml is added as the value for the handlerChainFile attribute. Example 24–8 show a SOAPHandlerConfig.xml file.

Example 24-8 SOAPHandlerConfig.xml

```
<weblogic-wsee-clientHandlerChain</pre>
 xmlns="http://www.example.com/ns/weblogic/90"
 xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
 xmlns:j2ee="http://java.sun.com/xml/ns/j2ee">
  <handler>
    <j2ee:handler-name>clienthandler1</j2ee:handler-name>
    <j2ee:handler-class>
      com.bea.wlcp.wlng.client.TestClientHandler
   </j2ee:handler-class>
  </handler>
</weblogic-wsee-clientHandlerChain>
```

TestClientHandler provides the following functionality:

- Adds a Session ID to the SOAP header, see "Session Management for SOAP, RESTful, and OneAPI Interfaces". The session ID is hardcoded into the member variable sessionId.
- Adds a service correlation ID to the SOAP header. See "Understanding How Service Correlation Orchestrates Services" for more information.
- Adds a SOAP attachment in the form of a MIME message with content-type text/plain. See "Understanding SOAP Payload Attachments" for more information.

The configuration file for the message handler contains the handler-name and the associated handler-class. The handler class, TestClientHandler, is shown in Example 24–9.

Example 24-9 TestClientHandler

```
package com.example.wlcp.wlng.client;
import javax.xml.rpc.handler.Handler;
import javax.xml.rpc.handler.HandlerInfo;
import javax.xml.rpc.handler.MessageContext;
import javax.xml.rpc.handler.soap.SOAPMessageContext;
import javax.xml.soap.*;
import javax.xml.namespace.QName;
public class TestClientHandler implements Handler{
 public String sessionId = "myID";
 public String SCID = "mySCId";
 public String contenttype = "text/plain";
 public String content = "The content";
 public boolean handleRequest(MessageContext ctx) {
    if (ctx instanceof SOAPMessageContext) {
```

```
try {
      SOAPMessageContext soapCtx = (SOAPMessageContext) ctx;
      SOAPMessage soapmsg = soapCtx.getMessage();
      SOAPHeader header = soapCtx.getMessage().getSOAPHeader();
      SOAPEnvelope envelope =
        soapCtx.getMessage().getSOAPPart().getEnvelope();
      // Begin: Add session ID
      Name headerElementName = envelope.createName("session","",
        "http://schemas.xmlsoap.org/soap/envelope/");
      SOAPHeaderElement headerElement =
        header.addHeaderElement(headerElementName);
      headerElement.setMustUnderstand(false);
      headerElement.addNamespaceDeclaration("soap",
        "http://schemas.xmlsoap.org/soap/envelope/");
      SOAPElement sessionId = headerElement.addChildElement("SessionId");
      sessionId.addTextNode(sessionId);
      // End: Add session ID
      // Begin: Add Combined Services ID
      Name headerElementName = envelope.createName("SCID","",
        "http://schemas.xmlsoap.org/soap/envelope/");
      SOAPHeaderElement headerElement =
        header.addHeaderElement(headerElementName);
      headerElement.setMustUnderstand(false);
      headerElement.addNamespaceDeclaration("soap",
        "http://schemas.xmlsoap.org/soap/envelope/");
      SOAPElement sessionId = headerElement.addChildElement("SCID");
      sessionId.addTextNode(SCID);
      // End: Add Combined Services ID
      // Begin: Add SOAP attachment
      AttachmentPart part = soapmsg.createAttachmentPart();
      part.setContent(content, contenttype);
      soapmsg.addAttachmentPart(part);
      // End: Add SOAP attachment
    } catch (Exception e) {
      e.printStackTrace();
    }
  return true;
public boolean handleResponse(MessageContext ctx) {
  return true;
public boolean handleFault(MessageContext ctx) {
  return true;
public void init(HandlerInfo config) {
public void destroy() {
public QName[] getHeaders() {
  return null;
}
```

Adding a SOAP2SOAP Communication Services

This chapter explains information about creating Oracle Communications Services Gatekeeper SOAP2SOAP communication services.

About SOAP2SOAP Communication Services

You use the Partner and API Management Portal to create SOAP2SOAP APIs and services. See "PRM Portals and the Application Development Process" in API *Management Guide* for information.

See "Adding a SOAP2SOAP Communication Service" in Extension Developer's Guide for details on about the SOAP2SOAP plugin, and the artifacts and properties it contains.

Adding SOAP-Based Quality of Service Support

This chapter describes how to add Quality of Service (QoS) support to SOAP-based applications for use with Oracle Communications Services Gatekeeper.

About the SOAP-Based QoS Interface

An application can use the SOAP-based QoS interface to apply a QoS policy, to query, modify and remove that policy, and to register as well as unregister for QoS-related notifications. A Policy Control and Charging Rules Function provider (PCRF) can also return QoS events to registered applications.

SOAP-Based Service Descriptions Available at Run-time

The WADL file to for SOAP-based QoS services is located at http://at_host:at_ port/parlayx40/qos/ApplicationQoS?WSDL.

Example Parlay X 4.0 Application-Driven QoS/Diameter Scenario

A typical QoS scenario involves a subscriber using a handset to access a video feed using a video application installed on the handset. Initially, because the default QoS is set to a low bandwidth, the video stops and stutters frequently as it is buffered repeatedly over the low speed connection. The subscriber requests a faster QoS through the application, presumably with a corresponding billing charge. Services Gatekeeper forwards that request to a PCRF which then applies the upgraded QoS. The subscriber's video now streams at the upgraded speed, without stuttering.

Note: While QoS frequently refers to raw bandwidth speed, it can apply to any factors that affect network performance, for example, connection latency and time-out.

Figure 26–1 shows a detailed QoS call flow sequence.




Figure 26–1 Example Parlay X 4.0 QoS Call Sequence

Configuring Services Gatekeeper to Use the QoS Communication **Services**

Before you can implement QoS functionality, a QoS plug-in must be deployed and configured in Services Gatekeeper. For information on deploying and configuring QoS

plug-ins, see the discussion on Parlay X 4.0 Application-driven Quality of Service (QoS) in Services Gatekeeper Communication Service Reference Guide.

Configuring Services	Gatekeeper t	Use the	QoS	Communication	Services
----------------------	--------------	---------	-----	---------------	----------

About the Supported SOAP Parlay X 2.1 Facades

This chapter describes the Oracle Communications Services Gatekeeper interfaces in the supported Parlay X 2.1 facades and contains information specific to Services Gatekeeper. For detailed descriptions of the interfaces, methods, and parameters, see the ETSI OSA Parlay X website for links to the specifications:

http://www.etsi.org/deliver/etsi_es/202300_202399/20239102/01.02.01_60/es_ 20239102v010201p.pdf

Parlay X 2.1 Part 2: Third Party Call

This interface is compliant with ETSI ES 202 391-2 V1.2.1 (2006-12) Open Service Access (OSA); Parlay X Web services; Part 2: Third Party Call (Parlay X 2).

Interface: ThirdPartyCall

The endpoint for the **ThirdPartyCall** interface is:

http://host:port/parlayx21/third_party_call/ThirdPartyCall

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

MakeCall

Sets up a call between two parties.

GetCallInformation

Displays information about a call.

EndCall

Ends a call.

CancelCall

Cancels a call setup procedure.

Error Codes

See General Error Codes.

Parlay X 2.1 Part 3: Call Notification

This set of interfaces is compliant with ETSI ES 202 391-3 V1.2.1 (2006-12) Open Service Access (OSA); Parlay X Web services; Part 3: Call Notification (Parlay X 2).

Interface: CallDirection

This interface is implemented by an application, and the consumer of this interface is Services Gatekeeper. The Web services Description Language (WSDL) file that defines the interface can be downloaded from:

http://host:port/parlayx21/call_notification/wsdls/parlayx_call_direction_ interface_2_2.wsdl

http://host:port/parlayx21/call_notification/wsdls/parlayx_call_direction_ service 2 2.wsdl

http://host:port/parlayx21/call_notification/wsdls/parlayx_call_ notification_types_2_2.xsd

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

HandleBusy

Services Gatekeeper calls this method, which is implemented by an application, when the called party is busy.

HandleNotReachable

Services Gatekeeper calls this method, which is implemented by an application, when the called party is not reachable.

HandleNoAnswer

Services Gatekeeper calls this method, which is implemented by an application, when the called party does not answer.

HandleCalledNumber

Services Gatekeeper calls this method, which is implemented by an application, before call setup.

Interface: CallNotification

The CallNotification interface is implemented by an application, and the consumer of this interface is Services Gatekeeper. The WSDL that defines the interface can be downloaded from:

http://host:port/parlayx21/call notification/wsdls/parlayx call notification_interface_2_2.wsdl

http://host:port/parlayx21/call_notification/wsdls/parlayx_call_ notification_service_2_2.wsdl

http://host:port/parlayx21/call_notification/wsdls/parlayx_call_ notification_types_2_2.xsd

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

NotifyBusy

Services Gatekeeper calls this method, which is implemented by an application, when the called party is busy.

NotifyNotReachable

Services Gatekeeper calls this method, which is implemented by an application, when the called party is not reachable.

NotifyNoAnswer

Services Gatekeeper calls this method, which is implemented by an application, when the called party does not answer.

NotifyCalledNumber

Services Gatekeeper calls this method, which is implemented by an application, before call setup.

Interface: CallNotificationManager

The endpoint for the **CallNotificationManager** interface is:

http://host:port/parlayx21/call_notification/CallNotificationManager

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

StartCallNotification

Starts a subscription for call notifications.

StopCallNotification

Stops a subscription for call notifications.

Interface: CallDirectionManager

The endpoint for the **CallDirectionManager** interface is:

http://host:port/parlayx21/call_notification/CallDirectionManager

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

StartCallDirectionNotification 8 1

Starts a subscription for call direction notifications.

StopCallDirectionNotification

Stops a subscription for call direction notifications.

Error Codes

See General Error Codes.

Parlay X 2.1 Part 4: Short Messaging

This set of interfaces is compliant with ETSI ES 202 391-4 V1.2.1 (2006-12) Open Service Access (OSA); Parlay X Web services; Part 4: Short Messaging (Parlay X 2).

Interface: SendSms

The endpoint for the **SendSms** interface is:

http://host:port/parlayx21/sms/SendSms

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

If a backwards-compatible communication service is used:

- The **senderAddress** parameter is either of the format tel: *mailbox ID\mailbox* password\Sender name or just sender name depending on how the application was provisioned in Services Gatekeeper.
- The priority parameter is not supported.

SendSms

Sends an SMS to one or more destinations.

SendSmsLogo

Sends an SMS Logo to one or more destinations.

Logos in SmartMessaging and EMS are supported. The image is not scaled.

Logos in the following raw image formats are supported:

- bmp
- gif
- jpg
- png

The logos are in pure black and white (gray scale not supported). Animated images are not supported. Scaling is not supported.

If the logo is converted to SmartMessaging format, the image cannot be larger than 72x14 pixels.

If the logo is sent in EMS format, the following rules apply:

- If the image is 16x16 pixels, the logo is sent as an EMS small picture.
- If the image is 32x32 pixels, the logo is sent as an EMS large picture.
- If the image is of any other size, the logo is sent as an EMS variable picture.
- Images up to 1024 pixels are supported.

SendSmsRingtone

Sends an SMS Ringtone to one or more destinations.

Ringtones can be in any of these formats:

- **RTX**
- SmartMessaging
- EMS (iMelody)

GetSmsDeliveryStatus

Gets the delivery status of a previously sent SMS.

It is possible to query delivery status of an SMS only if a callback reference was not defined when the SMS was sent. If a callback reference was defined, NotifySmsDeliveryReceipt is invoked by Services Gatekeeper and the delivery status is not stored. If the delivery status is stored in Services Gatekeeper, it is stored for a configurable period.

Interface: SmsNotification

This **SmsNotification** interface is implemented by an application, and the consumer of this interface is Services Gatekeeper. The WSDL file that defines the interface can be downloaded from:

http://host:port/parlayx21/sms/wsdls/parlayx_sms_notification_interface_2_

http://host:port/parlayx21/sms/wsdls/parlayx_sms_notification_service_2_ 2.wsdl

http://host:port/parlayx21/sms/wsdls/parlayx_sms_types_2_2.xsd

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

NotifySmsReception

Sends an SMS that is received by Services Gatekeeper to an application given that the SMS fulfills a set of criteria. The criteria is either defined by the application itself, using **startSmsNotification** or defined using a provisioning step in Services Gatekeeper.

Shortcode translation, if appropriate, is applied.

NotifySmsDeliveryReceipt

Sends a delivery receipt that a previously sent SMS has been received by its destination. The delivery receipt is propagated to the application given that the application provided a callback reference when sending the SMS.

Interface: ReceiveSms

The endpoint for the **ReceiveSms** interface is:

http://host:port/parlayx21/sms/ReceiveSms

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

GetReceivedSms

Gets messages that have been received by Services Gatekeeper. The SMS messages are retrieved using a registrationIdentifier used when the notification was registered using a provisioning step in Services Gatekeeper.

The maximum number of messages returned for one operation is controlled by the maxBatchSize attrribute of the SmsMBean. The default is 20. If you attempt to exceed the **maxBatchSize** value for an operation, Services Gatekeeper throws a policy exception. For details see SmsMBean in the "All Classes" section of the Services Gatekeeper OAM Java API Reference documentation.

Interface: SmsNotificationManager

The endpoint for the **SmsNotificationManager** interface is:

http://host:port/parlayx21/sms/SmsNotificationManager

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

StartSmsNotification

Initiates notifications to the application for a given service activation number and criteria.

> **Note:** A Service activation number may be provisioned to handle a range of numbers using short code translations.

Note: The equivalent of this operation may have been performed as an off-line provisioning step by the Services Gatekeeper administrator.

StopSmsNotification

Ends a previously started notification.

Sending Custom Message Content for Split and Submit Messaging Requests

With Split and Submit Messaging enabled, short messages addressed to many recipients are split into multiple individually-addressed requests by Services Gatekeeper. For information on enabling Split and Submit Messaging, see the discussion on **supportBulkRequest** in Services Gatekeeper System Administrator's Guide. For an overview of Split and Submit Messaging, see Services Gatekeeper Communication Service Reference Guide.

Using DifferentContentForSingleAddressInBulk to Customize Split Messages

You can provide custom content to be sent to particular addresses. To do this, specify the per-address content in a content attribute for each message element with custom content. Include an xparam DifferentContentForSingleAddressInBulk, set to true, with the SOAP request.

Each address in the bulk SMS request must have a content attribute if DifferentContentForSingleAddressInBulk is set to true.

For example:

```
<?xml version="1.0" encoding="UTF-8"?>
<messages>
  <message address="1100" content="1100abc"/>
  <message address="1200" content="1200abc"/>
  <message address="2100" content="2100abc"/>
  <message address="3100" content="3100abc"/>
</messages>
The schema is as follows:
<?xml version="1.0"?>
<xsd:schema xmlns:xsd="http://www.w3.org/2001/XMLSchema"</pre>
targetNamespace="http://www.oracle.com/ocsg/51"
xmlns:wlng="http://www.oracle.com/ocsg/51">
  <xsd:complexType name="messages">
```

```
<xsd:sequence>
    <xsd:element name="message" type="wlng:message" minOccurs="1"</pre>
maxOccurs="unbounded"/>
 </xsd:complexType>
 <xsd:complexType name="message">
   <xsd:attribute name="address" type="xsd:string" use="required"/>
    <xsd:attribute name="address" type="xsd:string" use="required"/>
    <xsd:attribute name="content" type="xsd:string" use="required"/>
 </xsd:complexType>
</xsd:schema>
```

Table 27–1 Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0002	n/a	Invalid input value for message part %1
		Log message:
		Parse bulk SMS XML message content failed: This log message indicates that xparam DifferentContentForSingleAddressInBulk in the request is set to true but the XML message content is not well-formed.
		Bulk SMS XML message cannot find content for address <code>dest_address</code> : This log message indicates that <code>xparam DifferentContentForSingleAddressInBulk</code> in the request is set to true and the XML is well-formed, but not every address has content provided for it. The first such address encountered is the one reported.

Error Codes

See General Error Codes.

Parlay X 2.1 Part 5: Multimedia Messaging

This set of interfaces is compliant with ETSI ES 202 391-5 V1.2.1 (2006-12) Open Service Access (OSA); Parlay X Web services; Part 5: Multimedia Messaging (Parlay X 2).

See "Sending Custom Message Content for Split and Submit Messaging Requests" for instructions on how to split messages into multiple individually-addressed requests

Interface: SendMessage

The endpoint for the **SendMessage** interface is:

http://host:port/parlayx21/multimedia_messaging/SendMessage

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

SendMessage

Sends a multimedia message. The content of the message is sent as a SOAP attachment. Sending as email is not supported.

Table 27–2 Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	WNG-000002	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.

Table 27-2 (Cont.) Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	MMS-000001	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.
SVC0001	MMS-000002	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.
SVC0001	MMS-000003	Address is utilizing an unsupported address type.
SVC0001	MMS-000005	Message could not be delivered to MMSC.

GetMessageDeliveryStatus

Gets the delivery status of a previously sent MMS.

It is possible to query delivery status of an MMS only if a callback reference was not defined when the message was sent. If a callback reference was defined, NotifyMessageDeliveryReceipt is invoked by Services Gatekeeper and the delivery status is not stored. If the delivery status is stored in Services Gatekeeper, it is stored for a configurable period.

Note: Storing delivery status for an MMS is configurable in Services Gatekeeper.

Table 27–3 Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	WNG-000002	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.
SVC0002	RequestIdentifier	Message is not found.

Interface: ReceiveMessage

The endpoint for this interface is: http://host:port/parlayx21/multimedia_ messaging/ReceiveMessage

Where the values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

GetReceivedMessages

Polls Services Gatekeeper for received messages.

The registrationIdentifier is required. Received message are stored in Services Gatekeeper only for a configurable period.

Table 27-4 Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	WNG-000002	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.
SVC0002	MMS-000002	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.

GetMessageURIs

Not supported.

GetMessage

Gets a specific message that was received by Services Gatekeeper and belongs to the application.

Table 27–5 Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	WNG-00000 2	Internal problem in Services Gatekeeper. Contact your Services Gatekeeper administrator.
SVC0001	MMS-000004	Correlator does not exist, no notification corresponds to the correlator.

Interface: MessageNotification

This interface is implemented by an application, and the consumer of this interface is Services Gatekeeper. The WSDL that defines the interface can be downloaded from:

http://host:port/parlayx21/multimedia_messaging/wsdls/parlayx_mm_ notification_interface_2_4.wsdl

http://host:port/parlayx21/multimedia_messaging/wsdls/parlayx_mm_ notification_service_2_4.wsdl

http://host:port/parlayx21/multimedia_messaging/wsdls/parlayx_mm_types_2_ 4.xsd

Where the values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

NotifyMessageReception

Sends a notification to an application that an MMS destined for the application is received by Services Gatekeeper.

When an application is notified about an incoming MMS message by an asynchronous call to **NotifyMessageReception** from Services Gatekeeper, the application receives a MessageReference structure containing information about the message.

If the MMS message contains only pure text, the <message> element of the MessageReference structure contains the entire text content as an ASCII string, and the message is not stored in Services Gatekeeper. If the message contains any content that is not pure text, such as an image, sound or video, the MessageReference structure does not include a <message> element, but instead includes a <messageIdentifer> element that contains a reference to the message stored in Services Gatekeeper. For more information about the MessageReference structure, see the Parlay X Web services Part 5: Multimedia Messaging specification.

NotifyMessageDeliveryReceipt

Sends a notification to an application that a previously sent MMS has been delivered to its destination.

> Supporting delivery notifications is optional for Services Gatekeeper.

Interface: MessageNotificationManager

The endpoint for the MessageNotificationManager interface is:

http://host:port/parlayx21/multimedia_messaging/MessageNotificationManager

Where the values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

StartMessageNotification

Initiates notifications to the application for a given service activation number and criteria.

Table 27–6 StartMessageNotification Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	WNG-000002	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.

Note: A service activation number may be provisioned to handle a range of numbers using short code translations.

Note: The equivalent to this operation may have been performed as an off-line provisioning step by the Services Gatekeeper administrator.

StartMessageNotification Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	WNG-000002	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.

StopMessageNotification

Ends a previously started notification.

Table 27-8 StopMessageNotification Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	WNG-000002	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.
SVC0002	correlator	Correlator does not exist, no notification corresponds to the correlator.

Error Codes

See General Error Codes.

Parlay X 2.1 Part 8: Terminal Status

This set of interfaces is compliant with ETSI ES 202 391-8 V1.2.1, Open Service Access (OSA); Parlay X Web services; Part 8: Terminal Status (Parlay X 2).

Interface: TerminalStatus

The endpoint for the **TerminalStatus** interface is:

http://host:port/parlayx21/terminal_status/TerminalStatus

Where values for host and port are the host name and port of the system on which Services Gatekeeper is installed.

getStatus

Gets the status for a single terminal.

getStatusForGroup

Gets the status for multiple terminals.

Interface: TerminalStatusNotificationManager

The endpoint for the **TerminalStatusNotificationManager** interface is:

http://host:port/parlayx21/terminal_ status/TerminalStatusNotificationManager

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

startNotification

Starts the terminal status change subscription.

endNotification

Notifies the Terminal Status communication service that it can cancel the terminal status change subscription.

Interface: TerminalNotification

The endpoint for the **TerminalNotification** interface is provided by the calling application.

statusNotification

Supplies the terminal status to the application. The status is sent by the Terminal Status communication service to the application.

statusError

Informs the application that the Terminal Status could not be obtained and contains an error message indicating why. Sent by the Terminal Status plug-in to the application.

statusEnd

Informs the application that the status notification subscription has ended. Sent by the Terminal Status plug-in to the application.

Error Codes

See the General Exceptions and General Error Codes sections for most error information. Table 27-9 includes additional diagnostic information specific to the Terminal Status/MAP plug-in.

1able 27-9	Terminal Sta	itus Exception and Error Code Information
Exception	Error code	Reason/Action
POL0002	N/A	A Terminal Status request was sent using a criteria of busy, in violation of a BusyAvailable = false is setting in an SLA.
POL0003	N/A	The number of Terminal Server addresses sent exceeded the MaximumNotificationAddresses setting in an SLA.
POL0004	N/A	An unlimited number of Terminal Status requests were sent, but the SLA UnlimitedCountAllowed was set to False.
POL0005	N/A	The number of Terminal Status requests exceeded the MaximumCount setting in an SLA.
POL0009	N/A	The Terminal Status request frequency violated the MaximumNotificationFrequency setting in an SLA.
POL0200	N/A	Busy criteria not supported.
SVC0001	MAP-0000 01	The Terminal Status communication service could not encode the anyTimeInterrogation MAP message. Check that the incoming Parlay X address request is correct and that the NetworkSelection for the supplied address has the correct MAPApplicationContext and MAPDialogueAS values.
SVC0001	SS7API-00 0001	The SS7 API failed to build and send a message to the SS7 stack. This usually means that the Terminal Status plug-in could not bind with the stack, or the bind was lost. Make sure that the stack is running and that the CpUserId and SS7 host/port/instance are correct.
SVC0001	SS7-000001	The SS7 stack received no answer or an incorrect answer. The SS7 stack did not send an anyTimeInterrogation call answer or the

Table 27-9 Terminal Status Exception and Error Code Information

Parlay X 2.1 Part 9: Terminal Location

This set of interfaces is compliant with ETSI ES 202 391-9 V1.2.1 (2006-12), Open Service Access (OSA); Parlay X Web services; Part 9: Terminal Location (Parlay X 2).

www.openss7.org website for more information.

answer was incorrect. This probably indicates a problem with the SS7 stack. Make sure that the global title/SPC/SSN is configured correctly in the NetworkSelection. Start an SS7 stack trace and check the ss7trace.log file. See the documentation reference at

Understanding Parlay X 2.1 Terminal Location Precision

The Parlay X 2.1 Terminal Location specification complies with the ISO 6709 [7] specification, specifying decimal values for longitude and latitude locations. The decimals representing longitude are floating point numbers in the range -90.0000 to +90.0000. Positive values for locations North of the equator and negative values for South of the equator. Longitude values are floating point numbers in the range -180.0000 to +180.0000. Positive values are East of the prime meridian, and negative values are West of the prime meridian.

It is important to understand that Services Gatekeeper rounds these floating point values to 8 significant digits. For example, if Services Gatekeeper receives messages with these longitude (X) and latitude (Y) values from the network:

```
"latitude": "12.34567890",
"longitude": "123.4567890",
```

Services Gatekeeper reports these rounded values to the application:

```
<X> 12.345679 </X>
<Y> 123.45679 </Y>
```

Interface: TerminalLocation

The endpoint for the **TerminalLocation** interface is:

http://host:port/parlayx21/terminal_location/TerminalLocation

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

GetLocation

Gets the location of a terminal.

Table 27–10 Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	TL-000007	There is a communication problems between Services Gatekeeper and the network node. Contact your Services Gatekeeper administrator.
SVC0001	TL-000010	There is a communication problem between Services Gatekeeper and the network node, and Services Gatekeeper was unable to interpret the response. Contact your Services Gatekeeper administrator.
SVC0001	TL-000009	No location data was received from network.
SVC0001	TL-000011	An unknown error was received from the network.
SVC0002	N/A	An invalid parameter was included in the terminal status request.
SVC0200	N/A	The location accuracy is invalid.
POL0001	N/A	General policy error.
POL0002	N/A	Privacy error.
POL0230	N/A	The requested accuracy is not supported.

GetTerminalDistance

Gets the distance from a certain point to the location of a terminal.

Table 27-11 Exceptions and Error Codes

Exception	Error code	Reason/Action	
SVC0001	TL-000007	There is a communication problems between Services Gatekeeper and the network node. Contact your Services Gatekeeper administrator.	
SVC0001	TL-000010	There is a communication problem between Services Gatekeeper and the network node, and Services Gatekeeper was unable to interpret the response. Contact your Services Gatekeeper administrator.	
SVC0001	TL-000009	No location data was received from the network.	
SVC0001	TL-000011	An unknown error was received from the network.	
SVC0002	N/A	An invalid parameter was included in the terminal status request.	
SVC0200	N/A	The location accuracy is invalid.	

Table 27-11 (Cont.) Exceptions and Error Codes

Exception	Error code	Reason/Action	
POL0001	N/A	General policy error.	
POL0002	N/A	Privacy error.	
POL0230	N/A	The requested accuracy is not supported.	

GetLocationForGroup

Gets the location for one or more terminals.

Table 27-12 Exceptions and Error Codes

Exception	Error code	Reason/Action	
SVC0001	TL-000007	There is a communication problems between Services Gatekeeper and the network node. Contact your Services Gatekeeper administrator.	
SVC0001	TL-000010	There is a communication problem between Services Gatekeeper and the network node, and Services Gatekeeper was unable to interpret the response. Contact your Services Gatekeeper administrator.	
SVC0001	TL-000009	No location data was received from the network.	
SVC0001	TL-000011	An unknown error was received from the network.	
SVC0002	N/A	An invalid parameter was included in the terminal status request.	
SVC0004	N/A	No valid addresses were passed in on the request.	
SVC0200	N/A	The location accuracy is invalid.	
POL0001	N/A	General policy error.	
POL0002	N/A	Privacy error.	
POL0230	N/A	The requested accuracy is not supported.	

Interface: TerminalLocationNotificationManager

The endpoint for the **TerminalLocationNotificationManager** interface is:

http://host:port/parlayx21/terminal_

location/TerminalLocationNotificationManager

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

StartGeographicalNotification

Initiates location notifications to the application when one or more terminals change their location according to a criteria.

Table 27–13 Exceptions and Error Codes

Exception	Error code	Reason/Action	
SVC0001	TL-000003	Unable to start the geographical notification due to a network error. Contact your Services Gatekeeper administrator.	
SVC0001	TL-000004	Unable to start geographical notification due to an internal error. Contact your Services Gatekeeper administrator.	

Table 27-13 (Cont.) Exceptions and Error Codes

Exception	Error code	Reason/Action	
SVC0002	N/A	The request included an invalid parameter.	
SVC0004	N/A	The request did not include any valid addresses.	
SVC0005	N/A	The correlator used already exists.	
POL0001	N/A	General policy error.	

StartPeriodicNotification

Initiates location notifications to the application on a periodic basis.

Table 27–14 Exceptions and Error Codes

Exception	Error code	Reason/Action	
SVC0001	TL-000005	Unable to start periodic notification due to a network error. Contact your Services Gatekeeper administrator.	
SVC0001	TL-000006	Unable to start periodic notification due to an internal error. Contact your Services Gatekeeper administrator.	
SVC0002	N/A	The request included an invalid parameter.	
SVC0004	N/A	The request did not include any valid addresses.	
SVC0005	N/A	The correlator used already exists.	
POL0001	N/A	General policy error.	

EndNotification

Ends a previously started notification.

Table 27–15 Exceptions and Error Codes

Exception	Error code	Reason/Action	
SVC0001	TL-000001	Unable to start geographical notification due to a network error. Contact your Services Gatekeeper administrator.	
SVC0001	TL-000002	Unable to start geographical notification due to an internal error. Contact your Services Gatekeeper administrator.	
SVC0002	N/A	The request included an invalid parameter.	
POL0001	N/A	General policy error.	

Interface: TerminalLocationNotification

The TerminalLocationNotification interface is implemented by an application, and the consumer of this interface is Services Gatekeeper. The WSDL that defines the interface can be downloaded from:

http://host:port/parlayx21/terminal_location/wsdls/parlayx_terminal_ location_notification_interface_2_2.wsdl

http://host:port/parlayx21/terminal_location/wsdls/parlayx_terminal_ location_notification_service_2_2.wsdl

http://host:port/parlayx21/terminal_location/wsdls/parlayx_terminal_ location_types_2_2.xsdl

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

LocationNotification

Notifies an application about a change of location for a terminal.

LocationError

Notifies an application that the subscription for location notifications was cancelled by Services Gatekeeper.

LocationEnd

Notifies an application that no more location notifications are being sent to the application.

Error Codes

See "General Error Codes".

Parlay X 2.1 Part 11: Audio Call

This set of interfaces is compliant with ETSI ES 202 391-11 V1.2.1 (2006-12) Open Service Access (OSA); Parlay X Web services; Part 11: Audio Call (Parlay X 2).

Interface: PlayAudio

The endpoint for the **PlayAudio** interface is: http://host:port/parlayx21/audio_ call/AudioCall.

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

EndMessage

Cancels previous play request.

GetMessageStatus

Requests the status of a previous play request.

PlayAudioMessage

Play an audio file (such as .WAV).

PlayTextMessage

Play text to a text-to-speech engine.

PlayVoiceXmlMessage

Play a VXML file.

Error Codes

See "General Error Codes".

Parlay X 2.1 Part 14: Presence

This set of interfaces is compliant with ETSI ES 202 391-14 V1.2.1 (2006-12), Open Service Access (OSA); Parlay X Web services; Part 14: Presence (Parlay X 2).

Interface: PresenceConsumer

The endpoint for the **PresenceConsumer** interface is:

http://host:port//parlayx21/presence/PresenceConsumer

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

subscribePresence

Requests a subscription for presence information about a presentity.

For the parameter presentity, only SIP URI can be used. Group-URI is not supported.

getUserPresence

Gets presence information about a presentity.

For the parameter presentity, only SIP URI can be used. Group-URI is not supported.

startPresenceNotification

Initiates presence notifications to the application when one or more presence attributes changes for a presentity.

For the parameter presentity, only SIP URI can be used. Group-URI is not supported.

The parameter frequency is not supported. The application is notified when an update of presence information is received from the network.

endPresenceNotification

Ends a previously started notification.

Interface: PresenceNotification

The **PresenceNotification** interface is implemented by an application, and the consumer of this interface is Services Gatekeeper. The WSDL that defines the interface can be downloaded from:

http://host:port/parlayx21/presence/wsdls/parlayx_presence_notification_ interface 2 3.wsdl

http://host:port/parlayx21/presence/wsdls/parlayx_presence_notification_ service_2_3.wsdl

http://host:port/parlayx21/presence/wsdls/parlayx_presence_types_2_3.xsd

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

statusChanged

Notifies an application about a change of presence attributes for a presentity.

statusEnd

Notifies an application that no more notifications will be sent to the application.

notifySubscription

Notifies an application that the presentity has handled the request for presence information.

subscriptionEnded

Notifies an application that the subscription for presence information has ended.

Interface: PresenceSupplier

The endpoint for the **PresenceSupplier** interface is:

http://host:port/parlayx21/presence/PresenceSupplier where values for host and port are the host name and port of the system on which Services Gatekeeper is installed.

The Presence Supplier interface requires that a presence server be available in the underlying network. Services Gatekeeper interacts with this server to provide this functionality to the application.

By default, Services Gatekeeper maps a presentity URI parameter to the client's Application Instance ID. This information is required to interact with the network and Parlay X 2.1 does not provide it by default.

The application can override the default presentity URI value by using "wlng.presence.parlay21.presentity.uri" as the key and the desired URI for the value in value = \$the_desired_URI. See "Understanding Parameter Tunneling" for more information.

publish

Publishes presence data about a presentity.

Note: The presence server in the network must support the "Publication of Partial Presence Information" IETF standard for this functionality to work. For the standards document, see http://tools.ietf.org/html/draft-ietf-simple-partial-publish -07#page-4

getOpenSubscriptions

Gets a list of new watchers who wish to subscribe to this presentity's data.

Note: The presence server in the network must support http://tools.ietf.org/html/draft-ietf-simple-partial-pidf-fo rmat-10 and http://tools.ietf.org/html/rfc3857 (http://tools.ietf.org/html/draft-ietf-simple-winfo-package-05) for this functionality to work.

updateSubscriptionAuthorization

Adds new watchers and updates the permissions of existing watchers of this presentity's data. This is the usual follow-up to the getOpenSubscriptions operation.

Note: This operation requires the presence of both a presence server and a Data Manipulation Server in the underlying network.

An SVC0220 service exception (NoSubscriptionRequest) is thrown if the presentity attempts to confirm the subscription of a watcher who has not asked to subscribe to the presentity's data.

getMyWatchers

Returns an array of the watchers that are subscribed to the presentity's data.

Note: The presence server in the network must support these IETF standards found at the IETF website for this feature to work:

```
http://tools.ietf.org/html/draft-ietf-simple-partial-pidf-fo
rmat-10
and
http://tools.ietf.org/html/rfc3857
(http://tools.ietf.org/html/draft-ietf-simple-winfo-package-
05).
```

getSubscribedAttributes

Not supported.

blockSubscription

Blocks the flow of presence information to a subscribed watcher by cancelling the subscription. The watcher is notified using "subscriptionEnded".

An SVC0221 service exception (Not a watcher) is thrown if the URI in the field watcher is not a watcher of the presentity.

Error Codes

See "General Error Codes".

About Notifications

After an application starts notification, the notification persists. If an application has started a notification and destroys the session, the notification remains registered and matching notifications are sent to the application when it connects to Services Gatekeeper.

General Exceptions

This section describes the exception handling for the Parlay X 2.1 interfaces.

These exception types are defined:

- Service exceptions
- Policy exceptions

Service exceptions are related to the operation of the service itself. The following exceptions are general:

- SVC0001: Service error.
- SVC0002: Invalid input value

- SVC0003: Invalid input value with list of valid values
- SVC0004: No valid addresses
- SVC0005: Duplicate correlator
- SVC0006: Invalid group
- SVC0007: Invalid charging information
- SVC0008: Overlapping Criteria

Policy Exceptions are thrown when a policy has been violated, including violations of a service level agreements. The following general Policy Exceptions are defined:

- POL0001: Policy error.
- POL0002: Privacy error.
- POL0003: Too many addresses specified.
- POL0004: Unlimited notifications not supported.
- POL0005: Too many notifications requested.
- POL0006: Groups not allowed.
- POL0007: Nested groups not allowed.
- POL0008: Charging not supported.
- POL0009: Invalid frequency requested.

Within the exception, an error code is defined. The error code details why the exception was thrown. See "General Error Codes".

General Error Codes

The following are general error codes for SVC0001: Service error:

- Null sessionID (loginTicket) expired.
- CN-000001 Two requests for call direction overlap with each other.
- CN-000002 Internal error when accessing the subscription storage.
- CN-000003 Could not find the call-back plug-in.
- CN-000004 The call direction routing address is not valid.
- MAP-000001 The Terminal Status plug-in failed to encode the anyTimeInterrorgation MAP message.
- MMS-000001 Unable to perform action. Network error. Check that the incoming Parlay X address request is correct and that the NetworkSelection for the supplied address has the correct MAPApplicationContext and MAPDialogueAS values
- MMS-000002 Unable to retrieve configuration, internal error.
- MMS-000003 The used address type is not supported.
- MMS-000004 An error occurred when an attachment was put into the request context.
- MMS-000005 The MM7 Relay server responded with an error code, which includes the status code and the status text in the following format: MMS-000005: Status Code: Status Text.

For example, if the MMSC response were:

```
<rel:Status>
   <rel:StatusCode>4000</rel:StatusCode>
    <rel:StatusText>Hello</rel:StatusText>
</rel:Status>
```

the SVC0001 ServiceException error code would be:

```
"MMS-000005:4000:Hello".
```

- OSA-000001 Invalid network state.
- OSA-000002 Invalid interface type.
- OSA-000003 Invalid event type.
- OSA-000004 Unsupported address plan.
- OSA-000005 Communication failure between OSA Gateway and Services Gatekeeper.
- PLC-000001 Internal policy engine error.
- PLG-000001 Could not find remote ejb home in access tier.
- PLG-000002 Could not create the ejb.
- PLG-000003 Could not access callback ejb.
- PLG-000004 Matching plug-in cannot be found because, for example, route has not been set up.
- PRESENCE-000001 Failed to use the default duration for a notification.
- PRESENCE-000002 Failed to use the default value for count for a notification.
- PRESENCE-000003 The application has no SIP-URI mapping configured.
- PRESENCE-000004 Internal error. Failed to put data in WorkContext.
- SIP-000001 Could not find remote ejb home.
- SIP-000002 Could not create the ejb.
- SIP-000003 Could not access remote ejb.
- SIP-000004 Could not create SIP session.
- SIP-000005 Failed to send SIP message.
- SIP-000006 Internal SIP stack error.
- SMS-000001 Unable to perform action. Network error.
- SMS-000002 Unable to retrieve configuration, internal error.
- SMS-000003 The used address type is not supported.
- SMS-000004 Unable to encode message segments.
- SMS-000005 GSM message format incorrect.
- SMS-000006 Could not send message. Message was not accepted by the network.

The status code and the status text are in the following format: SMS-000006:CommandStatus:Description

For example, if the SMSC commandstatus response is:

```
0x0000000B(ESME RINVDSTADR)
```

the SVC0001 ServiceException error code is:

"SMS-000006:11:Invalid Dest Addr".

The description of the command status is taken from the SMPP Specification v3.4. If the command status in the response from the SMSC is not explicitly described in the SMPP Specification, the text of the error is **No description available for** CommandStatus.

- SS7API-000001 The SS7 server failed to build and send the message to the SS7 stack. Make sure that the stack is running and that the CpUserId and SS7 host/port/instance are correct.
- SS7-000001 No answer or an incorrect answer received from the SS7 stack.
- TL-000001 Unable to end notification because of a network error.
- TL-000002 Unable to end notification because of an internal error.
- TL- 000003 Unable to start geographical notification because of a network error.
- TL-000004 Unable to start geographical notification because of an internal error.
- TL-000005 Unable to start periodic notification because of a network error.
- TL-000006 Unable to start periodic notification because of an internal error.
- TL-000007 Unable to get location because of a network error.
- TL-000008 Unable to get location because of an internal error.
- TL-000009 Unable to get location because no data was found.
- TL-000010 Failed to parse response because of an internal error.
- TL-000011 Failed to get location information because the MLP server returned an error.
- TPC-000001 Unable to retrieve configuration because of an internal error.
- TS-000001 Communication problems between Services Gatekeeper and the network node. Contact your Services Gatekeeper administrator. The GroupRequestTimeout attribute may be too low.
- TS-000002 Could not find a network service route to match the address. Validate the network selection routes. You may want to add a default route (expression=DEFAULT) to capture any addresses that do not matched any other expression.
- TS-000003 No result returned from a getStatusForGroup query. Update getGroupRequestTimeout to an appropriate value and check the status of network connection
- TS-000004 Did not find the correlator when sending an end-status notification. The value of correlator in the endNotification request is incorrect, or the notification has already been terminated by the network.
- TS-000005 Could not initialize the object. Check the instancemap configuration
- TS-000006 Failed to access storage. Check the status of the storage service and database.
- WNG-000000 No error.
- WNG-000001 Unknown error.
- WNG-000002 Storage service error.

Code Examples

The following code examples illustrate how to use the Parlay X 2.1 interfaces.

Example: sendSMS

This is an SMS sending example.

Example 27-1 SendSMS example

```
org.csapi.schema.parlayx.sms.send.v2_2.local.SendSms request =
new org.csapi.schema.parlayx.sms.send.v2_2.local.SendSms();
SimpleReference sr = new SimpleReference();
sr.setEndpoint(new
URI("http://localhost:8111/SmsNotificationService/services/SmsNotification?WSDL"));
sr.setCorrelator("cor188");
sr.setInterfaceName("InterfaceName");
ChargingInformation charging = new ChargingInformation();
charging.setAmount(new BigDecimal("1.1"));
charging.setCode("qwerty");
charging.setCurrency("USD");
charging.setDescription("some charging info");
sendInf.setCharging(charging);
URI[] uri = new URI[1];
uri[0] = new URI("1234");
request.setAddresses(uri);
request.setCharging(charging);
request.setReceiptRequest(sr);
request.setMessage("we are testing sms!");
request.setSenderName("6001");
org.csapi.schema.parlayx.sms.send.v2_2.local.SendSmsResponse response =
smport.sendSms(request);
String sendresult = response.getResult();
System.out.println("result: " + sendresult);
```

Example: startSmsNotification

This is an example of how to use startSmsNotification.

Example 27–2 startSmsNotification example

```
org.csapi.schema.parlayx.sms.notification_manager.v2_3.local.StartSmsNotification parameters =
new org.csapi.schema.parlayx.sms.notification_manager.v2_3.local.StartSmsNotification();
parameters.setCriteria("hello");
SimpleReference sr = new SimpleReference();
sr.setEndpoint(new
URI("http://localhost:8111/SmsNotificationService/services/SmsNotification?WSDL"));
sr.setCorrelator("cor189");
sr.setInterfaceName("interfaceName");
parameters.setReference(sr);
URI uri = new URI("tel:6001");
parameters.setSmsServiceActivationNumber(uri);
port.startSmsNotification(parameters);
```

Example: getReceivedSms

This example shows how to poll for SMS messages using getReceivedSms.

Example 27-3 getReceivedSms example

```
org.csapi.schema.parlayx.sms.receive.v2_2.local.GetReceivedSms_parameters =
new org.csapi.schema.parlayx.sms.receive.v2_2.local.GetReceivedSms();
parameters.setRegistrationIdentifier("1");
org.csapi.schema.parlayx.sms.receive.v2_2.local.GetReceivedSmsResponse response =
port.getReceivedSms(parameters);
org.csapi.schema.parlayx.sms.v2_2.SmsMessage[] msgs =
response.getResult();
if(msgs != null) {
 for(org.csapi.schema.parlayx.sms.v2_2.SmsMessage msg : msgs) {
    System.out.println(msg.getMessage());
  }
}
```

Example: sendMessage

This is an MMS sending example.

Example 27-4 sendMessage example

```
org.csapi.schema.parlayx.multimedia_messaging.send.v2_4.local.SendMessage request =
new org.csapi.schema.parlayx.multimedia_messaging.send.v2_4.local.SendMessage();
ChargingInformation charging = new ChargingInformation();
charging.setAmount(new BigDecimal("1.1"));
charging.setCode("qwerty");
charging.setCurrency("USD");
charging.setDescription("some charging info");
sendInf.setCharging(charging);
SimpleReference sr = new SimpleReference();
if(getProperty("notification_mt").equalsIgnoreCase("true")) {
  sr.setEndpoint(new URI(getProperty(ClientConstants.NOTIFICATION_LISTENER_URL)));
 sr.setCorrelator(getProperty("correlator"));
 sr.setInterfaceName(getProperty("interfacename"));
URI[] uri = new URI[1];
uri[0] = new URI("1234");
request.setAddresses(uri);
request.setCharging(charging);
request.setPriority(MessagePriority.fromString("Default"));
request.setReceiptRequest(sr);
request.setSenderAddress("6001");
request.setSubject("subject");
org.csapi.schema.parlayx.multimedia_messaging.send.v2_4.local.SendMessageResponse response =
smport.sendMessage(request);
String sendresult = response.getResult();
System.out.println("sendresult: " + sendresult);
```

Example: getReceivedMessages and getMessage

This is shows polling for a received MMS.

Example 27–5 getReceivedMessages and getMessage example

```
org.csapi.schema.parlayx.multimedia_messaging.receive.v2_4.local.GetReceivedMessages parameters =
new org.csapi.schema.parlayx.multimedia_messaging.receive.v2_4.local.GetReceivedMessages();
parameters.setPriority(org.csapi.schema.parlayx.multimedia_messaging.v2_
4.MessagePriority.fromString("Default"));
parameters.setRegistrationIdentifier("2");
```

```
org.csapi.schema.parlayx.multimedia_messaging.receive.v2_4.local.GetReceivedMessagesResponse result
port.getReceivedMessages(parameters);
org.csapi.schema.parlayx.multimedia_messaging.v2_4.MessageReference[] refs =
result.getResult();
if(refs != null) {
 for(org.csapi.schema.parlayx.multimedia_messaging.v2_4.MessageReference ref : refs) {
   String id = ref.getMessageIdentifier();
    org.csapi.schema.parlayx.multimedia_messaging.receive.v2_4.local.GetMessage p2 =
   new org.csapi.schema.parlayx.multimedia_messaging.receive.v2_4.local.GetMessage();
   p2.setMessageRefIdentifier(id);
   port.getMessage(p2);
}
```

Example: getLocation

This example shows how to get the location of a terminal.

Example 27-6 getLocation example

```
org.csapi.schema.parlayx.terminal_location.v2_2.local.GetLocation parameters =
new org.csapi.schema.parlayx.terminal_location.v2_2.local.GetLocation();
parameters.setAcceptableAccuracy(5);
parameters.setAddress(new URI("1234"));
parameters.setRequestedAccuracy(5);
TimeMetric maximumAge = new TimeMetric();
maximumAge.setMetric(TimeMetrics.fromString("Hour"));
maximumAge.setUnits(10);
parameters.setMaximumAge(maximumAge);
TimeMetric responseTime = new TimeMetric();
responseTime.setMetric(TimeMetrics.fromString("Hour"));
responseTime.setUnits(1);
parameters.setResponseTime(responseTime);
DelayTolerance tolerance = DelayTolerance.fromString("NoDelay");
parameters.setTolerance(tolerance);
org.csapi.schema.parlayx.terminal_location.v2_2.local.GetLocationResponse response =
port.getLocation(parameters);
org.csapi.schema.parlayx.terminal_location.v2_2.nfo result =
response.getResult();
System.out.println("accuracy : " + result.getAccuracy());
System.out.println("altitude : " + result.getAltitude().floatValue());
System.out.println("latitude : " + result.getLatitude());
System.out.println("longitude : " + result.getLongitude());
System.out.println("timestamp : " + result.getTimestamp());
```

About the Supported SOAP Parlay X 3.0 Facades

This chapter describes the Oracle Communications Services Gatekeeper interfaces in the supported Parlay X 3.0 facades and contains information specific to Services Gatekeeper not found in the specifications. For detailed descriptions of the interfaces, methods, and parameters, see the ETSI OSA Parlay X 3.0 specifications at:

http://www.etsi.org/deliver/etsi_es/202300_202399/20239111/01.02.01_60/es_ 20239111v010201p.pdf

Parlay X 3.0 Part 6: Payment

The Payment communication service interfaces follow Draft ETSI ES 202 504-6 v0.0.4 (2007-06), Open Service Access (OSA); Parlay X Web services; Part 6: Payment (Parlay X3)

Interface: AmountCharging

The **AmountCharging** interface endpoint is:

http://host:port/parlayx30/payment/AmountCharging

where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

chargeAmount

Charges the account indicated by the end user identifier.

Table 28-1 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0001	PAYMENT000002	A protocol-related error. This error is returned from the Diameter server. Make sure the server is running and reachable.
		Check the log files for more information.
SVC0001	PAYMENT000003	A transient error. This error is returned from the Diameter server, for example, in an authentication failure. Make sure the server is reachable and has adequate storage space.
		Check the log files for more information.
SVC0001	PLG-000004	General plug-in routing error.

Table 28–1 (Cont.) Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0001	PAYMENT000004	A permanent failure. This error is returned from the Diameter server, for example, when there is incorrect data in the AVP.
		Check the log files for more information.
SVC0270	PAYMENT000004	A permanent failure. This error is returned from the Diameter server containing a Diameter error code and string. The Diameter charging server returns the error code and string to Services Gatekeeper, and the Services Gatekeeper charging plug-in returns it to the calling application in the Diameter-Error-Message Xparam using this syntax:
		DIAMETERDiameter_error_code
		Diameter-Error-Message="Diameter_error_ string"
		Where Diameter_error_code and Diameter_ error_string are the codes and strings listed in Section 7.1 of Diameter RFC3588. For example:
		DIAMETER5001 Diameter-Error-Message="DIAMETER_AVP_ UNSUPPORTED"
		For details on the error codes and strings see Diameter RFC3588 Section 7.1 (http://www.ietf.org/rfc/rfc3588.txt)

refundAmount

Refunds the account indicated by the end user identifier.

Table 28–2 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0001	PAYMENT000002	A protocol-related error. This error is returned from the Diameter server. Make sure the server is running and reachable.
		Check the log files for more information.
SVC0001	PAYMENT000003	A transient error. This error is returned from the Diameter server, such as authentication failure. Make sure the server is reachable and has adequate storage space.
		Check the log files for more information.
SVC0001	PLG-000004	General plug-in routing error.
SVC0001	PAYMENT000004	A permanent failure. This error is returned from the Diameter server, such as incorrect data in the AVP.
		Check the log files for more information.

Table 28–2 (Cont.) Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0270	PAYMENT000004	A permanent failure. This error is returned from the Diameter server containing a Diameter error code and string. The Diameter charging server returns the error code and string to Services Gatekeeper, and the Services Gatekeeper charging plug-in returns it to the calling application in the Diameter-Error-Message Xparam using this syntax:
		DIAMETERDiameter_error_code Diameter-Error-Message="Diameter_error_ string"
		Where Diameter_error_code and Diameter_error_string are the codes and strings listed in Section 7.1 of Diameter RFC3588. For example:
		DIAMETER5001 Diameter-Error-Message="DIAMETER_AVP_ UNSUPPORTED"
		For details on the error codes and strings see Diameter RFC3588 Section 7.1 (http://www.ietf.org/rfc/rfc3588.txt)

chargeSplitAmount

Charges multiple end user accounts concurrently.

Table 28–3 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0001	PAYMENT000002	A protocol-related error. This error is returned from the Diameter server. Make sure the server is running and reachable.
		Check the log files for more information.
SVC0001	PAYMENT000003	A transient error. This error is returned from the Diameter server, for example, in an authentication failure. Make sure the server is reachable and has adequate storage space. Check the log files for more information.
SVC0001	PLG-000004	General plug-in routing error.
SVC0001	PAYMENT000004	A permanent failure. This error is returned from the Diameter server, for example, such as incorrect data in the AVP. Check the log files for more information.

Table 28–3 (Cont.) Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0270 PAYMENT000004	A permanent failure. This error is returned from the Diameter server containing a Diameter error code and string. The Diameter charging server returns the error code and string to Services Gatekeeper, and the Services Gatekeeper charging plug-in returns it to the calling application in the Diameter-Error-Message Xparam using this syntax:	
		DIAMETERDiameter_error_code Diameter-Error-Message="Diameter_error_ string"
		Where Diameter_error_code and Diameter_ error_string are the codes and strings listed in Section 7.1 of Diameter RFC3588. For example:
		DIAMETER5001 Diameter-Error-Message="DIAMETER_AVP_ UNSUPPORTED"
		For details on the error codes and strings see Diameter RFC3588 Section 7.1 (http://www.ietf.org/rfc/rfc3588.txt)

Interface: VolumeCharging

The **VolumeCharging** interface endpoint is:

http://host:port/parlayx30/payment/VolumeCharging

where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

chargeVolume

Charges the specified volume to the end user account.

Table 28-4 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0002	parameter	Invalid parameter value.
		Check the log files for more information.
SVC0270	PAYMENT000004	Charge failed.
		Check the log files for more information.

refundVolume

Refunds the specified volume to the end user account.

Table 28–5 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0002	parameter	Invalid parameter value.
		Check the log files for more information.
SVC0270	PAYMENT000004	Refund failed
		Check the log files for more information.

chargeSplitVolume

Charges a volume amount to multiple end user accounts based on percentages defined in a policy.

Table 28–6 **Exceptions and Error Codes**

Exception	Error Code	Explanation
SVC0002	parameter	Invalid parameter value.
		Check the log files for more information.
SVC0270	PAYMENT000004	The charge failed.
		Check the log files for more information.
SVC0271		Invalid sum of percentage allocations. The sum of percentage allocations must be 100.
POL0250		The number of endUserIdentifiers exceeds policy-defined maximum.
POL0251		Split charging is not supported by the defined policy.

getAmount

Converts the given volume to a currency amount.

chargeReservation

Charge the reserved volume to an end user account.

Table 28–7 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0002	parameter	Invalid parameter value.
		Check the log files for more information.
SVC0270	PAYMENT000004	Charge reservation failed
		Check the log files for more information.

releaseReservation

Release the reserved volume on an end user account.

Table 28–8 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0002	parameter	Invalid parameter value.
		Check the log files for more information.

Interface: ReserveAmountCharging

The **ReserveAmountCharging** interface endpoint is:

http://host:port/parlayx30/payment/ReserveAmountCharging

where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

reserveAmount

Reserves a charge for an account indicated by the end user identifier.

Table 28–9 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0001	PAYMENT000002	A protocol-related error. This error is returned from the Diameter server. Make sure the server is running and reachable.
		Check the log files for more information.
SVC0001	PAYMENT000003	A transient error. This error is returned from the Diameter server, such as authentication failure. Make sure the server is reachable and has adequate storage space.
		Check the log files for more information.
SVC0001	PLG-000004	General plug-in routing error.
SVC0001	PAYMENT000004	A permanent failure. This error is returned from the Diameter server, such as incorrect data in the AVP.
		Check the log files for more information.
SVC0270	PAYMENT000004	A permanent failure. This error is returned from the Diameter server containing a Diameter error code and string. The Diameter charging server returns the error code and string to Services Gatekeeper, and the Services Gatekeeper charging plug-in returns it to the calling application in the Diameter-Error-Message Xparam using this syntax:
		DIAMETERDiameter_error_code Diameter-Error-Message="Diameter_error_ string"
		Where Diameter_error_code and Diameter_ error_string are the codes and strings listed in Section 7.1 of Diameter RFC3588. For example:
		DIAMETER5001 Diameter-Error-Message="DIAMETER_AVP_ UNSUPPORTED"
		For details on the error codes and strings see Diameter RFC3588 Section 7.1 (http://www.ietf.org/rfc/rfc3588.txt)

reserveAdditionalAmount

Adds to or subtracts from a charge to or from an existing reservation.

Table 28–10 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0001	PAYMENT000002	A protocol-related error. This error is returned from the Diameter server. Make sure the server is running and reachable. Check the log files for more information.
SVC0001	PAYMENT000003	A transient error. This error is returned from the Diameter server, such as authentication failure. Make sure the server is reachable and has adequate storage space. Check the log files for more information.
SVC0001	PLG-000004	General plug-in routing error.

Table 28–10 (Cont.) Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0001	PAYMENT000004	A permanent failure. This error is returned from the Diameter server, such as incorrect data in the AVP.
		Check the log files for more information.
SVC0270	PAYMENT000004	A permanent failure. This error is returned from the Diameter server containing a Diameter error code and string. The Diameter charging server returns the error code and string to Services Gatekeeper, and the Services Gatekeeper charging plug-in returns it to the calling application in the Diameter-Error-Message Xparam using this syntax:
		DIAMETERDiameter_error_code Diameter-Error-Message="Diameter_error_ string"
		Where Diameter_error_code and Diameter_ error_string are the codes and strings listed in Section 7.1 of Diameter RFC3588. For example:
		DIAMETER5001 Diameter-Error-Message="DIAMETER_AVP_ UNSUPPORTED"
		For details on the error codes and strings see Diameter RFC3588 Section 7.1 (http://www.ietf.org/rfc/rfc3588.txt)

chargeReservation

Charges to a reservation indicated by the reservation ID.

Table 28–11 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0001	PAYMENT000002	A protocol-related error. This error is returned from the Diameter server. Make sure the server is running and reachable.
		Check the log files for more information.
SVC0001	PAYMENT000003	A transient error. This error is returned from the Diameter server, such as authentication failure. Make sure the server is reachable and has adequate storage space.
		Check the log files for more information.
SVC0001	PLG-000004	General plug-in routing error.
SVC0001	PAYMENT000004	A permanent failure. This error is returned from the Diameter server, such as incorrect data in the AVP.
		Check the log files for more information.

Table 28-11 (Cont.) Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0270	PAYMENT000004	A permanent failure. This error is returned from the Diameter server containing a Diameter error code and string. The Diameter charging server returns the error code and string to Services Gatekeeper, and the Services Gatekeeper charging plug-in returns it to the calling application in the Diameter-Error-Message Xparam using this syntax:
		DIAMETERDiameter_error_code Diameter-Error-Message="Diameter_error_ string"
		Where Diameter_error_code and Diameter_ error_string are the codes and strings listed in Section 7.1 of Diameter RFC3588. For example:
		DIAMETER5001 Diameter-Error-Message="DIAMETER_AVP_ UNSUPPORTED"
		For details on the error codes and strings see Diameter RFC3588 Section 7.1 (http://www.ietf.org/rfc/rfc3588.txt)

releaseReservation

Returns funds left in a reservation to the account from which this reservation was made.

Table 28–12 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0001	PAYMENT00000 2	A protocol-related error. This error is returned from the Diameter server. Make sure the server is running and reachable.
		Check the log files for more information.
SVC0001	PAYMENT00000 3	A transient error. This error is returned from the Diameter server, such as authentication failure. Make sure the server is reachable and has adequate storage space.
		Check the log files for more information.
SVC0001	PLG-000004	General plug-in routing error.
SVC0001	PAYMENT00000 4	A permanent failure. This error is returned from the Diameter server, such as incorrect data in the AVP.
		Check the log files for more information.

Table 28-12 (Cont.) Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0270	PAYMENT00000 4	A permanent failure. This error is returned from the Diameter server containing a Diameter error code and string. The Diameter charging server returns the error code and string to Services Gatekeeper, and the Services Gatekeeper charging plug-in returns it to the calling application in the Diameter-Error-Message Xparam using this syntax:
		DIAMETERDiameter_error_code Diameter-Error-Message="Diameter_error_ string"
		Where Diameter_error_code and Diameter_ error_string are the codes and strings listed in Section 7.1 of Diameter RFC3588. For example:
		DIAMETER5001 Diameter-Error-Message="DIAMETER_AVP_ UNSUPPORTED"
		For details on the error codes and strings see Diameter RFC3588 Section 7.1 (http://www.ietf.org/rfc/rfc3588.txt)

Interface: ReserveVolumeCharging

The **ReserveVolumeCharging** interface endpoint is:

http://host:port/parlayx30/payment/ReserveVolumeCharging

where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

reserveVolume

Reserves a volume amount for the end user account.

Table 28-13 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0001	PAYMENT000002	Service error.
		Check the log files for more information.
SVC0002	parameter	Invalid parameter value.
		Check the log files for more information.
POL0001		Policy error.
		Check the log files for more information.

reserveAdditionalVolume

Adds or reduces a volume amount to for an existing reservation on an end user account.

Table 28–14 Exceptions and Error Codes

Exception	Error Code	Explanation
SVC0002	parameter	Invalid parameter value.
		Check the log files for more information.

getAmountReserveCharging

Converts a reserved volume to a currency amount.

Parlay X 3.0 Part 13: Address List Management

The Address List Management communication service interfaces follow 3GPP TS 29.199-13 V7.0.2 (2007-06), Open Service Access (OSA); Parlay X Web services; Part 13: Address List Management (Parlay X 3).

Interface: GroupManagement

This section describes the **GroupManagement** interface.

The GroupManagement interface endpoint is:

http://host:port/parlayx30/address_list/GroupManagement

where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

createGroup

Creates an Address List Management group.

Table 28-15 Exceptions and Error Codes

Exception	Error Code	Explanation	
POL0212	n/a	Group name too long.	
POL0213	n/a	Group already exists.	

queryGroups

Queries an Address List Management group to return details about a particular group attribute, which is specified by attributeName.

deleteGroup

Deletes the specified Address List Management group.

setAccess

Sets access permissions for a member of an Address List Management group.

queryAccess

Queries the access permissions set for the group member passed in the requester parameter.

General Exceptions

See "General Exceptions".

Interface: Group

This section describes the **Group** interface.

The Group interface endpoint is:

http://host:port/parlayx30/address_list/Group

where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

addMember

Adds a single member to an Address List Management group.

addMembers

Adds multiple members to an Address List Management group.

Table 28–16 Exceptions and Error Codes

Exception	Error Code	Explanation	
POL0210	n/a	Too many members in group.	
POL0210	n/a	Subgroups not allowed.	

queryMembers

Deletes the specified Address List Management group.

deleteMember

Deletes a single member from an Address List Management group.

deleteMembers

Deletes multiple members from an Address List Management group.

addGroupAttribute

Adds an attribute to an Address List Management group.

queryGroupAttribute

Queries an Address List Management group for the value associated with the passed attribute name. The attribute's value and status are returned.

deleteGroupAttribute

Deletes an attribute from an Address List Management group.

addGroupMemberAttribute

Adds an attribute to a member of an Address List Management group.

queryGroupMemberAttributes

Queries a member of an Address List Management group for list of attributes attached to the member.

deleteGroupMemberAttribute

Deletes an attribute from a member of an Address List Management group.

Interface: Member

This section describes the **Member** interface.

The Member interface endpoint is:

http://host:port/parlayx30/address_list/Member

where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

addMemberAttribute

Adds an attribute to a member outside of the context of a particular Address List Management group.

queryMemberAttributes

Queries a list of attributes for a member and retrieves their values.

deleteMemberAttribute

Deletes an attribute from a member.

Parlay X 3.0 Part 18: Device Capabilities and Configuration

The Device Capabilities and Configuration communication service interfaces follow ETSI ES 202 504-18 v0.0.1(2007-06), Open Service Access (OSA); Parlay X Web services; Part 18: Device Capabilities and Configuration (Parlay X 3).

Interface: DeviceCapabilities

This section describes the **DeviceCapabilities** interface.

The Device Capabilities interface endpoint is:

http://host:port/parlayx30/rest/device_capabilities

where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

getCapabilities

Retrieves the following capability information for a device:

- The device's unique ID.
- The name and model of the device.
- A link to the UAProf file.

getDeviceId

Retrieves the device's equipment identifier.

General Exceptions

See "General Exceptions".

Interface: DeviceCapabilitiesNotificationManager

This section describes the DeviceCapabilitiesNotificationManager interface.

startNotification

Not supported.

endNotification

Not supported.

Interface: DeviceCapabilitiesNotification

This section describes the **DeviceCapabilitiesNotification** interface.

deviceNotification

Not supported.

deviceError

Not supported.

deviceEnd

Not supported.

Interface: DeviceConfiguration

This section describes the DeviceConfiguration interface.

pushConfiguration

Not supported.

getConfigurationList

Not supported.

getConfigurationHistory

Not supported.

General Exceptions

This section describes the exception handling for the Parlay X 3.0 interfaces.

The following exception types are defined:

- Service exceptions
- Policy exceptions

Service exceptions are related to the operation of the service itself. The following exceptions are general:

- SVC0001: Service error.
- SVC0002: Invalid input value
- SVC0003: Invalid input value with list of valid values
- SVC0004: No valid addresses
- SVC0005: Duplicate correlator
- SVC0006: Invalid group
- SVC0007: Invalid charging information
- SVC0008: Overlapping Criteria

Policy exceptions are thrown when a policy has been violated, including violations of a service level agreements. The following general policy exceptions are defined:

- POL0001: Policy error
- POL0002: Privacy error
- POL0003: Too many addresses specified
- POL0004: Unlimited notifications are not supported
- POL0005: Too many notifications requested
- POL0006: Groups not allowed
- POL0007: Nested groups not allowed
- POL0008: Charging not supported
- POL0009: Invalid frequency requested

Within the exception, an error code is defined. The error code details why the exception was thrown.

About the Supported SOAP Parlay X 4.0 Facades

This chapter describes the Oracle Communications Services Gatekeeper interfaces in the supported Parlay X 4.0 facades and contains information specific to Services Gatekeeper not found in the specifications. For detailed descriptions of the interfaces, methods, and parameters, refer to the specifications, see the ETSI OSA Parlay X 4.0 specifications at:

http://www.3gpp.org/DynaReport/29199-01.htm

Parlay X 4.0 Part 17 Application-Driven QoS

The application driven QoS communication service interfaces follow.ETSI ES 202 504-17 V1.1.1 (2008-05) Open Service Access (OSA); Parlay X Web services; Part 17: Application-driven Quality of Service (QoS); Parlay X 3.

See the specification at the ETSI website:

http://www.etsi.org/deliver/etsi_es/202500_202599/20250417/01.01.01_60/es_ 20250417v010101p.pdf

See the discussion on Parlay X 4.0 application-driven quality of service (QoS) in Services Gatekeeper Communication Service Reference Guide for details on the supported operations.

There are two interfaces available for this specification:

- Interface: Application-driven QoS
- Interface: ApplicationQoSNotificationManager

Interface: Application-driven QoS

The Application-driven Quality of Service interface endpoint is:

http://host:port/parlayx40/qos/ApplicationQoS

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

These operations are available to applications to manage QoS requests. These operations are also available from the Platform Test Environment (PTE) graphical user interface:

- applyQoSFeature
- getQoSHistory

- getQoSStatus
- modify QoSF eature
- notifyQoSEvent
- removeQoSFeature

applyQoSFeature

Applications use this operation to apply the connection settings in a temporary QoS feature profile to a subscriber connection.

Table 29–1 lists the **applyQoSFeature** request parameters.

Table 29-1 applyQoSFeature Request Parameters

Name	Data Type/Values	Mandato ry?	Description
endUserIdentifier	xsd:anyURI	Yes	Identifies the network subscriber for which to apply the QoS feature profile for. Uses the standard URI format: tel:[0-9]
qoSFeatureIdentifier	xsd:string	Yes	The name of the QoS feature profile to apply to the subscriber connection. The QoS feature profile must exist before use, so use the Operation: loadQoSRequestTemplate MBean operation to create it first.
defaultQoSFeature	xsd:boolean	Yes	Always set to false.
modifyExistingSession	xsd:boolean	No	Always set to false.
qosFeatureProperties	QoSFeatureProp erties	No	Specifies values for the configurable service attributes that apply to the temporary QoS feature profile.
qosFeatureProperties.Durati on	common:TimeM etri	No	The duration of the QoS feature profile being applied. Supported units of measurement are Second, Minute, Hour, Day, Week, Month, Year. A 0 or negative value extends the duration for the entire session.
qosFeatureProperties.UpStre amSpeedRate	xsd:string	No	The upload speed rate of the QoS feature profile. The format is [0-9]bps Kbps Mbps Gbps Tbps. The maximum value is 4294967295bps.
qosFeatureProperties.DownS treamSpeedRate	xsd:string	No	The download speed rate of the QoS feature profile. The format is [0-9]bps Kbps Mbps Gbps Tbps. The maximum value is 4294967295bps
qosFeatureProperties.OtherProperties	Property[0unb ounded	No	The attribute-value pairs that replace the default values defined in QoS feature profile. For example, you can define an application identifier variable in the QoS feature profile: <applicationidentifier parametername="\$APP_ID">test_appId</applicationidentifier> And then specify a value for the variable by setting applicationIdentifier to app_id: "\$APP_ID=app_id"

Request Example This example shows a request that attempts to apply a QoS feature profile named pxt to the tel:555012 subscriber, for a duration of 7200 seconds (120 minutes, or 2 hours). The upload rate is 1000 Mbps and the download rate is 1000 Kbps:

```
<S:Bodv>
             <ns2:applyQoSFeature
         xmlns:ns2="http://www.csapi.org/schema/parlayx/adq/v4_0/local"
         xmlns:ns3="http://www.csapi.org/schema/parlayx/common/v4_0">
         <ns2:endUserIdentifier>tel:555012
         <ns2:qoSFeatureIdentifier>pxt</ns2:qoSFeatureIdentifier>
         <ns2:defaultOoSFeature>false/ns2:defaultOoSFeature>
         <ns2:modifyExistingSession>false</ns2:modifyExistingSession>
         <ns2:qosFeatureProperties>
         <duration>
              <metric>Second</metric>
              <units>7200</units>
         </duration>
         <upStreamSpeedRate>1000 Mbps</upStreamSpeedRate>
         <downStreamSpeedRate>1000 kbps</downStreamSpeedRate>
         </ns2:gosFeatureProperties>
    </ns2:applyQoSFeature>
</S:Body>
```

Response Parameters Table 29–3 lists the applyQoSFeature response parameters.

Table 29–2 applyQoSFeature Response Parameters

Name	Data Type	Mandat ory?	Description
result	QoSFeatureDat a	Yes	Details of the actions taken as a result of the QoS feature profile request.
result.requestID	XSD:string	Yes	A unique request identifier generated by this communication service and used by the application to identify this specific invocation of the applyQoSFeature operation.
result.qoSFeatureIdentifie r	XSD:string	Yes	A name that uniquely identifies the QoS feature profile being applied temporarily to the subscriber's connection.
actualProperties	QoSFeaturePro perties	No	The AVPs returned by the PCRF.

Response Example This example shows a response to an applyQoSFeature request. It identifies the pxt feature profile that the QoS applies to, and Diameter Rx session details.

```
<env:Body>
    <loc:applyQoSFeatureResponse</pre>
    xmlns:loc="http://www.csapi.org/schema/parlayx/adq/v4_0/local">
    <loc:result>
         <requestId>localhost;1385973500;0-1386001353054</requestId>
          <qoSFeatureIdentifier>pxt</qoSFeatureIdentifier>
          <actualProperties>
              <duration>
                    <metric>Second</metric>
                    <units>6000</units>
              </duration>
                    <upStreamSpeedRate>100000000bps</upStreamSpeedRate>
                    <downStreamSpeedRate>1000000bps</downStreamSpeedRate>
                    <otherProperties>
                         <name>supportedFeatures[0].vendorId
                         <value>10415</value>
                    </otherProperties>
                    <otherProperties>
```

```
<name>supportedFeatures[0].featureListID</name>
                         <value>1</value>
                    </otherProperties>
                    <otherProperties>
                         <name>ratType</name>
                         <value>WLAN</value>
                    </otherProperties>
                    <otherProperties>
                        <name>ipcanType</name>
                         <value>_3GPP-GPRS</value>
                    </otherProperties>
                    <otherProperties>
                        <name>supportedFeatures[0].featureList</name>
                        <value>2</value>
                    </otherProperties>
               </actualProperties>
          </loc:result>
     </loc:applyQoSFeatureResponse>
</env:Body>
```

getQoSHistory

Applications use this operation to return a list of the QoS transactions (feature profile requests and responses) for a subscriber. You can filter the list by specifying:

- A QoS feature profile identifier
- A maximum number of transactions
- A date and time limit
- Additional custom criteria that you create

After a request/response, there is approximately a 20-second delay before its record is available to getQoSHistory. To avoid filling up the database, request/response records are maintained for a period of 30 days and then deleted.

Request Parameters Table 29–3 lists the **getQoSHistory** request parameters.

Table 29-3 getQoSHistory Request Parameters

Name	Data Type	Manda tory?	Description
endUserIdentifier	XSD:anyURI	Yes	Identifies the subscriber for which to get a history. Uses the standard URI format.
qosFeatureIdentifier	XSD:string	No	The name of the QoS feature profile this operation returns a history for. If not specified, a history is returned for all feature profiles for this subscriber.
date	XSD:datTime	No	Limits the history returned to the date and time specified. If not specified, a history is returned for this subscriber for the previous minute only.
maxEntries	XSD:Integer	No	Specifies the maximum number of QoS feature profile requests and responses to return. If not specified (or a value of 0 is specified) the maximum is set to 10. The largest value allowed is 100.
additionalCriteria	Property[0unbou nded]	No	Not implemented in this release.

Request Example This example shows a request for a QoS feature profile history of requests and responses for the subscriber tel:555012, for the pxt feature, that transpired on December 12th, 2013 at 01:33:53.

```
<S:Body>
     <ns2:getQoSHistory
         xmlns:ns2="http://www.csapi.org/schema/parlayx/adq/v4_0/local"
          xmlns:ns3="http://www.csapi.org/schema/parlayx/common/v4_0">
          <ns2:endUserIdentifier>tel:555012</ns2:endUserIdentifier>
          <ns2:goSFeatureIdentifier>pxt</ns2:goSFeatureIdentifier>
          <ns2:date>2013-12-05T01:33:53Z</ns2:date>
          <ns2:maxEntries>10</ns2:maxEntries>
    </ns2:getQoSHistory>
</S:Body>
```

Response Parameters Table 29–4 lists the getQoSHistory response parameters.

Table 29-4 getQoSHistory Response Parameters

Name	Data Type	Mandat ory?	Description
transactionDateTime	XSD:date Time	Yes	Specifies the transaction time.
transactionDetails	XSD:strin	Yes	Specifies the request/response details.
	g		The details name the portion of the name/value pairs separated by the # symbol. The name portion of the name/value pairs include:
			■ startTime
			■ endTime
			requstId
			duration
			■ featureName
			A list of request/response records, including the transaction time and a list of the modified variables.

Response Example This example shows an example of a history returned to the application:

```
<env:Body>
    <loc:getQoSHistoryResponse</pre>
         xmlns:loc="http://www.csapi.org/schema/parlayx/adq/v4_0/local">
         <loc:result>
<transactionDateTime>2013-12-05T09:33:53.522+08:00
<transactionDetails>requestId=localhost;1386206978;0-1386207233485#duration=7200
seconds#endTime=2013-12-05 09:53:42#featureName=pxt#modification:time=
1386207684611#duration=9600seconds#$FLOW_DESCRIPTION_0=permit out ip from any to
any#</transactionDetails>
    </loc:result>
    </le>
</env:Body>
```

getQoSStatus

Applications use this operation to retrieve the status and details of a subscriber's current QoS feature profile.

Request Parameters Table 29–5 lists the getQoSStatus request parameters.

Table 29–5 getQoSStatus Request Parameters

Name	Data Type	Mandatory?	Description
endUserIdentifier	XSD:any URI	Yes	Identifies a subscriber to obtain QoS details for.

Request Example This example requests QoS details for subscriber tel:555012.

```
<S:Body>
     <ns2:getQoSStatus xmlns:ns2="http://www.csapi.org/schema/parlayx/adq/v4_</pre>
0/local"
          xmlns:ns3="http://www.csapi.org/schema/parlayx/common/v4_0">
          <ns2:endUserIdentifier>tel:555012</ns2:endUserIdentifier>
     </ns2:getQoSStatus>
</S:Body>
```

Response Parameters Table 29–6 lists the **getQoSStatus** response parameters.

Table 29-6 getQosStatus Response Parameters

Name	Data Type	Mandatory?	Description
result	QosStatus	Yes	Returns the status of a subscriber connection, including information about the temporary QoS feature profile details that are currently activated.
result.userIsConnected	XSD:Boolean	Yes	Specifies whether the subscriber account is currently connected (true or false).
result.defaultQoSFeatur eIdentifier	XSD:string	No	Not used because setting a default QoS feature profile is not supported.
trafficClasses	TrafficClass[0unbounded]	No	Not used because setting a default QoS feature profile is not supported.
qosFeatureStatuses	QoSFeatureD ata[0unbou nded]	No	An array of the QoS feature profile details for the subscriber.

Response Example This example shows the QoS status details returned for a subscriber:

```
<env:Body>
     <loc:getQoSStatusResponse</pre>
          xmlns:loc="http://www.csapi.org/schema/parlayx/adq/v4_0/local">
          <loc:result>
               <userIsConnected>true</userIsConnected>
               <gosFeatureStatuses>
                    <requestId>localhost;1386206978;0-1386207233485</requestId>
                    <qoSFeatureIdentifier>pxt</qoSFeatureIdentifier>
                    <actualProperties>
                         <duration>
                              <metric>Second</metric>
                              <units>9600</units>
                         </duration>
                         <upStreamSpeedRate>100000000bps</upStreamSpeedRate>
```

```
<downStreamSpeedRate>1000000bps</downStreamSpeedRate>
                         <otherProperties>
                              <name>supportedFeatures[0].vendorId</name>
                              <value>10415</value>
                         <otherProperties>
                         <otherProperties>
                              <name>supportedFeatures[0].featureListID</name>
                              <value>1</value>
                         </otherProperties>
                         <otherProperties>
                              <name>ratType</name>
                              <value>WLAN</value>
                         </otherProperties>
                         <otherProperties>
                              <name>ipcanType</name>
                              <value>_3GPP-GPRS</value>
                         </otherProperties>
                         <otherProperties>
                              <name>supportedFeatures[0].featureList</name>
                              <value>2</value>
                         </otherProperties>
                    </actualProperties>
               </gosFeatureStatuses>
          </loc:result>
</loc:getQoSStatusResponse>
</env:Body>
```

modifyQoSFeature

Applications use this operation to alter a QoS feature profile that has already been applied using "applyQoSFeature". Specify the attributes you want to change in the QoS feature profile. Any other attributes remain as originally set. Remember that the new values only take effect for the time limit set by the qosFeatureProperties.Duration attribute of "applyQoSFeature"

This operation must take place inside an active application session, and you must send in the request ID generated by **applyQosFeature**.

Request Parameters Table 29–7 lists the **modifyQoSFeature** request parameters:

Table 29–7	modify	Request Parameters			
				_	

Name	Data Type	Mandat ory?	Description
requestID	XSD:string	Yes	Specifies the unique request identifier generated by this communication service from the original "applyQoSFeature" operation.
requestProperties	QoSFeatureP roperties	Yes	Specifies new values of the attributes of the QoS feature profile.

Request Example This example shows a request that modifies the QoS feature profile identified as localhost;1386206978;0-1386207233485. It changes the values of the upStreamSpeedRate, downStreamSpeedRate, and flow description attributes.

```
<S:Body>
    <ns2:modifyQoSFeature
         xmlns:ns2="http://www.csapi.org/schema/parlayx/adq/v4_0/local"
         xmlns:ns3="http://www.csapi.org/schema/parlayx/common/v4_0">
```

```
<ns2:requestId>localhost;1386206978;0-1386207233485/ns2:requestId>
          <ns2:requestProperties>
              <duration>
                   <metric>Second</metric>
                    <units>9600</units>
              </duration>
              <upStreamSpeedRate>1000 Mbps</upStreamSpeedRate>
              <downStreamSpeedRate>1000 kbps</downStreamSpeedRate>
               <otherProperties>
                    <name>$FLOW_DESCRIPTION_0</name>
                    <value>permit out ip from any to any</value>
                    <description></description>
              </otherProperties>
          </ns2:requestProperties>
    </ns2:modifyQoSFeature>
</S:Body>
```

Response Parameters Table 29–8 lists the **modifyQoSFeature** response parameters.

Table 29-8 modifyQoSFeature Response Parameters

Name	Data Type	Mandator y?	Description
result	QoSFeatur eProperties	Yes	Specifies the attributes that have been modified and their values.

Response Example This example shows the attributes changed by **modifyQoSFeature**. The modified attributes are returned in the **result** array.

```
<env:Body>
          <loc:modifyQoSFeatureResponse
               xmlns:loc="http://www.csapi.org/schema/parlayx/adq/v4_0/local">
               <loc:result>
                    <duration>
                         <metric>Second</metric>
                         <units>9600</units>
                    </duration>
                    <upStreamSpeedRate>1000 Mbps</upStreamSpeedRate>
                    <downStreamSpeedRate>1000 kbps</downStreamSpeedRate>
                    <otherProperties>
                        <name>$FLOW_DESCRIPTION_0
                         <value>permit out ip from any to any</value>
                         <description></description>
                    </otherProperties>
              </loc:result>
          </loc:modifyQoSFeatureResponse>
</env:Body>
```

notifyQoSEvent

Your PCRF uses this operation to report certain network events that occurred against one or more subscriber's active QoS features profiles.

Request Parameters Table 29–9 lists the **notifyQoSEvent** request parameters.

notifyQoSEvent Request Parameters Table 29–9

Name	Data Type	Mandato ry?	Description
correlator	xsd:string	yes	The correlator identifying the original notification registration.
endUserIdentities	xsd:anyURI[1unbound ed]	Yes	The network subscribers associated with the event.
eventType	QoSEvent	Yes	The event being reported.

Response Parameters There are no response parameters.

removeQoSFeature

Applications use this operation to remove an active temporary QoS feature profile, and return the QoS values to the state they were in before the temporary QoS feature profile was applied.

This operation must take place inside an active session.

Request Parameters Table 29–10 lists the **removeQoSFeature** request parameters.

Table 29-10 removeQoSFeature Request Parameters

Name	Data Type	Mandatory?	Description
requestID	XSD:String		Contains the unique request ID generated by the original applyQoSFeature call.

Request Example This example shows a removeQoSFeature request that removes the temporary QoS feature profile identified as localhost;1386206978;0-1386207233485:

```
<S:Bodv>
     <ns2:removeQoSFeature</pre>
          xmlns:ns2="http://www.csapi.org/schema/parlayx/adq/v4_0/local"
          xmlns:ns3="http://www.csapi.org/schema/parlayx/common/v4_0">
          <ns2:requestId>localhost;1386206978;0-1386207233485</ns2:requestId>
     </ns2:removeOoSFeature>
</S:Body>
```

Response Parameters Table 29–11 lists the removeQoSFeature response parameters.

Table 29-11 removeQoSFeature Response Parameters

Name	Data Type	Mandatory?	Description
result	XSD:boolean		Returns true if the QoS feature profile was successfully removed.

Response Example This example shows a response to a request to remove a temporary QoS feature profile in which the removal was successful:

```
<env:Body>
     <loc:removeQoSFeatureResponse</pre>
          xmlns:loc="http://www.csapi.org/schema/parlayx/adq/v4_0/local">
          <loc:result>true</loc:result>
     </loc:removeQoSFeatureResponse>
</env:Body>
```

Interface: ApplicationQoSNotificationManager

The Application-driven Quality of Service interface endpoint is:

http://host:port/parlayx40/qos/ApplicationQoSNotificationManager

Where values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

These operations are available to applications to manage start and stop QoS notification. These operations are also available from the Platform Test Environment (PTE) graphical user interface:

- startQoSNotification
- stopQoSNotification

startQoSNotification

Applications use this operation to register interest in receiving notifications of specific event types for a subscriber.

Request Parameters Table 29–12 lists the **startQoSNotification** request parameters.

Table 29–12 startQoSNotification Request Parameters

Name	Data Type	Mandato ry?	Description
reference	common:SimpleReference	Yes	The application end point to receive event notifications.
reference.Endpoint	xsd:anyURI	Yes	The end point address.
reference.InterfaceNa me	xsd:string	Yes	The interface name.
reference.Correlator	xsd:string	Yes	Correlation information.
endUserIdentities	xsd:anyURI[1unbounded]	Yes	The subscriber for which to monitor events.
eventCriteria	QoSEvent[1unbounded]	Yes	The events to be monitored.

Table 29–13 lists the event definitions that you use for the events request parameter to startQoSNotifiation.

startQoSNotification event Definitions Table 29-13

Event Name	Description	Trigger Condition
AbnormalConnectionTermination	The subscriber connections were terminated abnormally by a network fault that released all temporary QoS feature profile requests.	This communication service can not detect this kind of event, so you must use this event definition for all abnormal terminations.
NormalConnectionTermination	The subscriber connections were terminated normally (for example, the subscriber logged off), which automatically released all of the temporary QoS feature profile requests.	This event is triggered by a Diameter Rx abort session request (ASR) message.
TemporaryQoSFeatureReleased	An active temporary QoS feature profile request on a subscriber connection was released, because it reached a threshold specified by one of the service attributes.	This event is triggered by this communication service when a QoS feature profile duration expires.

Request Example This example shows an application requesting notifications for the subscriber tel:555012 for both normal network connection terminations and temporary QoS feature profiles released.

```
<S:Body>
    <ns2:startQoSNotification</pre>
         xmlns:ns2="http://www.csapi.org/schema/parlayx/adq/notification_
manager/v4_0/local"
         xmlns:ns3="http://www.csapi.org/schema/parlayx/common/v4_0">
         <ns2:reference>
            <endpoint>http://endpoint_host.port/jaxws/QoSNotification</endpoint>
            <interfaceName>interfaceName</interfaceName>
            <correlator>987654321
         </ns2:reference>
         <ns2:endUserIdentities>tel:555012</ns2:endUserIdentities>
         <ns2:eventCriteria>NormalConnectionTermination/ns2:eventCriteria>
         <ns2:eventCriteria>TemporaryQoSFeatureReleased/ns2:eventCriteria>
    </ns2:startQoSNotification>
</S:Body>
```

Response Parameters There are no response parameters because the connections have been terminated.

stopQoSNotification

Applications use this operation to cancel notification registrations started by startQoSNotification.

Request Parameters Table 29–14 lists the **stopQoSNotification** request parameters.

Table 29-14 stopQoSNotification Request Parameter

Name	Data Type	Mandat ory?	Description
correlator	XSD:string	Yes	The correlator identifying the original notification registration.

Response Parameters There are no response parameters.

About the Supported SOAP Native Facade

This chapter describes the Oracle Communications Services Gatekeeper interfaces in the supported SOAP Native facade and contains information specific to Services Gatekeeper not found in the specifications.

About the Native Interfaces

This chapter provides details on these supported native interfaces:

- MM7
- **SMPP**
- **UCP**

MM7

The MM7 specification is available from the 3GPP website:

```
http://www.3gpp.org/ftp/Specs/html-info/23140.htm
```

Messages are compliant with the schema defined by Rel-5-MM7-1-2.xsd. Because the network-facing interface supports Rel-5-MM7-1-5.xsd, Rel-5-MM7-1-2.xsd and a modified version of REL-5-MM7-1-0.xsd, some mapping may be done during processing.

The endpoint for this interface is:

http://host:port/mm7/Mms

where values for host and port are the host name and port of the system on which Services Gatekeeper is installed.

Note: The MM7 interface uses HTTP basic authentication, username/password. The username is the application instance ID.

Supported MM7 Operations

Services Gatekeeper supports the following MM7 operations:

- MM7_submit
- MM7_deliver
- MM7_cancel
- MM7_replace

- MM7_delivery_report
- MM7_read_reply_report

MM7_submit

Sends an application-initiated multimedia message

Table 30-1 Error Codes

Error code	Reason/Action			
4006	Service unavailable. Communication error within Services Gatekeeper or between Services Gatekeeper and the MMSC			
	Transient error. The client should try again.			
4007	Service denied. The request was not allowed by policy.			
	Contact the Services Gatekeeper administrator.			
<all codes="" fault="" mmsc=""></all>	Passed along transparently			
	Contact the Services Gatekeeper administrator.			

MM7_deliver

Services Gatekeeper delivers a network-triggered message to the application, at an endpoint implemented by the application.

MM7 cancel

Not supported.

MM7_replace

Not supported

MM7_delivery_report

Services Gatekeeper delivers a delivery report on a previously sent message to the application, at an endpoint implemented by the application.

MM7_read_reply_report

Services Gatekeeper delivers a read reply report on a previously sent message to the application, at an endpoint implemented by the application.

SMPP

The native SMPP communication service exposes SMPP version 3.4 to applications.

The specification is the Short Message Peer to Peer, Protocol Specification v3.4, Document Version:- 12-Oct-1999 Issue 1.2. It can be downloaded from

http://smsforum.net/

The native SMPP communication service supports all Protocol Data Units (PDUs) for SMPP version 3.4, and all header and body elements except when stated otherwise.

The native SMPP communication service also supports the billing identification parameter in the format defined by SMPP Specification 5.1, section 4.8.4.3. This parameter works with SMPP 5.1 SMSCs. Services Gatekeeper supports it as a tunneled parameter named **smpp_billing_id**. It also supports the ussd_service_operation parameter, which was expanded to support the deliver_sm opration in SMPP 5.1.

Services Gatekeeper supports it as a tunneled parameter named ussd_service_ operation. For details about these tunneled parameters, see the discussion on the Tunneled Parameters for Parlay X 2.1 Short Messaging / SMPP in Services Gatekeeper Communication Service Reference Guide.

An application using this interface acts as an External Short Message Entity (ESME).

Bind PDUs and Sessions

An application must bind to the native SMPP communications service. It can bind using:

- bind transmitter PDU
- bind receiver PDU
- bind transceiver PDU

As a result of a bind operation, Services Gatekeeper authenticates the application and establishes a session.

The following is valid for all bind operations:

- An application binds using host name or IP address and port that depends on the installation. The server to bind to is a network tier server.
- The system_id field must be the application instance group ID assigned to the application instance.
- The password field must be the same as the password for the application instance group.

A session is maintained until the application sends an "unbind PDU".

Services Gatekeeper can be configured to allow a limited number of sessions per application through the maxSession parameter of the addApplicationSpecificSettings operation. See Services Gatekeeper Communication Service Reference Guide for information about this operation.

Services Gatekeeper can be configured to terminate a session if:

- The session is inactive. See the **InactivityTimerValue** in *Services Gatekeeper* Communication Service Reference Guide.
- The application takes too long time to respond to a request. See the **RequestTimerValue** in Services Gatekeeper Communication Service Reference Guide.

Error Handling

All errors are reported in the command_status field of a response PDU.

Table 30–2 lists the error codes that are specific for Services Gatekeeper. Errors from the SMSC are transparently forwarded to the application.

Table 30–2 Error 0	Codes for SMPP	Communication Service
--------------------	----------------	-----------------------

	Error Code in Response	
SMPP PDU	(command_status)	Description
bind_transmitter	ESME_RBINDFAIL	Could not bind.
bind_receiver	ESME_RBINDFAIL	Could not bind.
bind_transceiver	ESME_RBINDFAIL	Could not bind.

Table 30–2 (Cont.) Error Codes for SMPP Communication Service

	Error Code in Response	
SMPP PDU	(command_status)	Description
submit_sm	ESME_RTHROTTLED	Throttling limit or quota limit exceeded.
		The application has performed too many requests per time unit and has exceeded the Service Level Agreement.
N/A	ESME_RSUBMITFAIL	Could not submit the message. Possible reasons include time-out encountered when sending the message and configuration error.
submit_sm_multi	ESME_RTHROTTLED	Same as for submit_sm.
N/A	ESME_RSUBMITFAIL	Same as for submit_sm.

Supported Operations

The following operations are supported or not supported as indicated.

bind_transmitter PDU

The application binds to Services Gatekeeper as an SMPP transmitter.

bind_transmitter_resp PDU

Services Gatekeeper sends this PDU to an application as a response to "bind_ transmitter PDU".

bind receiver PDU

The application binds as an SMPP receiver to Services Gatekeeper.

The address_range field must be the same as provisioned for the application instance group in the addressRange parameter to the addApplicationSpecificSettings operation. See Services Gatekeeper Communication Service Reference Guide for information about this operation.

bind_receiver_resp PDU

Services Gatekeeper sends this PDU to an application as a response to "bind_receiver PDU".

bind transceiver PDU

The application binds as an SMPP transceiver to Services Gatekeeper.

The address_range field must be the same as provisioned for the application instance group in the addressRange parameter to the addApplicationSpecificSettings operation. See Services Gatekeeper Communication Service Reference Guide for information about this operation.

bind_transceiver_resp PDU

Services Gatekeeper sends this PDU to an application as a response to "bind_ transceiver PDU".

outbind PDU

Not supported.

unbind PDU

The application unbinds from Services Gatekeeper.

unbind resp PDU

Services Gatekeeper sends this PDU to an application as a response to "unbind PDU".

generic_nack PDU

Services Gatekeeper sends this PDU as a negative acknowledgement of a PDU sent from the application if the PDU can not be recognized.

If this PDU is sent from the application, it is propagated to the SMPP SMSC.

submit sm PDU

The application sends a short message to Services Gatekeeper, which forwards it to the destination address using an SMSC.

submit sm resp PDU

Services Gatekeeper sends this PDU to an application as a response to "submit_sm PDU".

submit multi PDU

The application sends a short message to Services Gatekeeper, which forwards it to a set of destination addresses using an SMSC.

submit_multi_resp PDU

Services Gatekeeper sends this PDU to an application as a response to "submit_multi PDU".

deliver sm PDU

Services Gatekeeper sends this PDU to an application upon receiving from an SMSC a network-triggered short message that matches the destination addresses that the application is interested in. The PDU contains the short message.

The application expresses interest by subscribing for notifications addressed to specific destination addresses.

deliver_sm_resp PDU

The application sends this PDU to acknowledge the reception of a "deliver_sm PDU".

data sm PDU

Not supported.

data_sm_resp PDU

Not supported.

query_sm PDU

The application sends this PDU to query the status of a previously-sent short message.

The communication service can be configured to allow or block this operation through the subsequentOperationsAllowed parameter to the addApplicationSpecificSettings operation.

query_sm_resp PDU

Services Gatekeeper sends this PDU to an application as a response to "query_sm PDU".

cancel sm PDU

The application sends this PDU to cancel the sending of one more previously-sent short messages, if the message has not yet been delivered to the end-user terminal.

The communication service can be configured to allow or block this operation through the subsequentOperationsAllowed parameter to the addApplicationSpecificSettings operation.

cancel_sm_resp PDU

Services Gatekeeper sends this PDU to an application as a response to "cancel_sm PDU".

replace sm PDU

The application sends this PDU to replace a previously-sent short message with the short message provided in this PDU, if the message has not yet been delivered to the end-user terminal.

The communication service can be configured to allow or block this operation through the subsequentOperationsAllowed parameter to the addApplicationSpecificSettings operation. See Services Gatekeeper Communication Service Reference Guide for information about this operation.

replace sm resp PDU

Services Gatekeeper sends this PDU to an application as a response to "replace_sm PDU".

enquire link PDU

The application or Services Gatekeeper sends this PDU to verify the connection between the application and Services Gatekeeper.

The communication service can be configured to send this PDU to the application on a regular interval. When an application receives this PDU it must respond with "enquire_link_resp PDU" within the configured time-interval. See the

EnquireLinkTimerValue attribute for the native SMPP plug-in in *Services Gatekeeper* Communication Service Reference Guide.

enquire_link_resp PDU

Services Gatekeeper or an application sends this PDU as a response to "enquire_link PDU".

alert_notification PDU

Not supported.

UCP

The universal computer protocol (UCP) communication service complies with the Short Message Service Centre EMI-UCP Interface 5.1 specification.

Error Handling

The following errors are reported to the application or the SMSC in the UCP NACK PDU under the conditions described.

ERROR CODE OPERATION NOT ALLOWED

- The UCP service has received something in suspended mode.
- The UCP service has received an openSession request on a connection that has already received an openSession request and has processed an OK response to it. Further openSession requests are not allowed.
- The UCP service has received an openSession request on a connection where it is currently processing an openSession request.
- All SMSCs have responded with NACK to an openSession request.
- The UCP service has received a session management operation on a client-side connection.

ERROR_CODE_AUTH_FAILURE

Authentication between Services Gatekeeper and the application has failed.

ERROR_CODE_OPERATION_NOT_SUPPORTED

- The UCP service has received a session management operation that is not of the openSession subtype.
- The UCP service has received an operation that it does not understand or support on a server-side connection.
- The UCP service has received an operation that it does not understand or support on a client-side connection.

ERROR_CODE_SYNTAX_ERROR

- The UCP service received an exception when trying to deliver a PDU that was received on a server-side connection to a plug-in.
- The UCP service received an exception when trying to deliver a PDU that was received on a client-side connection to a plug-in.

Any errors triggered in the SMSC are propagated to the application. See the Short Message Service Centre EMI-UCP Interface 4.6 specification for a list of those error codes.

Native UCP Operations: Application-Facing Interface

This section describes the native UCP operations in the NativeUCPPluginNorth interface.

submitSM

Sends a mobile-terminated SMS.

Signature:

submitSM(UcpPDU submitSMPDU, ServerPort sourceServerPort, String sourceConnectionId)

openSession

Opens a new UCP session.

Signature:

openSession(UcpPDU openSessionPDU, ServerPort sourceServerPort, String sourceConnectionId)

ack

Sends an ACK to the SMSC.

Signature:

ack(UcpPDU ack, String sourceConnectionId)

nack

Sends a NACK to the SMSC.

Signature:

nack(UcpPDU nack, String sourceConnectionId)

deliverSM

Delivers a mobile-originated SMS.

Signature:

deliverSM(UcpPDU deliverSMPDU, String connectionId)

deliveryNotification

Delivers a message delivery notification associated with a previously sent mobileterminated SMS.

Signature:

deliveryNotification(UcpPDU deliveryNotificationPDU, String connectionId)

Native UCP Operations: Network-Facing Interface

This section describes the supported native UCP operations in the NativeUCPPluginSouth interface.

ack

Sends an ACK to the application.

Signature:

ack(UcpPDU ack, String connectionId)

nack

Sends a NACK to the application.

Signature:

nack(UcpPDU ack, String connectionId)

Part V

Creating Applications Using Extended Web Service Interfaces

Part V explains how to use the native telephony facade to create applications that interact with Oracle Communications Services Gatekeeper.

Part V contains the following chapters:

- Understanding the Extended Web Services Common Definitions
- Adding Extended Web Service Binary SMSs Support
- Adding WAP Push Extended Web Service Message Support
- Adding Subscriber Profile Extended Web Service Support

Understanding the Extended Web Services Common Definitions

This chapter describes the Oracle Communications Services Gatekeeper definitions that the Extended Web Services share.

Namespace

The namespace for the common data types is:

http://www.bea.com/wlcp/wlng/schema/ews/common

The namespace for the common faults is:

http://www.bea.com/wlcp/wlng/wsdl/ews/common/faults

XML Schema Datatype Definition

This section explains the XML schema datatype definition.

Additional Property Structure

Defines a name-value pair.

Table 31–1 Additional Property Structure

Element Name	Element type	Optional	Description
name	xsd:string	Y	Name part.
value	xsd:string	Y	Value part.

ChargingInformation structure

For services that include charging as an inline message part, the charging information is provided in this data structure.

Table 31–2 ChargingInformation Structure

Element Name	Element type	Optional	Description
description	xsd:string	N	Description text to be use for information and billing text.
currency	xsd:string	Y	Currency identifier as defined in ISO 4217.
amount	xsd:decimal	Y	Amount to be charged.

Table 31–2 (Cont.) ChargingInformation Structure

Element Name	Element type	Optional	Description
code	xsd:string	Y	Charging code, referencing a contract under which the charge is applied.

SimpleReference structure

For those services that require a reference to a Web service, the information required to create the endpoint information is provided in this data structure.

Table 31–3 SimpleReference Structure

Element Name	Element type	Optional	Description
endpoint	xsd:anyURI	N	Description text to be use for information and billing text.
interfaceName	xsd:string	Y	Name of interface.
correlator	xsd:decimal	Y	Correlation information.

Fault Definitions

This section explains the fault definitions.

ServiceException

Faults related to the operation of the service, not including policy related faults, result in the return of a ServiceException message.

Table 31-4 ServiceException

Element Name	Element type	Optional	Description
messageId	xsd:string	N	Message identifier, with prefix SVC.
text	xsd:string	N	Message text, with replacement variables marked with %#
variables	xsd:string [0unbounded]	Y	Variables to substitute into text string.

Service exceptions are related to the operation of the service itself. The following exceptions are general:

- SVC0001: Service error
- SVC0002: Invalid input value
- SVC0003: Invalid input value with list of valid values
- SVC0004: No valid addresses
- SVC0005: Duplicate correlator
- SVC0006: Invalid group
- SVC0007: Invalid charging information
- SVC0008: Overlapping criteria

PolicyException

Faults related to policies associated with the service, result in the return of a PolicyException message.

Table 31–5 PolicyException

Element Name	Element type	Optional	Description
messageId	xsd:string	N	Message identifier, with prefix POL.
text	xsd:string	N	Message text, with replacement variables marked with %#
variables	xsd:string [0unbounded]	Y	Variables to substitute into text string.

PolicyExceptions are thrown when a policy has been violated, including violations of a service level agreements. The following general PolicyExceptions are defined:

- POL0001: Policy error
- POL0002: Privacy error
- POL0003: Too many addresses specified
- POL0004: Unlimited notifications not supported
- POL0005: Too many notifications requested
- POL0006: Groups not allowed
- POL0007: Nested groups not allowed
- POL0008: Charging not supported
- POL0009: Invalid frequency requested

Adding Extended Web Service Binary SMSs **Support**

This chapter explains how to use the Oracle Communications Services Gatekeeper binary SMS extended web service interface to add binary SMS support to applications.

Understanding the Binary SMS Web Service

The Extended Web Services Binary SMS Web Service allows for the sending and receiving of any generic binary content through SMSs. Both application-initiated and network-triggered requests are supported. The binary content can include data beyond the logos and ringtones specified by Parlay X Short Messaging. Examples of supported binary content include vCards, calendar entries, and WAP Push messages.

The Extended Web Services Binary SMS Web Service supports the automatic chunking of oversized binary SMS messages to handle messages that exceed the maximum size of a single SMS request. Oversized unsegmented messages are automatically divided into size conforming individual messages and handled by Services Gatekeeper if the proper encoding is provided in the message header.

Namespaces

The BinarySMS interface and service use the namespaces:

- http://www.bea.com/wlcp/wlng/wsdl/ews/binary_sms/interface
- http://www.bea.com/wlcp/wlng/wsdl/ews/binary_sms/service

The BinarySmsNotificationManager interface and service use the namespaces:

- http://www.bea.com/wlcp/wlng/wsdl/ews/binary_sms/notification/interface
- http://www.bea.com/wlcp/wlng/wsdl/ews/binary_sms/notification/service

In addition, Extended Web Services Binary SMS uses common data type definitions common for all Extended Web Services interfaces, see "Understanding the Extended Web Services Common Definitions".

Fault definitions are according to ETSI ES 202 391-1 V1.2.1 (2006-10) Open Service Access (OSA); Parlay X Web Services; Part 1: Common (Parlay X 2).

Endpoints

The endpoint for the BinarySMS interface is: http://<host:port>/ews/binary_ sms/BinarySms

The endpoint for the BinarySmsNotificationManager interface is: http://host:port/ews/binary_sms/BinarySmsNotificationManager

Where the values for host and port depend on your specific Services Gatekeeper deployment.

Sequence Diagram

This section explains the sequence diagrams for sending and receiving an SMS.

Send SMS

Figure 32–1 shows the general message sequence for sending a binary SMS message from an Extended Web Services Binary SMS application to the network. In this message sequence the application also receives a notification from the network indicating the delivery status of the SMS, that is that the message has reached its destination. It also displays how an application can query the delivery status of the message.

The interaction between the network and Services Gatekeeper is illustrated in a protocol-agnostic manner. The exact operations and sequences depend on which network protocol is being used.

Note: The delivery notifications are sent from the Parlay X 2.1 Short Messaging implementation.




Figure 32-1 Sequence diagram Application-initiated send Extended Web Services Binary SMS

Receive SMS

Figure 32–2 shows the general message sequence for receiving a binary SMS message from the Network using Services Gatekeeper. In this message sequence the application also subscribes for a notifications on network triggered short messages.

The interaction between the network and Services Gatekeeper is illustrated in a protocol-agnostic manner. The exact operations and sequences depend on which network protocol is being used.




Figure 32-2 Sequence diagram receive Extended Web Services Binary SMS

XML Schema data type definition

The following data structures are used in the Extended Web Services Binary SMS Web Service.

BinaryMessage structure

Defines the binary payload of the SMS for application-initiated messages.

Defines the TP-User Data (TP-UD).

For a description of TP-User Data (TP-UD), TP-User-Data-Header-Indicator (TP UDHI), see 3GPP TS 23.040 V6.5.1, Technical realization of the Short Message Service (SMS) at:

http://www.3gpp.org/ftp/Specs/html-info/23040.htm

Table 32-1 BinaryMessage structure

Element Name	Element type	Optional	Description
udh	xsd:base64Binary	Y if message is set, otherwise N	Defines the User Data Header. See the description of TP-User Data (TP-UD) in the 3GPP specification for information about how to format the User Data Header.
message	xsd:base64Binary	Y if udh is set, otherwise N	Binary message data. Must be formatted according to TP-User Data (TP-UD), excluding the User Data Header.

BinarySmsMessage structure

Defines the binary payload of the SMS for network-triggered messages.

Table 32–2 BinarySmsMessage structure

Element Name	Element type	Optional	Description
message	ews_binary_ sms_ xsd:BinaryMess age[1unbounde d]	N	See "BinaryMessage structure".
dcs	xsd:byte	N	Data code schema, according to SMPP v3.4.
protocolId	xsd:byte	Y	TP-Protocol-Identifier according to 3GPP 23.040 6.5.1. Defines the TP-User Data
			(TP-UD). For a description of TP-User Data (TP-UD), TP-User-Data-Header-Indicato r (TP UDHI), see 3GPP TS 23.040 V6.5.1, Technical realization of the Short Message Service (SMS) at:
			http://www.3gpp.org/ftp/Sp ecs/html-info/23040.htm
			The protocol identifier is the information element by which the short message transport layer either refers to the higher layer protocol being used, or indicates interworking with a certain type of telematic device.
			Example: 123
senderAddress	xsd:anyURI	N	The address of the sender of the short message.
			Example:
			tel:1234556
smsServiceActivationNumber	xsd:anyURI	N	The destination address of the short message.
			Example:
			tel:1222
dateTime	xsd:dateTime	N	The timestamp of the message.

Interface: BinarySms

Operations to send SMSs with binary content.

Operation: sendBinarySMS

Sends an SMS with any binary data as content.

Input message: sendBinarySMS

Table 32–3 Input message: sendBinarySMS

Part name	Part type	Optional	Description
addresses	xsd:anyURI[1unbounded]	N	An array of end-user terminal addresses. Example: tel:1234

Table 32–3 (Cont.) Input message: sendBinarySMS

Part name	Part type	Optional	Description
senderName	xsd:string	Y	The name of the sender. Alphanumeric.
			Example: tel:7485, Mycompany.
dcs	xsd:byte	N	Defines the data encoding scheme for the binaryMessage parameter.
			Formatted according to data_coding parameter in SMPP v3.4.
			See http://www.smsforum.net/
binaryMessage	binary_sms_	N	Message payload.
	xsd:BinaryM essage[1unb ounded]		An array comprised of UDH elements and message elements, see "BinaryMessage structure".
			This array must be equal to or less than 140 bytes in size.
protocolId	xsd:byte	Y	TP-Protocol-Identifier (TP-PID) according to 3GPP TS 23.040 V6.5.1, Technical realization of the Short Message Service (SMS) at:
			http://www.3gpp.org/ftp/Specs/html-info/2 3040.htm
			Specifies the higher layer protocol being used, or indicates interworking with a certain type of telematic device.
validityPeriod	xsd:string	Y	Defines the validity period for the short message.
			Formatted according to validity_period parameter in SMPP v3.4.
			See http://www.smsforum.net/
charging	ews_	Y	Charging information.
	common_ xsd:Charging Information		See "ChargingInformation structure".
receiptRequest	ews_ common_ xsd:SimpleRe ference	Y	It defines the application endpoint, interfaceName and correlator that will be used to notify the application when the message has been delivered to the terminal or if delivery is impossible.
			See "SimpleReference structure"

$Output\ message: sendBinary SMSR esponse$

Table 32–4 Output message: sendBinarySMSResponse

Part name	Part type	Optional	Description
result	xsd:string	N	Identifies a specific SMS delivery request.

Table 32–5 exceptions and error codes

Exception	Error code	Reason/Action
SVC0001	BSMS-000001	Unable to perform action. Network error

Table 32-5 (Cont.) exceptions and error codes

Exception	Error code	Reason/Action
SVC0001	BSMS-000002	Unable to retrieve configuration, internal error.
SVC0001	BSMS-000003	The used address type is not supported
SVC0001	BSMS-000004	Unable to encode message segments.
		make sure the number of message segments is not 0.
SVC0001	BSMS-000005	GSM message format error.
SVC0001	BSMS-000006	Binary Message has too many segments.
SVC0001	PLG-000004	General plug-in routing error.
SVC0002	N/A	SenderName in non-alphanumeric format.
SVC0003	N/A	N/A
SVC0004	N/A	N/A
SVC0005	N/A	N/A
EPOL0001	N/A	N/A

Interface: BinarySmsNotificationManager

Operations to start and stop subscriptions for notifications for short messages with binary content.

Operation: StartBinarySmsNotification

Starts a subscription for notifications for short messages that have content in the form of binary data. A correlator is provided in the request. This correlator is used when stopping the subscription.

Input message: StartBinarySmsNotification

Table 32–6 Input message: StartBinarySmsNotification

Part name	Part type	Optional	Description
reference	ews_common_ xsd:SimpleRefe rence	N	Defines the application endpoint, interfaceName and correlator that will be used to forward a binary short message from the network. See "SimpleReference structure"
smsServiceActivationNumber	xsd:xsd:anyURI	Y	The destination address of the short message.

Output message: StartBinarySmsNotificationResponse

Table 32–7 Output message: StartBinarySmsNotificationResponse

Part name	Part type	Optional	Description
N/A	N/A	N/A	N/A

Table 32–8 exceptions and error codes

Exception	Error code	Reason/Action
SVC0001	BSMS-000001	Unable to perform action. Network error
SVC0001	BSMS-000002	Unable to retrieve configuration, internal error.
SVC0001	BSMS-000003	The used address type is not supported
SVC0001	BSMS-000004	Unable to encode message segments.
		make sure the number of message segments is not 0.
SVC0001	BSMS-000005	GSM message format error.
SVC0001	BSMS-000006	Binary Message has too many segments.
SVC0001	PLG-000004	General plug-in routing error.
SVC0002	N/A	N/A
SVC0003	N/A	N/A
SVC0004	N/A	N/A
SVC0005	N/A	N/A
EPOL0001	N/A	N/A

Operation: StopBinarySmsNotification

Stops a previously started subscription for notifications for short messages that have content in the form of binary data. A correlator is provided in the request. This correlator was provided when the subscription was started, see "Operation: StartBinarySmsNotification".

Input message: StopBinarySmsNotification

Table 32-9 Input message: StopBinarySmsNotification

Part name	Part type	Optional	Description
correlator	xsd:String	N	The identifier for the subscription.

Output message: StopBinarySmsNotificationResponse

Table 32–10 Output message: StopBinarySmsNotificationResponse

Part name	Part type	Optional	Description
N/A	N/A	N/A	N/A

Table 32–11 exceptions and error codes

Exception	Error code	Reason/Action
SVC0001	BSMS-000001 Unable to perform action. Network	
SVC0001	BSMS-000002	Unable to retrieve configuration, internal error.
SVC0001	BSMS-000003	The used address type is not supported

Table 32–11 (Cont.) exceptions and error codes

Exception	Error code	Reason/Action
SVC0001	BSMS-000004	Unable to encode message segments.
		make sure the number of message segments is not 0.
SVC0001	BSMS-000005	GSM message format error.
SVC0001	BSMS-000006	Binary Message has too many segments.
SVC0001	PLG-000004	General plug-in routing error.
SVC0002	N/A	N/A
SVC0003	N/A	N/A
SVC0004	N/A	N/A
SVC0005	N/A	N/A
EPOL0001	N/A	N/A

Interface: BinarySmsNotification

This interface is implemented by the application. It is used by Services Gatekeeper to deliver short messages with binary content to an application. Only messages that match a previously started subscription for notifications are delivered.

Note: Notifications on delivered short messages are delivered using the Parlay X 2.1 Short Messaging SmsNotification interface, using the method NotifySmsDeliveryReceipt.

Operation: NotifyBinarySmsReception

Services Gatekeeper calls this methods on

The notification is used to send a short message with binary content to the application. The notification occurs if the short message matched the criteria specified when starting the notification. See "Operation: StartBinarySmsNotification".

The method must be implemented by a Web Service at the application side. It is be invoked by Services Gatekeeper when it receives a short message with binary content form the network and the criteria is fulfilled.

Input message: NotifyBinarySmsReceptionRequest

Table 32–12 Input message: NotifyBinarySmsReceptionRequest

Part name	Part type	Description
correlator	xsd:String	The correlator for the subscription.
message	ews_binary_ sms_ xsd:BinarySmsM essage	The message in binary form. See "BinarySmsMessage structure".

Output message: NotifyBinarySmsReceptionResponse

Table 32–13 Output message: NotifyBinarySmsReceptionResponse

Part name	Part type	Optional	Description
N/A	N/A	N/A	N/A

Referenced faults

None.

Configuring Automatic Chunking of Binary SMSs

This interface includes a feature that automatically separates oversize SMS messages into smaller segments so that even switches that limit the size of SMSs will support them. This feature works for SMS messages that use either user data header (UDH) headers, or Sar_ headers. Each chunk gets its own header segment, so your switches treat them a separate SMS messages.

You use the wlng.smpp.concatenated_message_indicator Services Gatekeeper system property to select the type of header you use. 0 is the default value. It indicates UDH headers. Change this setting to 1 if your implementation processes SMSs with Sar_ headers.

This feature follows the 3GPP TS 23.038 and 3GPP TS 23.040 specifications for UDH and the SMPPv3.4 specification for Sar.

WSDLs

The document/literal WSDL representation of the interfaces can be retrieved from the Web Services endpoints, see "Endpoints".

The notification interface can be downloaded from:

http://host:port/ews/binary_sms/wsdls/ews_binary_sms_notification_service.wsdl http://host:port/ews/binary_sms/wsdls/ews_binary_sms_notification_interface.wsdl

Where the values for *host* and *port* depend on the Services Gatekeeper deployment.

Error Codes

The following error codes are defined for SVC0001: Service error:

- See "General Error Codes".
- Error codes defined for Parlay X 2.1 Short Messaging, see "Error Codes".
- 16133 Too many segments in message.

The following error codes are defined for EPOL0001: Policy error:

- See "Code Examples".
- Policy error codes defined for Parlay X 2.1 Short Messaging, see "Error Codes".

Sample Send Binary SMS

Example 32-1 Example Send Binary SMS

BinarySmsService service = new BinarySmsService_Impl("http://localhost:8001/ews/binary_ sms/BinarySms?WSDL");

```
BinarySms port = service.getBinarySms();
com.bea.wlcp.wlng.schema.ews.binary_sms.local.SendBinarySms parameters =
new com.bea.wlcp.wlng.schema.ews.binary_sms.local.SendBinarySms();
URI[] addresses = new URI[1];
addresses[0] = new URI("tel:1234");
parameters.setAddresses(addresses);
parameters.setDcs((byte)0);
parameters.setProtocolId((byte)0x7b);
parameters.setSenderName("tel:7878");
parameters.setValidityPeriod("020610233429000R");
com.bea.wlcp.wlng.schema.ews.binary_sms.BinaryMessage[] binaryMessages =
new com.bea.wlcp.wlng.schema.ews.binary_sms.BinaryMessage[1];
binaryMessages[0] = new com.bea.wlcp.wlng.schema.ews.binary_sms.BinaryMessage();
byte[] udh = {0};
byte[] message = {0x4d, 0x61, 0x64, 0x65, 0x20, 0x69, 0x6e, 0x20, 0x2e};
binaryMessages[0].setUdh(udh);
binaryMessages[0].setMessage(message);
parameters.setBinaryMessage(binaryMessages);
port.sendBinarySms(parameters);
```

Adding WAP Push Extended Web Service **Message Support**

This chapter explains how to use the Oracle Communications Services Gatekeeper WAP Push Extended Web Service interface to add WAP Push support to applications.

Understanding the WAP Push Extended Web Service Interface

The WAP Push Extended Web Services interface sends messages which are rendered as WAP Push messages by the addressee's terminal. The content of the message is coded as a PAP message. It also provides an asynchronous notification mechanism for delivery status.

The payload of a WAP Push message must adhere to the following specifications:

- WAP Service Indication Specification, as specified in Service Indication Version 31-July-2001, Wireless Application Protocol WAP-167-ServiceInd-20010731-a.
- WAP Service Loading Specification, as specified in Service Loading Version 31-Jul-2001, Wireless Application Protocol WAP-168-ServiceLoad-20010731-a.
- WAP Cache Operation Specification, as specified in Cache Operation Version 31-Jul-2001, Wireless Application Protocol WAP-175-CacheOp-20010731-a.

See the Open Mobile Alliance websitewebsite for links to the specifications:

http://www.openmobilealliance.org/tech/affiliates/wap/wapindex.html

The payload is sent as a SOAP attachment.

See "Sending Custom Message Content for Split and Submit Messaging Requests" for instructions on how to split messages into multiple individually-addressed requests

Namespaces

The PushMessage interface and service use the namespaces:

- http://www.bea.com/wlcp/wlng/wsdl/ews/push_message/interface
- http://www.bea.com/wlcp/wlng/wsdl/ews/push_message/service

The PushMessageNotification interface and service use the namespaces:

- http://www.bea.com/wlcp/wlng/wsdl/ews/push message/notification/interface
- http://www.bea.com/wlcp/wlng/wsdl/ews/push_message/notification/service

The data types are defined in the namespace:

http://www.bea.com/wlcp/wlng/schema/ews/push_message

In addition, WAP Push Extended Web Service uses definitions common for all Extended Web Services interfaces:

- The datatypes are defined in the namespace:
 - http://www.bea.com/wlcp/wlng/schema/ews/common
- The faults are defined in the namespace:
 - targetNamespace="http://www.bea.com/wlcp/wlng/wsdl/ews/common/faults"

Endpoint

The endpoint for the PushMessage interface is: http://host:port/ews/push_ message/PushMessage

Where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Sequence Diagram

Figure 33–1 shows the general message sequence for sending a WAP Push message from an application that uses WAP Push Extended Web Service to the network. In this message sequence the application also receives a notification from the network indicating the delivery status of the WAP Push message, that is that the message has been read The interaction between the network and Services Gatekeeper is illustrated in a protocol-agnostic manner. The exact operations and sequences depend on which network protocol is being used.

Note: Zero or more resultNotificationmesages are sent to the application, depending on parameters provided in the initial SendPushMessage request.




Figure 33–1 Sequence Diagram of WAP Push Extended Web Services

XML Schema Data Type Definition

The following data structures are used in the WAP Push Extended Web Service.

PushResponse Structure

Defines the response that Services Gatekeeper returns from a sendPushMessage operation.

Table 33-1 PushResponse Structure

Element Name	Element type	Optional	Description
result	push_message_ xsd:ResponseRe sult	No	The ResponseResult allows the server to specify a code for the outcome of sending the push message. See "ResponseResult structure"
pushId	xsd:string	No	The push ID provided in the request.
senderAddress	xsd:string	Yes	Contains the address to which the message was originally sent, for example the URL to the network node.
senderName	xsd:string	Yes	The descriptive name of the server.
replyTime	xsd:dateTime	Yes	The date and time associated with the creation of the response.
additionalProperties	ews_common_ xsd:AdditionalP roperty	Yes	Additional properties. The supported properties are: pap.stage, pap.note, pap.time

ResponseResult structure

Defines the result element in the PushResponse structure, which is used in the response returned from a sendPushMessage operation.

Table 33-2 ResponseResult Structure

Element Name	Element type	Optional	Description
code	xsd:string	No	A code representing the outcome when sending the push message. Generated by the network node. Possible status codes are listed in this section.
description	xsd:string	No	Textual description.

Table 33–3 Outcome Status Codes

Status code	Description
1000	OK.
1001	Accepted for processing.
2000	Bad request.
2001	Forbidden.
2002	Address error.
2003	Address not found.
2004	Push ID not found.
2005	Capabilities mismatch.
2006	Required capabilities not supported.
2007	Duplicate push ID.
2008	Cancellation not possible.
3000	Internal server error.
3001	Not implemented.
3002	Version not supported.
3003	Not possible.
3004	Capability matching not possible.
3005	Multiple addresses not supported.
3006	Transformation failure.
3007	Specified delivery method not possible.
3008	Capabilities not available.
3009	Required network not available.
3010	Required bearer not available.
3011	Replacement not supported.
4000	Service failure.
4001	Service unavailable.

ReplaceMethod enumeration

Defines the values for the replacePushId parameter in the sendPushMessage operation. This parameter is used to replace an existing message based on a given push ID. This parameter is ignored if it is set to NULL.

Table 33-4 ReplaceMethod Enumeration

Enumeration value	Description
all	Indicates that this push message must be treated as a new push submission for all recipients, whether or not a previously submitted push message with pushId equal to the replacePushId in this push message can be found.
pending-only	Indicates that this push message should be treated as a new push submission only for those recipients who have a pending push message that is possible to cancel.
	In this case, if no push message with pushId equal to the replacePushId in this push message can be found, the server responds with status code PUSH_ID_NOT_FOUND in the responseResult.
	Status code CANCELLATION_NOT_POSSIBLE may be returned in the responseResult if no message can be cancelled.
	Status code CANCELLATION_NOT_POSSIBLE may also be returned in a subsequent resultNotification to indicate a non-cancellable message for an individual recipient.

MessageState enumeration

Defines the values for the messageState parameter in a resultMessageNotification.

Table 33-5 MessageState Enumeration

Enumeration value	Description	
rejected	Message was not accepted by the network.	
pending	Message is being processed.	
delivered	Message successfully delivered to the network.	
undeliverable	The message could not be delivered.	
expired	The message reached the maximum allowed age or could not be delivered by the time specified when the message was sent.	
	Some network elements allows for defining policies on maximum age of messages.	
aborted	The end-user terminal aborted the message.	
timeout	The delivery process timed out.	
cancelled	The message was cancelled.	
unknown	The state of the message is unknown.	

WAP Push Extended Web Service Interface Descriptions

The following describes the interfaces and operations that are available in the WAP Push Extended Web Service.

Interface: PushMessage

Operations to send, or to manipulate previously sent, WAP Push messages.

Operation: sendPushMessage

Sends a WAP Push message. The message Content Entity (the payload) is provided as a SOAP attachment in MIME format. The Content Entity is a MIME body part containing the content to be sent to the wireless device. The content type is not defined, and can be any type as long as it can be described by MIME. The Content Entity is included only in the push submission and is not included in any other operation request or response.

Input message: sendPushMessage

Table 33-6 Input Message: sendPushMessage

Part name	Part type	Optional	Description
pushId	xsd:string	N	Provided by the application. Serves as a message ID. The application is responsible for its uniqueness, for example, by using an address within its control (for example a URL) combined with an identifier for the push message as the value for pushId. Supported types are PLMN and USER. For example:
			"www.wapforum.org/123" or "123@wapforum.org"
destinationAddresses	xsd:string [1unbounde d]	N	An array of end-user terminal addresses.
			The addresses should be formatted according to the Push Proxy Gateway Service Specification (WAP-249-PPGService-20010713-a).
			Example addresses:
			■ WAPPUSH=+155519990730
			TYPE=PLMN@ppg.carrier.com
			■ WAPPUSH=john.doe%40wapforu m.org
			TYPE=USER@ppg.carrier.com
resultNotificationEndpoint	xsd:anyURI	Y	Specifies the URL the application uses to return result notifications.
			The presence of this parameter indicates that a notification is requested. If the application does not want a notification, this parameter must be set to NULL.

Table 33–6 (Cont.) Input Message: sendPushMessage

Part name	Part type	Optional	Description
replacePushId	xsd:string	Y	The pushId of the still pending message to replace.
			The presence of this parameter indicates that the client is requesting that this message replace one previously submitted, but still pending push message.
			The following rules apply:
			 Setting the replacePushId parameter to NULL indicates that it is a new message. It does not replace any previously submitted message.
			■ The initial pending (pending delivery to the end-user terminal) message is cancelled, if possible, for all recipients of the message. This means that it is possible to replace a message for only a subset of the recipients of the original message.
			 Message replacement will occur only for the recipients for whom the pending message can be cancelled.
replaceMethod	push_ message_ xsd:Replace Method	N	Defines how to replace a previously sent message. Used in conjunction with the replacePushId parameter described above.
			Ignored if replacePushId is NULL.
deliverBeforeTimestamp	xsd:dateTime	Y	Defines the date and time by which the content must be delivered to the end-user terminal.
			The message is not delivered to the end-user terminal after this time and date.
			If the network node does not support this parameter, the message is rejected.
deliverAfterTimestamp	xsd:dateTime	Y	Specifies the date and time after which the content should be delivered to the wireless device.
			The message is delivered to the end-user terminal after this time and date.
			If the network node does not support this parameter, the message is be rejected.
sourceReference	xsd:string	Y	A textual name of the content provider.

Table 33-6 (Cont.) Input Message: sendPushMessage

Part name	Part type	Optional	Description
progressNotesRequested	xsd:boolean	Y	This parameter informs the network node if the client wants to receive progress notes.
			TRUE means that progress notes are requested.
			Progress notes are delivered using the PushMessageNotification interface.
			If not set, progress notes are not sent.
serviceCode	xsd:string	N	Used for charging purposes.
requesterID	xsd:string	N	The application ID as given by the operator.
additionalProperties	ews_ common_ xsd:Addition alProperty [0unbound ed]	Y	Additional properties, defined as name/value pairs, can be sent using this parameter. The supported properties are: pap.priority, pap.delivery-method, pap.network, pap.network-required, pap.bearer, pap.bearer-required.

Output message: sendPushMessageResponse

Table 33–7 Output Message: sendPushMessageResponse

Part name	Part type	Optional	Description
result	push_ message_ xsd:PushRes ponse	N	The response that Services Gatekeeper returns for sendPushMessage operation

Referenced faults

Table 33–8 Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	WNG-000001	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.
SVC0001	WNG-000002	Internal problem in Services Gatekeeper.
		Contact Services Gatekeeper administrator.
SVC0001	PUSHMSG-000002	Failed to create push message.
SVC0001	PUSHMSG-000003	Unable to retrieve configuration.
SVC0001	PUSHMSG-000001	Failed to submit push message to PPG.
SVC0001	PLG-000004	General plug-in routing error

Interface: PushMessageNotification

 $Operations\ result Notification Message\ and\ result Notification Message\ Response.$

Operation: resultNotificationMessage Input message: resultNotificationMessage

Table 33–9 Input Message: resultNotificationMessage

Part name	Part type	Optional	Description
pushId	xsd:string	N	Defined by the application in the corresponding sendPushMessage operation.
			Used to match the notification to the message.
address	xsd:string	N	The address of the end-user terminal.
messageState	push_ message_ xsd:Message State	N	State of the message.
code	xsd:string	N	Final status of the message.
description	xsd:string	Y	Textual description of the notification. Supplied by the network. May or may not be present, depending on the network node used.
senderAddress	xsd:string	Y	Address of the network node.
			May or may not be present, depending on the network node used.
senderName	xsd:string	Y	Name of the network node.
			May or may not be present, depending on the network node used.
receivedTime	xsd:dateTime	Y	Time and date when the message was received at the network node.
eventTime	xsd:dateTime	Y	Time and date when the message reached the end-user terminal.
additionalProperties	ews_ common_ xsd:Addition	Y	Additional properties can be sent using this parameter in the form of name/value pairs. The supported properties are:
	alProperty		pap.priority
			pap.delivery-method
			pap.network
			pap.network-required
			pap.bearer
			pap.bearer-required
			Which properties are sent, if any, is dependent on the network node.

Output message: resultNotificationMessageResponse

Table 33-10 Output Message: resultNotificationMessageResponse

Part name	Part type	Optional	Description
N/A	N/A	N/A	N/A

Table 33-11 Exceptions and Error Codes

Exception	Error code	Reason/Action
SVC0001	PUSHMSG-000004	Failed to send result notification to the application.

WSDLs

The document/literal WSDL representation of the PushMessage interface can be retrieved from the Web services endpoint.

The document/literal WSDL representation of the PushMessageNotification interface can be downloaded from

```
http://host:port/ews/push_message/wsdls/ews_common_types.xsd
http://host:port/ews/push_message/wsdls/ews_push_message_notification_
interface.wsdl
http://host:port/ews/push_message/wsdls/ews_push_message_notification_
service.wsdl
http://host:port/ews/push_message/wsdls/ews_push_message_types.xsd
```

Where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Sample Send WAP Push Message

Example 33-1 Example Send WAP Push Message

```
// Add handlers for MIME types needed for WAP MIME-types
MailcapCommandMap mc = (MailcapCommandMap) CommandMap.getDefaultCommandMap();
mc.addMailcap("text/vnd.wap.si;;x-java-content-handler=com.sun.mail.handlers.text_xml");
CommandMap.setDefaultCommandMap(mc);
// Create a MIME-message where with the actual content of the WAP Push message.
InternetHeaders headers = new InternetHeaders();
headers.addHeader("Content-type", "text/plain; charset=UTF-8");
headers.addHeader("Content-Id", "mytext");
byte[] bytes = "Test message".getBytes();
MimeBodyPart mimeMessage = new MimeBodyPart(headers, bytes);
// Create PushMessage with only the manadatory parameters
// SendPushMessage is provided in the stubs generated from the WSDL.
SendPushMessage sendPushMessage = new SendPushMessage();
String [] destinationAddresses = {"wappush=461/type=user@ppg.o.se"};
sendPushMessage.setDestinationAddresses(destinationAddresses);
// Create "unique" pushId, using a combination of timestamp and domain.
sendPushMessage.setPushId(System.currentTimeMillis() + "@wlng.bea.com");
// ReplaceMethod is provided by the stubs generated from the WSDL.
sendPushMessage.setReplaceMethod(ReplaceMethod.pendingOnly);
// Defined by the operator/service provider contractual agreement
sendPushMessage.setServiceCode("Service Code xxx");
// Defined by the operator/service provider contractual agreement
sendPushMessage.setRequesterID("Requester ID xxx");
// Endpoint to send notifications to. Implemented on the application side.
String notificationEndpoint = "http://localhost:80/services/PushMessageNotification";
sendPushMessage.setResultNotificationEndpoint(new URI(notificationEndpoint));
```

```
// Send the WAP Push message
PushMessageService pushMessageService = null;
// Define the endpoint of the WAP Push Web service
String endpoint = "http://localhost:8001/ews/push_message/PushMessage?WSDL";
try {
 // Instantiate an representation of the Web service from the generated stubs.
 pushMessageService = new PushMessageService_Impl(endpoint);
} catch (ServiceException e) {
 e.printStackTrace();
 throw e;
PushMessage pushMessage = null;
try {
 // Get the Web service interface to operate on.
 pushMessage = pushMessageService.getPushMessage();
} catch (ServiceException e) {
   e.printStackTrace();
   throw e;
 }
SendPushMessageResponse sendPushMessageResponse = null;
 // Send the WAP Push message.
 sendPushMessageResponse = pushMessage.sendPushMessage(sendPushMessage);
} catch (RemoteException e) {
 e.printStackTrace();
 throw e;
} catch (PolicyException e) {
 e.printStackTrace();
 throw e;
} catch (com.bea.wlcp.wlng.schema.ews.common.ServiceException e) {
 e.printStackTrace();
 throw e;
// Assign the pushId provided in the in the response to a local variable.
String pushId = sendPushMessageResponse.getPushId();
```

Adding Subscriber Profile Extended Web Service Support

This chapter explains how to use the Oracle Communications Services Gatekeeper subscriber profile extended web service interface to add subscriber profile information applications.

Understanding the Subscriber Profile Extended Web Service Interface

The Subscriber Profile Extended Web Service interface allows an application to get subscriber-specific data from data sources within the network operator's domain.

Examples of data sources are subscriber databases containing information about terminal types in use, preferred language, and currency types. This information can be used by applications in order to control rendering options for rich media, charging information, and the language to be used in voice and text interaction with the end-user.

The interface is built around a model where the data can be retrieved in two different ways:

- Individual attributes, identified using a path.
- A collection of attributes.

The attributes are keyed on a subscriber ID that uniquely identifies the subscriber for whom the attributes are valid or by an address that uniquely identifies the terminal for which the attributes are valid. An attribute is identified by a path name, which corresponds to a specific property. The following is an example of a path name:

serviceName/accessControlId/accessControlId

The syntax for the path is similar to relative file system paths in UNIX.

A collection of attributes is specified in a subscriber profile filter for the application or the service provider. Only allowed attributes, as specified in the filter, are returned.

The returned attributes are returned in the form of name-value pairs, or property tuples, where the name is expressed as a path name with a associated property value.

The interface is based on a proposal for a Parlay X Subscriber Profile Web service interface.

Namespaces

The SubscriberProfile interface and service use these namespaces:

http://www.bea.com/wlcp/wlng/wsdl/ews/subscriber_profile/interface

http://www.bea.com/wlcp/wlng/wsdl/ews/subscriber_profile/service The data types are defined in the namespace:

http://www.bea.com/wlcp/wlng/schema/ews/subscriber_profile

In addition, the Subscriber Profile Extended Web Service interface uses definitions common for all Extended Web Services interfaces:

- The datatypes are defined in the namespace:
 - http://www.bea.com/wlcp/wlng/schema/ews/common
- The faults are defined in the namespace:
 - http://www.bea.com/wlcp/wlng/wsdl/ews/common/faults

Endpoint

The endpoint for the PushMessage interface is: http://host:port/ews/subscriber_ profile/SubscriberProfile

Where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Address schemes

Table 34-1 Supported Address Schemes

Address scheme Valid for Communication service	
tel	Subscriber Profile Extended Web Service profile for LDAPv3
id	Subscriber Profile Extended Web Service profile for LDAPv3
imsi	Subscriber Profile Extended Web Service profile for LDAPv3
ipv4	Subscriber Profile Extended Web Service profile for LDAPv3

XML Schema data type definition

The following data structures are used in the Subscriber Profile Extended Web Service.

PropertyTuple Structure

Defines the response that Services Gatekeeper returns from "Operation: get" and "Operation: getProfile".

Table 34–2 PropertyTuple Structure

Element Name	Element type	Optional	Description
pathName	xsd:string	N	The key of the name-value pair.
			Expressed as a relative UNIX path.
			Example:
			serviceName/accessControlId/access ControlId
propertyValue	xsd:string	N	The value associated with the key.

WAP Push Extended Web Service Interface Descriptions

The following describes the interfaces and operations that are available in the Subscriber Profile Extended Web Service.

Interface: SubscriberProfile

Operations to obtain specific subscriber profile attributes and operations to obtain a set of profile properties grouped together in a profile.

Operation: get

Gets specific subscriber profile attributes. The requested attributes are identified by the pathNames parameter, and the possible values are restricted by the configured capabilities of the underlying data source. The allowed path name values are also restricted individually per service provider and application in the SLA.

Input message: get

Table 34–3 Input Message: get

Part name	Part type	Optional	Description
address	xsd:anyURI	N	Identity to get profile attributes for.
pathNames	xsd:string [1unbounded]	N	Requested subscriber properties. Expressed as a relative UNIX path. Example: serviceName/accessControlId/accessControlId

Output message: getResponse

Output Message: getResponse

Part name	Part type	Optional	Description
properties	PropertyTuple [1unbounded]	N	All retrieved subscription property name and value pairs which are requested by application and allowed by the usage policies as specified in a filter. See "PropertyTuple Structure".

Table 34–5 Exceptions and Error Codes

Exception	Error code	Reason/Action
ESVC0001	WNG000002	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.
ESVC0001	SP000001	Internal problem in Services Gatekeeper.
		The LDAP connection is not working. There might be a configuration error for with the underlying LDAP server or a network error.
		Contact your Services Gatekeeper administrator.

Table 34–5 (Cont.) Exceptions and Error Codes

Exception	Error code	Reason/Action
ESVC0001	SP000002	Internal problem in Services Gatekeeper.
		LDAP operation failed.
		Contact your Services Gatekeeper administrator.
ESVC0001	SP000003	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.
ESVC0001	SP000004	Internal problem in Services Gatekeeper.
		Contact your Services Gatekeeper administrator.

Operation: getProfile

Gets a set of profile properties grouped together in a profile identified by a certain profile ID.

Input message: getProfile

Table 34-6 Input Message: getProfile

Part name	Part type	Optional	Description
subscriberID	xsd:string	N	Identity to get profile attributes for.
profileID	xsd:string	N	Identity of the profile to get.

Profile ID is ignored when connecting the to the network using the LDAPv3 network protocol plug-in. The collection of attributes that identifies the profile are provisioned as filters.

Output message: getProfileResponse

Table 34-7 Output Message: getProfileResponse

Part name	Part type	Optional	Description
properties	PropertyTuple [1unbounded]	N	All retrieved subscription property name and value pairs which are requested by application and allowed by the usage policies as specified in a filter. See "PropertyTuple Structure".

Table 34–8 Exceptions and Error Codes

Exception	Error code	Reason/Action	
SVC0001	WNG-000002	Internal problem in Services Gatekeeper.	
		Contact your Services Gatekeeper administrator.	

Table 34–8 (Cont.) Exceptions and Error Codes

Exception	Error code	Reason/Action	
SVC0001	SP-000001	Internal problem in Services Gatekeeper.	
		The LDAP connection is not working. There might be a configuration error for with the underlying LDAP server or a network error.	
		Contact your Services Gatekeeper administrator.	
SVC0001	SP-000002	Internal problem in Services Gatekeeper.	
		LDAP operation failed.	
		Contact your Services Gatekeeper administrator.	
SVC0001	SP-000003	Internal problem in Services Gatekeeper.	
		Contact your Services Gatekeeper administrator.	
SVC0001	SP-000004	Internal problem in Services Gatekeeper.	
		Contact your Services Gatekeeper administrator.	
SVC0001	PLG-000004	General plug-in routing error	

WSDLs

The document/literal WSDL representation of the SubscriberProfile interface can be retrieved from the Web services endpoint, see "Endpoint", or:

- http://host:port/ews/subscriber_profile/SubscriberProfile?WSDL
- http://host:port/ews/subscriber_profile/SubscriberProfile?WSDL/ews_ subscriber_profile_interface.wsdl
- http://host:port/ews/subscriber_profile/SubscriberProfile?WSDL/ews_common_ types.xsd

Where *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed.

Part VI

Testing Applications with the Application Test Environment

Part VI describes the Oracle Communications Services Gatekeeper Application Test Environment Graphical User Interface, and explains how to use and customize it.

Part VI contains the following chapters:

- Understanding the Application Test Environment
- Testing Applications with the Application Test Environment
- Customizing the Application Test Environment
- ATE Endpoints
- Virtual Communication Services Exception Codes

Understanding the Application Test Environment

This chapter provides an overview of the Oracle Communications Services Gatekeeper Software Development Kit (SDK) which includes the Application Test Environment (ATE). This chapter assumes that you have used the instructions in Services Gatekeeper Multi-tier Installation Guide to install the ATE.

Understanding the ATE

You use the ATE to test applications you have created that interact with Services Gatekeeper. The ATE tests applications without needing access to a running Services Gatekeeper implementation. The ATE contains a set of virtual communication services (VCSs) that simulate many of the communication services provided by Services Gatekeeper.

You can develop applications that require interaction with Services Gatekeeper (for tasks such as opening sessions, sending and receiving messages, and examining delivery reports) through the VCSs without having to connect to the network operator's Services Gatekeeper installation. When you are ready to test and deploy the application on a real Services Gatekeeper installation, you only need to change a few URLs and authentication credentials in the application.

Using the ATE, you can:


- Test the basic functionality of your application
- Test the application's behavior with different configuration settings
- Test the application's behavior with different authentication credentials
- Test the application's behavior with policy restrictions

You can customize the ATE interface, changing it's appearance and functionality to meet your implementation's needs.

Understanding the ATE Graphical Interface

The default configuration on startup resembles Figure 35–1. Your ATE may look different depending on how it has been customized by the network operator.

Figure 35-1 ATE



The upper-left panel is the elements panel. In the **Elements** tab of this panel, you create and configure elements representing mobile terminals that your application can send messages to and receive messages and notifications from. These elements are persistent. You can also create notification areas that your application can monitor. In the Messages tab of this panel, you can see a log of all the messages and notifications received by a VCS during the current session.

The upper-right panel is the map panel. You can place elements created in the elements panel on the map and drag them to another location on the map. You can also send messages from some elements and change the status of an element by right-clicking it on the map. If a notification area has been configured to monitor the location of any of the mobile terminals on the map, it will signal when a terminal has entered or left the area, depending on the configuration.

The lower-left panel is the VCS panel. Each tab accesses a different VCS, which simulates an actual communication service in Services Gatekeeper. You can display hidden VCS tabs by clicking the arrows in the tab region of the VCS panel. Each module, except the Session Manager, has two tabs: Controls and Configuration. In the **Controls** tab, you can stop and start the VCS module. The **Configuration** tab provides some configuration options, which vary for each VCS.

The **Session Manager** has a single panel from which you can start and stop the session manager.

The lower-right panel is the account manager/SLA manager/payment panel. In the **Account Manager** tab, you can set up accounts for your application to use. In the **SLA** Manager tab, you can set up simple enforcements based on values in a request or the rate of requests. In the **Payment Account** and **Payment Account Detail** tabs, you can monitor charging activity resulting from your application's requests in the Payment VCS.

You can hide and show these individual panels by clicking the small triangles at the edges of the panels. You can also resize the entire window and the individual panels.

Supported Interfaces

The ATE supports both Simple Object Access Protocol (SOAP) and Representational State Transfer (RESTful) application interfaces.

See "Creating Applications Using the SOAP Interfaces" for information about the SOAP application interface. You can also access the Parlay X 2.1 specifications at:

ftp://ftp.3gpp.org/Specs/archive/29_series/29.199-04/29199-04-650.zip and the Parlay X 3.0 specifications at:

ftp://ftp.3gpp.org/Specs/archive/29_series/29.199-02/29199-02-740.zip

See "Creating Applications Using the RESTful Interfaces" for information about the RESTful application interface.

Supported Communication Services

The ATE supports the following VCSs:

- Session Manager
- **Short Messaging**
- MultiMedia Messaging
- **Terminal Location**
- **Terminal Status**
- Payment/Diameter
- Third Party Call
- **Binary Short Messaging**

Testing Applications with the Application Test Environment

The Application Test Environment (ATE) is a graphical user interface that lets you test your applications on a simulation of Oracle Communications Services Gatekeeper.

Starting the ATE

The ATE is a standalone application. It is not necessary to install Services Gatekeeper to use the ATE.

For information about installing ATE, see "Installing the Application Test Environment" in Services Gatekeeper Multi-tier Installation Guide.

Starting the ATE on UNIX

To start the ATE on UNIX:

- Change directory to the SDK root directory.
- At a command prompt, enter run.sh.

Starting the ATE on Windows

To start the ATE on Windows, do one of the following

- To start the ATE from the Start menu, select Oracle Communications Services Gatekeeper, then select SDK.
- To start the ATE from a command prompt, change directory to the SDK root directory and enter run.cmd.

Starting the ATE on Mac OS X

To start the ATE on Mac OS X:

- Change directory to the SDK root directory.
- Enter run.sh.

Stopping the ATE

To stop the ATE:

In the ATE window, select **Exit** from the **File** menu.

Understanding Application Testing

Using the ATE, you can:

- Test the basic functionality of your application. See Basic Testing for instructions.
- Test the application's behavior with different configuration settings. See Test with Virtual Communication Service Configuration Settings for instructions.
- Test the application's behavior with different authentication credentials. See Test with Account Credentials for instructions.
- Test the application's behavior with policy restrictions. See Test Policy Enforcement for instructions.

Basic Testing

This section provides a high-level workflow for performing basic testing.

To perform basic testing:

- 1. Set the endpoints in your application to point to the ATE. See "Substituting ATE Endpoints in Your Application" for more information.
- 2. Change the credentials in the headers of your application's requests either to the default credentials or to those provided to you by the network operator.

See "Substituting Credentials in Your Application" for more information.

3. Start the ATE.

See "Starting the ATE" for more information.

4. Add some elements to the ATE map or use existing elements.

By default, a mobile terminal element with the address "tel:1234" is provided in the default configuration. Your application can send messages to and receive messages and notifications from mobile terminals on the map. You can also verify whether a terminal has entered or left a defined notification area.

See "Setting Up and Using Map Elements" for more information.

5. Verify that the VCSs that your application uses are started.

They should be started by default, but if they are not, start them. See "Starting/Stopping a VCS" for more information.

- **6.** Start your application.
- 7. (Optional) If your application uses the SOAP-based application interfaces and you want to see the SOAP content for each VCS request, do the following:
 - **a.** In the ATE, select **Settings** from the **File** menu.

The Settings dialog box appears.

b. Select the **Print SOAP content for each VCS request** check box.

The SOAP content is displayed in the command window from which you started the ATE. You must have started the ATE from a command window to use this option.

8. Use the application to send and receive messages and notifications to and from the elements that you created in step 4.

9. Check results in the ATE (to verify that messages were received) and in your application.

Test with Virtual Communication Service Configuration Settings

To test your application's behavior with different configuration settings:

- Configure each VCS that corresponds to a communication service that your application uses.
 - See "Configuring VCS Settings" for more information.
- 2. Repeat the steps outlined in Basic Testing with different VCS configuration settings.

Test with Account Credentials

To test requests with credentials that are different from the defaults:

- Set up one or more accounts using the Account Manager.
 - See "Managing Accounts" for more information.
- Change the credentials in the headers of your application's requests to the credentials of the accounts that you set up in the ATE.
- Repeat the steps outlined in Basic Testing with the credentials of your ATE accounts.

Test Policy Enforcement

To test simple policy enforcements:

- Set up one or more value and rate enforcements using the SLA Manager. See "Managing Service-Level Agreements" for more information.
- Repeat the basic testing outlined in Basic Testing by sending requests that violate the SLA enforcements that you set up in the ATE.

Substituting ATE Endpoints in Your Application

To use the ATE, you must change the endpoints in your application to point to the ATE rather than to Services Gatekeeper. See "ATE Endpoints" for the ATE endpoints for the SOAP and RESTful interfaces.

Substituting Credentials in Your Application

By default, the ATE enforces security.

Applications sending requests to the VCS must supply a user name/password combination in the SOAP header or Hypertext Transfer Protocol (HTTP) basic authentication credentials that correspond to those in your application account in the ATE.

The default credentials are:

- User Name=domain_user
- Password=domain user

Your network operator may have set up a special ATE account for your application and configured your ATE for those credentials.

You can also create your own accounts. See "Managing Accounts" for more information.


Setting Up and Using Map Elements

The ATE provides three graphic elements to test applications:

- Phone
- Mobile elements that are not phones (truck)
- Circular notification area

You add elements from the elements panel. After you have added elements to the map, you can move them by dragging around the map. Figure 36–1 shows an elements panel containing a a phone element, a circular notification area element, and a truck element.

Figure 36-1 Elements Panel



If the elements panel is not currently displayed, you can display it.

To display the elements panel:

- 1. Click one of the small black triangles at the edge of one of the panels that is displayed.
- **2.** Click the **Elements** tab if it is not already selected.

Adding and Using Phone Elements

The phone element represents a mobile terminal that can send and receive messages. You use a phone element to test how your application handles incoming and outgoing messages to and from mobile phones.

Every phone has an address, a position, and a status.

Adding a Phone Element

To add a phone to the map from the elements panel:

- Click the + symbol in the bottom left corner of the elements panel.
 - The Add Map Element dialog box appears.
- From the menu, select **Phone**.
- 3. Click OK.

The Properties dialog box appears, with some default values.

- **4.** In the **address** field, enter a value that is unique in the ATE in the tel: address format: for example **tel: 1234**.
- 5. From the **status** menu, select the status of the phone. Valid values are **Busy**, Reachable and Unreachable.
- **6.** If desired, set the position of the phone by entering values in the **longitude**, **latitude**, and **altitude** fields.

For these values, the ATE considers a maximum precision of four positions after the decimal point.

You can also set the latitude and longitude by dragging the phone element across the map after it has been added.

Changing the phone element's position in the Properties dialog box may cause the phone to move off the map. You can still access the phone from the elements panel, even when it is not visible on the map.

7. Click OK.

The phone is added. If its position is within the coordinates of the map, it appears on the map.

Changing a Phone Element's Properties

To change a phone element's properties:

- 1. Access the phone's properties by doing one of the following:
 - In the elements panel, double-click the phone element.
 - In the elements panel, select the phone element and click the pencil symbol in the bottom left corner of the elements panel.

The Properties dialog box appears.

Enter the values that you want to change.

See "Adding a Phone Element" for information about the individual fields.

3. Click **OK**.

Removing a Phone Element

To remove a phone, do one of the following:

- In the map, right-click on the phone and select **Remove**.
- In the elements panel, select the phone and click the symbol in the bottom left corner of the elements panel.

Sending an SMS from a Phone Element

You can send an Short Message Service (SMS) message from a phone element that is on the map.

To send an SMS message:

- Right-click the phone element that is sending the message and select Send SMS. The SmsMessage dialog appears.
- 2. In the **sourceAddress** field, enter the address of the terminal sending the message. The default is the phone element that you clicked, but you can enter a different address in this field.
- In the **destinationAddress** field, enter the terminal/short code of the terminal that will receive the message.
- **4.** In the **message** field, enter the text of the message.
- Click **OK**.

Sending an MMS from a Phone Element

You can send an Multimedia Messaging Service (MMS) message from a phone element that is on the map.

To send an MMS message:

- 1. Right-click the phone element that is sending the message and select **Send MMS**. The MmsMessage dialog appears.
- **2.** In the **sourceAddress** field, enter the address of the terminal sending the message. The default is the phone element that you clicked, but you can enter a different address in this field.
- 3. In the **destinationAddress** field, enter the terminal/short code of the terminal that will receive the message.
- **4.** In the **subject** field, enter the subject line of the message.
- **5.** In the **priority** field, enter the priority of the message. This can be any text.
- 6. Click OK.

Sending a Binary SMS from a Phone Element

You can send a Binary SMS from a phone element that is on the map.

The binary data must be in hexadecimal format.

To send a Binary SMS:

1. Right-click the phone element that is sending the message and select **Send Binary** SMS.

The SmsBinaryMessage dialog appears.

2. In the **sourceAddress** field, enter the address of the terminal sending the message.

- The default is the phone element that you clicked, but you can enter a different address in this field.
- 3. In the destinationAddress field, enter the terminal/short code of the terminal that will receive the message.
- 4. In the byteMessage field, enter message data formatted according to the TP-User Data (TP-UD), excluding the TP-User-Data-Header--Indicator (TP UDHI).
- **5.** In the **dcs_hex** field, enter the data encoding schema used to encode the binary data.

Table 36-1 Data Encoding Schemes

Bits 7 6 5 4 3 2 1	Meaning
0000000	SMSC Default Alphabet
00000001	IA5 (CCITT T.50)/ASCII (ANSI X3.4)
00000010	Octet unspecified (8-bit binary)
00000011	Latin 1 (ISO-8859-1)
00000100	Octet unspecified (8-bit binary)
00000101	JIS (X 0208-1990)
00000110	Cyrllic (ISO-8859-5)
00000111	Latin/Hebrew (ISO-8859-8)
00001000	UCS2 (ISO/IEC-10646)
00001001	Pictogram Encoding
00001010	ISO-2022-JP (Music Codes)
00001011	reserved
00001100	reserved
00001101	Extended Kanji JIS(X 0212-1990)
00001110	KS C 5601
00001111	reserved
10111111	reserved
1100xxxx	GSM MWI control. See:
	http://www.etsi.org/deliver/etsi_gts/03/0338/05.03.00_60/gsmts_0338v050300p.pdf
1101xxxx	GSM MWI control. See:
	http://www.etsi.org/deliver/etsi_gts/03/0338/05.03.00_60/gsmts_0338v050300p.pdf
1110xxxx	reserved
1111xxxx	GSM message class control. See:
	http://www.etsi.org/deliver/etsi_gts/03/0338/05.03.00_60/gsmts_0338v050300p.pdf

For more information about data encoding, see the data_encoding section of the SMPP v 3.4 specification.

6. In the **protocolId_hex** field, enter the protocol identifier.

The protocol identifier specifies the higher layer protocol being used or indicates networking with a certain type of telematic device. For more information, see 3GPP TS 23.040 V6.5.0, Technical realization of the Short Message Service (SMS) at:

http://www.3gpp.org/ftp/Specs/html-info/23040.htm

Click OK.

Sending an Example Message from a Phone Element

This is identical to the procedure for sending an SMS.

See "Sending an SMS from a Phone Element" for more information.

Reading a Phone Element's Received Messages

If a phone element has received messages, from another element on the map or from your application, a number next to the phone element indicates the number of messages in its inbox.

To read a phone element's received messages:

Right-click the phone element and select **Read Messages**.

The phone element's messages are displayed.

You can also view a log of the messages received by all the phone elements in the **Messages** tab of the elements panel.

Deleting a Phone Element's Messages

To delete all of a phone element's messages:

Right-click the phone element for which you want to delete messages and select Delete Messages.

The Delete Messages dialog box appears.

2. Select Yes.

To delete a selected message:

1. Right-click the phone element and select **Read Messages**.

The phone element's messages are displayed.

- **2.** Select the message that you want to delete.
- **3.** Click the trash icon in the lower right corner of the message window.

The message is deleted.

Setting a Phone Element's Status

To set a phone element's status:

- 1. Right-click the phone element in the map.
- Select Set Status.
 - A **StatusMessage** menu appears, displaying a status menu.
- **3.** In the status menu, select the status of the phone. Valid values are **Busy**, Reachable and Unreachable.

You can also set a phone element's status in the phone element's Properties dialog box. See "Changing a Phone Element's Properties" for more information.

Reading a Phone Element's Third Party Call Status


The Third Party Call VCS logs the call status of successful third party calls.

To read the log of third party calls:

- Right-click the phone element on the map.
- Select Read Call Status . . .

The Call Information window appears.

Figure 36–2 Third Party Call Log



The three status conditions that can be logged for successful third party calls are:

- **CallInitial**: The call has been place but not yet connected.
- **CallConnected**: The call has connected.
- **CallTerminated**: The call has terminated.

If the caller or callee terminal status is Busy or Unreachable, the third party call is not established and not recorded in the log. See "Setting a Phone Element's Status" for information about setting the terminal status.

The call log holds a maximum of ten calls. If more than ten calls are made, calls are automatically deleted from the log on a first-in first-out (FIFO) basis. The user can also manually delete a call from the log by selecting it and then clicking trash icon in lower left corner of the Call Information window.

Adding and Using Mobile Elements That Are Not Phones

The truck element symbolizes a mobile terminal that is not a phone. Typically it is used to represent a vehicle that contains a flat panel capable of receiving and displaying messages to a driver, but it can be used to represent other mobile devices as well.

A truck element has the same characteristics as a phone element.

To add, remove, configure, and use a truck element, follow the instructions for phone elements in "Adding and Using Phone Elements".

Adding and Using Circular Notification Area Elements

The circular notification area element represents the geographic area for which the application wishes to receive notifications when a mobile terminal enters or leaves the area. The ATE supports multiple notification areas on the same map. Notification areas can overlap.

Adding a Circular Notification Area

To add a circular notification area to the map:

- 1. Click the + symbol in the bottom left corner of the elements panel.
 - The Add Map Element dialog box appears.
- Select **Circular Notification Area** from the menu.
- Click OK.

The Circular Notification Area Properties dialog box appears, with some default values.

- In the **id** field, enter a unique identifier for the notification area.
- In the addresses field, enter a comma-separated lists of the addresses for which notification is requested. The format is "tel:1234, tel:2345, tel:3456, . . . ".
- In the trigger field, specify whether notification is requested when terminals enter the area or when they leave the area. Valid values are MS_ENTERING and MS_ LEAVING.
- **7.** Optional settings:
 - a. Set the position of the area by entering values in the **longitude** and **latitude** fields. These coordinates represent the center of the notification area.

For these values, the ATE considers a maximum precision of four positions after the decimal point.

You can change the latitude and longitude of a notification area by dragging the area element across the map after it has been created.

Changing the position may cause the notification area to move off the map. You can still access the notification area from the elements panel, even when it is not visible on the map.

- Set the size of the notification area by entering a value in the **radius** field.
 - The ATE considers a maximum precision of four positions after the decimal point.
- **c.** Enter the frequency (in seconds) at which periodic location notifications should be sent to the application in the **interval** field.
- Enter the maximum number of notifications to be sent to the application in the **count** field. This value represents the number of notifications sent in total, not the number of notifications per mobile terminal address.

Changing a Circular Notification Area's Properties

To change a notification area's properties:

- To access the notification area's properties do one of the following:
 - Double-click the notification area's element in the elements panel.
 - Select the notification area's element in the elements panel and click the pencil symbol in the bottom left corner of the elements panel.

The Properties dialog box appears.

2. Enter the values that you want to change.

See "Adding a Circular Notification Area" for information about the individual fields.

Removing a Circular Notification Area

To remove a circular notification area, do one of the following:

- In the map, right-click on the edge of the circular notification area and select Remove.
- In the elements panel, select the circular notification and click the symbol in the bottom left corner of the elements panel.

Displaying a Custom Map

You can substitute a map of your choice for the default map.

The map must be in BMP, JPEG, or PNG format.

You need to know the geographic coordinates of at least two diagonally-opposite corners of the map to be able to set the map's latitude and longitude ranges.

For the latitude and longitude values that define the edges of the map, the ATE considers a maximum precision of four positions after the decimal point.

Figure 36–3 shows a typical custom map, displaying a truck and mobile device.




Figure 36-3 Custom Map with Coordinates Displayed

If the map panel is not currently displayed, you can display it by clicking one of the small black triangles at the edge of one of the panels that is displayed.

You add a custom map from the map panel.

To display a custom map:

1. Click the following symbol, which appears in the lower-right corner of the map panel.



The Map Properties dialog box appears.

- In left Longitude field, enter the lowest longitude value for an east/west edge of the map.
- **3.** In the right **Longitude** field, enter the highest longitude for the other east/west edge of the map.
- In the left **Latitude** field, enter the lowest latitude value for a north/south edge of the map.
- In the right **Latitude** field, enter the highest latitude value for the other north/south edge of the map.
- If you want the values of the coordinates set in the preceding steps to be displayed in the map, check the **Show Ranges** check box.
- Select the **Custom Image** option.
 - A file browser appears.
- Navigate to the file that contains your map image.
- Select the map image file.
- 10. Click OK.

The custom map appears in the map panel.

You can return to the default map by selecting the **Default Image** option in the Map Properties dialog box.


Any elements created after the substitution of a custom map will have their default coordinates adjusted to the coordinates of the new map.

Configuring, Starting and Stopping the VCS

You manipulate the VCS used by your application in the VCS panel.

Figure 36–4 shows the VCS panel with the **Short Messaging/Controls** tab selected.

Figure 36-4 VCS Panel



If the VCS panel is not currently displayed, you can display it by clicking one of the small black triangles at the edge of one of the panels that is displayed.

Each individual VCS is represented by a tab in the VCS panel. Choose the tabs that correspond to the services used by your application to access a particular VCS's settings.

Starting/Stopping a VCS

By default, all VCSs are started when the ATE starts.

You can stop and restart a VCS using the Start and Stop buttons that appear in the **Session Manager** tab and in the **Control** sub-tabs displayed for the other VCSs.

VCS MBean Object and Class Names

If you want to connect your application to a VCS programmatically, you need to know the full paths of the MBean object and class names.

To view the object name and class name of any VCS:

- 1. Click a VCS tab.
- Click the **Configuration** tab.
- Click any attribute or operation in the VCS tab.

A panel appears displaying fields for configuration.

Click this icon, which appears at the top of the configuration panel when an operation or attribute is selected:



A window displaying the VCS's object name and class name appears.

Configuring VCS Settings

This section describes the attributes that you can configure and the operations you can perform for a specific VCS.

These settings are for the purpose of testing the application's behavior in the ATE and do not necessarily represent attributes and operations in Services Gatekeeper or in the application.

Configuring the Short Messaging VCS

To configure the Short Messaging VCS:

- In the VCS panel, click the **Short Messaging** tab.
 - The Short Messaging panel appears.
- Click the **Configuration** tab.

The Short Messaging VCS's list of configuration options appears.

Select the operation that you want to perform.

A panel displaying fields for the operation's input parameters and, if appropriate, a field for the operation's output appears.

- **4.** Enter any input parameters required by the operation. See "Configuring Offline Notifications for SMS Messages" below.
- Click the green triangle, which performs the operation.

Configuring Offline Notifications for SMS Messages

The Short Messaging VCS supports operations for configuring how offline notifications are handled.

An offline notification is a message received by the ATE when the application is offline. The ATE saves the message. When the application comes online and polls for mobile-originated messages, the ATE forwards the saved messages to the application if offline notification is enabled.

disableReceiveSms

Disables offline notification of a received SMS.

If offline notification is disabled, the ATE does not save or forward mobile-originated messages received while the application was offline.

Table 36-2 Parameters for disableReceiveSms

Parameter	Description
Correlator	The id value returned by the corresponding enableReceiveSms operation.

enableReceiveSms

Enables offline notification of a received SMS addressed to a specified shortcode.

The ATE notifies the application when it has received a message addressed to the specified shortcode in which the message contains a match to the specified criteria. If no criteria are specified, the ATE forwards all messages received by the specified shortcode while the application was offline.

Table 36-3 Parameters for enableReceiveSms

Parameter	Description
Shortcode	Destination address to which the message was sent.
Criteria	Optional. Text to match in the message. If the text matches, the application receives the notification.

listOfflineNotifications

Displays a list of registered offline notifications.

Configuring the Multimedia Messaging VCS

To configure the Multimedia Messaging VCS:

- 1. In the VCS panel, click the Multimedia Messaging tab. The Multimedia Messaging panel appears.
- **2.** Click the **Configuration** tab.

The Multimedia Messaging VCS's list of configuration options appears.

3. Select the operation that you want to perform.

A panel displaying fields for the operation's input parameters and, if appropriate, a field for the operation's output appears.

- **4.** Enter any input parameters required by the operation.
 - Operations and parameters are listed below.
- Click the green triangle, which performs the operation.

Configuring Offline Notifications for MMS Messages

The Multimedia Messaging VCS supports operations for configuring how offline notifications are handled.

An offline notification is a message received by the ATE when the application is offline. The ATE saves the message. When the application comes online and polls for mobile-originated messages, the ATE forwards the messages to the application if offline notification is enabled.

disableReceiveMms

Disables off-line notification of a received MMS.

If offline notification is disabled, the ATE does not save or forward mobile-originated messages received while the application was offline.

Table 36–4 Parameters for disableReceiveMms

Parameter	Description
Correlator	The value returned by the corresponding enableReceiveMms operation.

enableReceiveMms

Enables off-line notification of a received message sent to a specified short code. This is used by applications that poll for mobile-originated messages.

The ATE notifies the application when it has received a message addressed to the specified shortcode in which the message contains a match to the specified criteria. If no criteria are specified, the ATE forwards all messages received by the specified shortcode while the application was offline.

Table 36–5 Parameters for enableReceiveMms

Parameter	Description
Shortcode	Destination address to which the message was sent.
Criteria	Optional. Text in the message to match against. If the text matches the first word in the message, the application receives the notification.
AppInstanceID	Application instance identifier of the application instance receiving the notification.

listOfflineNotifications

Displays a list of registered offline notifications.

Configuring the Terminal Location VCS

To configure the Terminal Location VCS:

In the VCS panel, click the **Terminal Location** tab.

The Terminal Location panel appears.

2. Click the **Configuration** tab.

The Terminal Location VCS's list of configuration options appears.

3. Click the attribute to configure.

A panel displaying the attribute's check box or field appears.

4. Set the attribute.

Attributes for the Terminal Location VCS are listed below.

- **5.** If you want to restore all the settings to their default values, do the following:
 - **a.** Click the **resetToDefault** operation.

The operation's panel appears.

b. Click the green triangle in the panel, which re-sets the attributes to their default values.

The Terminal Location VCS supports the following attributes:

AltitudeAlwaysAvailable

If selected, altitude information is always available for all location responses.

AltitudeSometimesAvailable

If selected, altitude information is sometimes available for some or all location responses.

GeographicalNotificationAvailable

If selected, notifications can be set up based on geographical coordinates.

MaximumAddresses

Maximum number of addresses for which a notification can be requested.

MaximumCount

Maximum number of notifications that can be requested.

If zero or blank, there is no maximum. In this case, select UnlimitedCountAllowed also.

MaximumNotificationDuration

Maximum amount of time (in seconds) for which a notification can be set up.

MaximumNotificationFrequency |

Maximum rate of notification delivery. Can also be viewed as the minimum interval (in seconds) between notifications.

MinimumAcceptableAccuracy |

Minimum distance from the terminal that the application considers useful. The unit applies to distance (for example, meters or feet).

MinimumAccuracy

Minimum distance from the terminal for which the application wishes to receive location information. The unit applies to distance (for example, meters or feet).

MinimumTrackingAccuracy

Minimum tracking accuracy refers to the accuracy of the tracking technology, not to the accuracy of the notification area. For example, a low value is appropriate to a device tracking a person entering a building, while a high value would be appropriate to a device tracking a plane landing in a city.

The unit applies to distance (for example, kilometers or feet).

PeriodicNotificationAvailable

If selected, periodic notification can be set up for a set of terminals at an application-defined interval.

UnlimitedCountAllowed

If selected, an unlimited notification count is allowed.

Configuring the Terminal Status VCS

To configure the Terminal Status VCS:

1. In the VCS panel, click the **Terminal Status** tab.

The Terminal Status panel appears.

2. Click the **Configuration** tab.

The Terminal Status VCS's list of configuration options appears.

3. Click the attribute that you want to configure.

A panel displaying the attribute's check box or field appears.

4. Set the attribute.

Attributes for the Terminal Status VCS are listed below.

- **5.** If you want to restore all the settings to their default values:
 - **a.** Click the **resetToDefault** operation.

The operation's panel appears.

b. Click the green triangle in the panel, which re-sets the attributes to their default values.

The Terminal Status VCS supports the following attributes:

BusyAvailable

If selected, **busy** can be returned as a status.

If not checked and the application includes the **busy** criterion in a Start Notification request, the client is not notified of the terminal's busy status and the VCS throws a policy exception.

MaximumAddresses

Maximum number of addresses for which a notification can be set up or statuses be retrieved.

MaximumCount

Maximum number of notifications that can be requested.

If zero or blank there is no maximum. In this case, select UnlimitedCountAllowed also.

MaximumNotificationDuration

Maximum amount of time (in seconds) for which a notification can be set up.

MaximumNotificationFrequency

Maximum rate of notification delivery. Can also be viewed as the minimum interval (in seconds) between notifications.

UnlimitedCountAllowed

If selected, an unlimited notification count is allowed.

Configuring the Payment VCS

To configure the Payment VCS:

1. In the VCS panel, click the **Payment** tab.

The Payment panel appears.

2. Click the **Configuration** tab.

The Payment VCS's list of configuration options appears.

3. Click the attribute that you want to configure.

A panel displaying the attribute's check box or field appears.

4. Set the attribute.

Attributes for the Payment VCS are listed below.

5. Select the operation that you want to perform.

A panel displaying fields for the operation's input parameters and, if appropriate, a field for the operation's output appears.

Enter any input parameters required by the operation.

Operations and parameters are listed below.

7. Click the green triangle, which performs the operation.

The Payment VCS supports the following attributes:

ExpiredTime

Duration of a reservation, in milliseconds.

The default is -1, which indicates that no duration is set.

SplitSupport

If checked, the chargeSplitAmount request is supported.

SplitNumbers

Maximum number of end users that can be charged in a single chargeSplitAmount request.

The Payment VCS supports the following operations:

createUserAccount

Creates a user account.

Table 36-6 Parameters for createUserAccount

Parameter	Description
username	User name for the account
originalAmount	Original amount of money in the account

listAllReservationRecords

Lists all the reservation records.

listAllUserAccounts

Lists all the user accounts.

listReservationRecord

Lists the reservation record detail for the specified session.

Table 36-7 Parameters for listReservationRecord

Parameter	Description
reservatiionID	Reservation ID for the reservation records to be described

listUserAccount

Lists user account information, including the account's current balance and original amount, for the specified account.

Table 36-8 Parameters for listUserAccount

Parameter	Description
userID	UserID for the account to be described

listUserChargeRecord

Lists the charge record detail for the specified account.

Table 36-9 Parameters for listUserChargeRecord

Parameter	Description
userID	User ID for the charge record to be described

refreshPaymentUI

Refreshes the Payment VCS user interface.

resetToDefault

Resets all the Payment VCS settings to their default values.

Configuring the Third Party Call VCS

To configure the Third Party Call VCS:

In the VCS panel, click the **Third Party Call** tab.

The Third Party Call panel appears.

Click the **Configuration** tab. 2.

The Third Party Call VCS's list of configuration options appears.

Click the attribute that you want to configure.

A panel displaying the attribute's check box or field appears.

Set the attribute.

Attributes for the Third Party call VCS are listed below.

- If you want to restore all the settings to their default values:
 - **a.** Click the **resetToDefault** operation.

The operation's panel appears.

Click the green triangle in the panel, which re-sets the attributes to their default values.

The Third Party Call VCS supports the following attributes:

ChargingAllowed

If selected, charging can be applied to calls.

StatusRententionTime

The length of time, in seconds, to retain status after the call has terminated.

Configuring the Binary Short Messaging VCS

To configure the Binary Short Messaging VCS:

- 1. In the VCS panel, click the **Binary Short Messaging** tab.
 - The Binary Short Messaging panel appears.
- **2.** Click the **Configuration** tab.
 - The Binary Short Messaging VCS's configuration option appears.
- **3.** Click the green triangle, which performs the operation.

The Binary Short Messaging VCS supports the following operation.

listOfflineNotifications

Displays a list of registered offline notifications.

An offline notification is a message received by the ATE when the application is offline. The ATE saves the message. When the application comes online and polls for mobile-originated messages, the ATE forwards the saved messages to the application if offline notification is enabled.

Troubleshooting

If your application does not perform as expected (for example, your messages and notifications are not received), check the exceptions thrown by the failing operation.

Exceptions with an SVC prefix indicate an error against the service. Exceptions with a POL prefix indicate a violation of a policy enforcement. See "Managing Service-Level Agreements" for information about setting policy enforcements in a VCS.

See "Virtual Communication Services Exception Codes" for the lists of exception codes for each VCS.

Simple Mobile-Terminated Test

A simple example is to test a Send Sms request from your application to a phone element in the ATE.

To test Send Sms:

1. In your application, change the endpoint for the Send Sms request to point to the

If you are using the SOAP interface, see Table A-5, "Endpoints for SOAP SendMessage Interface" for the endpoint. If you are using the RESTful interface, see Table A-21, "Endpoints for RESTful Send SMS Operation".

- **2.** Start the SDK.
- **3.** Add a phone element to the map.

See "Adding a Phone Element" for information about adding a phone element.

- **4.** Click the **Short Messaging** VCS tab to verify that the Short Messaging VCS is running. Click the **Start** button if it is not running.
- **5.** Start the application.
- From the application, send an SMS to the phone element.
- **7.** Read the received message in the ATE.

See "Reading a Phone Element's Received Messages" for more information.

If the message text does not appear in the ATE, check the exceptions associated with the Send Sms request to identify the source of the problem. See "Short Messaging Exception Codes" for more information.

You can use this procedure as a general outline for testing mobile-terminated requests.

Simple Mobile-Originated Test

A simple example is to test a Receive Sms request by sending an SMS from a phone element in the ATE to an address in your application.

To test Receive Sms:

In your application, change the endpoint for the Receive Sms request to point to the ATE.

If you are using the SOAP interface, see Table A-7, " Endpoints for SOAP ReceiveMessage Interface" for the endpoint. If you are using the RESTful interface, see Table A-24, "Endpoints for RESTful Get Received SMS Operation".

- **2.** Start the SDK.
- **3.** Add a phone element to the map.

See "Adding a Phone Element" for information about adding a phone element.

- Click the Short Messaging VCS tab to make sure that the Short Messaging VCS is running. Click the **Start** button if it is not running.
- **5.** Start the application.
- From the phone element, send an SMS to an address defined in the application.
- **7.** Fetch the SMS in the application using the Receive Sms request.

If the message is not available in the application, check the exceptions associated with the Receive Sms request to identify the source of the problem. See "Short Messaging Exception Codes" for more information.

You can use this procedure as a general outline for testing mobile-originated requests.

Managing Accounts

The ATE is configured with a default application account: domain_user/domain_user.

You can remove this default account.

You can also set up additional accounts.

To set up an account:

- In the account manager/sla manager panel, click the **Account Manager** tab.
- Click the + symbol.

A new row for the account information appears with the default values name/password.

- **3.** Overwrite the name with the account's user name in the **User Name** field.
- **4.** Overwrite the password with the account's password in the **Password** field.

The account is set up. An application should pass the user name/password values for its account before it submits a request to a secure VCS.

To modify an account's user name or password:

- In the account manager/sla manager panel, click the **Account Manager** tab.
- Overwrite the values that you want to change.

To remove an account:

- In the account manager/sla manager panel, click the **Account Manager** tab.
- Select the account that you want to remove.
- Click the symbol.

The account is removed.

Managing Service-Level Agreements

You can set up simple service-level agreement (SLA) enforcement for VCS requests to use in your tests. The ATE supports two types of enforcement:

- Value enforcement: rejects a request based on a specific value in the request; for example: the subject of an SMS contains the string "foo"
- Rate enforcement: rejects a request based on a rate value: for example, a specified number of requests per minute

To enable/disable simple SLA enforcement:

- 1. In the account manager/sla manager panel, click the SLA Manager tab.
- **2.** Do one of the following:
 - To enable SLA enforcement, select the **Enable SLA enforcements** check box.
 - To disable SLA enforcement, select the **Disable SLA enforcements** check box.

All SLA enforcements set up for the VCS are either enabled or disabled as a group. You cannot selectively enable or disable a subset of them.


Managing Value Enforcements

To set up a value enforcement:

- 1. In the account manager/sla manager panel, click the **SLA Manager** tab.
- **2.** Click the **Value Enforcements** tab.
- **3.** Click the + symbol.
- In the **Path** field, enter the element in the VCS request against which the value will be enforced; for example: **SendMessage.subject**, SendMessage.charging.currency, GetLocation.maximumAge. No spaces are permitted in the **Path** field.

If you do not know the exact name of the element, click the magnifying glass icon next to the **Path** field. A browser appears in which you can locate the path by expanding the entry for the appropriate service.


Figure 36-5 Browser for Element Paths



- From the **Operation** menu, select the operation to be applied. Valid values are: CONTAINS, DOES_NOT_CONTAIN.
- In the **Value** field, enter the value against which the element will be tested.

Figure 36–6 shows two value enforcements in the SLA Manager. The first allows messages in which the subject contains the word urgent. The second allows messages in which the charging currency does not contain **renminbi**.

Figure 36–6 SLA Manager Value Enforcements Tab



To modify a value enforcement:

- In the account manager/sla manager panel, click the **SLA Manager** tab.
- Overwrite the values that you want to change.

To remove a value enforcement:

- In the account manager/sla manager panel, click the **SLA Manager** tab.
- Click the Value Enforcements tab.

- **3.** Select the value enforcement that you want to remove.
- **4.** Click the **-** symbol.

The enforcement is removed.

Managing Rate Enforcements

To set up a rate enforcement:

- 1. In the account manager/sla manager panel, click the **SLA Manager** tab.
- **2.** Click the **Rate Enforcements** tab.
- **3.** Click the + symbol.
- 4. In the **Request Name** field, select the request for which the enforcement will be enforced. No spaces are permitted in the **Request** field.
- **5.** In the **Request Count** field, enter an integer representing the maximum number of requests allowed in a specified time period.
- In the **Time Amount** field, enter an integer representing the time period against which the request count is applied.
- From the **Time Unit** menu, select the unit of time to which the time amount applies. Valid values are SECONDS, MINUTES, or HOURS.

Figure 36–7 shows a rate enforcement in the SLA Manager. It allows a maximum of 5 sendSms requests every 10 seconds.

Figure 36–7 SLA Manager Rate Enforcements Tab



Monitoring Payment Accounts

You can test the charging functionality in your application by monitoring changes in the **Payment Account** and **Payment Account Detail** tabs.

To test charging:

- 1. Create one or more subscriber accounts using the createUserAccount operation in the Payment VCS. See "createUserAccount" for more information.
 - Or use a default account displayed in the Payment Account tab. The Payment VCS creates a subscriber account for every phone element in the ATE.
- 2. In your application, charge and refund the subscriber accounts created in step 1 using various Payment requests such as chargeAmount, refundAmount, and chargeSplitAmount.
- **3.** Click the **Payment Account** tab.

The amounts in the Credits column reflect the resulting balance of the charges and refunds made by the application for each account.

4. Click the **Payment Account Detail** tab.

Each charge and refund made by the application against subscriber accounts is logged here.

Example Module

A VCS example module is deployed in the SDK.

You can find it in the <code>ocsg_sdk/lib/modules</code> subdirectory of your SDK installation.

Customizing the Application Test Environment

This chapter describes how to customize the Oracle Communications Services Gatekeeper Application Test Environment (ATE) using a configuration file.

Understanding Customizing the ATE

Network operators can use a startup configuration file to create a custom version of the ATE that reflects the services and defaults that they want to expose to application developers. Once created, you can distribute the configuration file to any number of systems, and ATEs that you start on those systems have identical configurations.

For information on incorporating new custom communication services into the ATE, see the discussion of the virtual communication service module for the ATE in Services Gatekeeper Extension Developer's Guide.

Understanding the ATE Configuration File

To customize the ATE, create a configuration file that defines the version to distribute. This configuration sets the appearance of the ATE on its initial startup.

To create an ATE configuration file:

- Create a file named **startup-configuration.xml**.
- Save this file in the product installation directory of the ATE.

If a startup-configuration.xml file exists in the product installation directory of the ATE, the ATE takes on the appearance and behavior configured by the elements in that file. Elements not included in this configuration file retain their default appearance and behavior.

If no **startup-configuration.xml** file exists in the product installation directory, the entire default configuration is used.

You can use a different filename for startup-configuration.xml by overriding the oracle.ocsq.pte.startup.confiq system property.

Example Startup Configuration File

The following is a sample **startup-configuration.xml** file that you can use as a basis for creating your own. The rest of this chapter explains the various elements in detail.

```
<config xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
    xsi:noNamespaceSchemaLocation="http://www.oracle.com/ns/ocsg/50/at">
```

<general>

```
<title>A new title for the ATE</title>
    <version>7.0</version>
    <copyright>(c) 2010 My Company</copyright>
    <icon>anewicon.gif</icon>
  </general>
  <account visible="true">
    <users>
      <user name="domain_user" password="domain_user"/>
      <user name="bob" password="foo"/>
  </account>
  <sla visible="true">
    <enforcements enabled="true">
      <value path="sendMessage.subject" operation="contains" value="world"/>
      <value path="sendMessage.charging.currency" operation="does_not_contain"</pre>
value="euro"/>
      <request name="sendSms" count="5" timeAmount="10" timeUnit="seconds"/>
    </enforcements>
  </sla>
  <payment visible="false"/>
  <VCS>
    <mbeans>
      <mbean name="px21_tl" attribute="MaximumCount" value="7"/>
    </mbeans>
    <visible>
      <module
className="oracle.ocsg.pte.impl.vcs.sessionmanager.SessionManagerModule"
title="Session Manager"/>
      <module className="oracle.ocsg.pte.impl.vcs.px21_sms.SmsModule" title="Short</pre>
Messaging"/>
      <module className="oracle.ocsg.pte.impl.vcs.px21_tl.TerminalLocationModule"</pre>
title="Terminal Location"/>
    </visible>
  </vcs>
</config>
```

Configuration Element Order

The top-level configuration elements must appear in the order in which they appear in the example.

The order is:

- 1. <general>
- 2. <account>
- **3.** <sla>
- 4. <payment>
- **5.** <vcs>

When Configuration Elements Are Read

The ATE reads most configuration elements when the ATE starts.

Exceptions are the data elements: <users> inside the <account> element and <enforcements>, inside the <sla> element. The ATE reads <users> and <enforcements> only on installation of the ATE.

To force the ATE to use the elements in the configuration file without reinstalling the ATE:

- 1. Stop the ATE.
- Delete the *sdk_home_dir/product_installation_dir/***runtime/pte.dat** file.
- Edit the **startup-configuration.xml** file with your changes.
- Save the file.
- Start the ATE.

Customizing ATE General Characteristics

You can change the following general characteristics of the ATE in the <general> element in the **startup-configuration.xml** file.

- title
- version
- copyright
- icon

The title, version, and icon appear in the ATE title bar and in the About window accessed from the ATE's **Help** menu item.

The copyright appears in the About window.

To customize general characteristics of the ATE:

- Create a <general> element in the **startup-configuration.xml** file, or use an existing <general> element.
- Do any or all of the following:
 - To change the title of the ATE, create a <title> element inside the <general> element and enter your title for the ATE between the <title> element's delimiters.
 - To change the version of the ATE, create a <version> element inside the <general> element and enter your version string between the <version> element's delimiters.
 - To change the copyright of the ATE, create a <copyright> element inside the <general> element and enter your copyright string between the <copyright> element's delimiters.
 - To change the icon of the ATE, create an <icon> element inside the <general> element and enter the name of the icon image file between the <icon> element's delimiters.
 - Store the icon image in the ATE root directory, which is the same directory that contains the **startup-configuration.xml** file.
- **3.** Save the file.

Any elements that you do not specify remain unchanged from the default ATE.

The following is a sample <general> element.

```
<general>
 <title>A new title for the ATE</title>
 <version>7.0</version>
 <copyright>(c) 2010 My Company</copyright>
 <icon>anewicon.gif</icon>
</general>
```

Customizing a VCS

You can customize a virtual communication service (VCS) in the following ways:

- Showing/Hiding a VCS Module
- Changing a VCS Title
- Reconfiguring the Default VCS MBean Attributes.

You configure these customizations in the <vcs> element of the startup-configuration.xml file.

Showing/Hiding a VCS Module

By default, all VCSs are invisible in the ATE.

To display a VCS module:

- 1. Create a <vcs> element in the **startup-configuration.xml** file, or use an existing <vcs> element.
- 2. Create a <visible> element inside the <vcs> element, or use an existing <visible> element.
- 3. For each VSC module that you want to show, insert a <module> element inside the <visible> element.

Each <module> element has an attribute for:

- The class name of the VCS in the className attribute
- The title that you want to appear on the VCS's tab in the title attribute

Table 37–1 lists the class names of the VCS modules. These are the valid values for the className attribute.

vcs	Class Name
Session Manager	oracle.ocsg.pte.impl.vcs.sessionmanager.SessionManagerModule
Short Messaging	oracle.ocsg.pte.impl.vcs.px21_sms.SmsModule
Multimedia Messaging	oracle.ocsg.pte.impl.vcs.px21_mms.MmsModule
Terminal Location	oracle.ocsg.pte.impl.vcs.px21_tl.TerminalLocationModule
Terminal Status	oracle.ocsg.pte.impl.vcs.px21_ts.TerminalStatusModule
Payment	oracle.ocsg.pte.impl.vcs.px30_payment.ParlayX30PaymentModule
Third Party Call	oracle.ocsg.pte.impl.vcs.px21_tpc.ThirdPartyCallModule
Binary Sms	oracle.ocsg.pte.impl.vcs.binarysms.BinarySmsModule
Example	oracle.ocsg.pte.example.vcs.ExampleModule

4. Save the file.

Any VCS that you do not specify in the <visible> element remains hidden.

To hide a VCS module, delete its <module> element.

The following <vcs> element example shows the Session Manager, Short Messaging, and Terminal Location VCSs in the ATE. All the other VCSs remain hidden.

```
<VCS>
    <visible>
       <module
className="oracle.ocsg.pte.impl.vcs.sessionmanager.SessionManagerModule"
title="Session Manager"/>
       <module className="oracle.ocsg.pte.impl.vcs.px21_sms.SmsModule"</pre>
title="Short Messaging"/>
       <module className="oracle.ocsg.pte.impl.vcs.px21_tl.TerminalLocationModule"</pre>
title="Terminal Location"/>
    </visible>
</vcs>
```

The <visible> elements are applied each time the ATE starts up.

Changing a VCS Title

You can display a different title on a VCS tab by changing the title attribute of the <module> element inside the <visible> element.

To change the title of a VCS tab, specify a different value for the title attribute of the VCS module that you want to change inside the <module> element. See step 3 in "Showing/Hiding a VCS Module".

The following example sets the title on the **Short Messaging** VCS tab to **SMS**.

```
<vcs>
    <visible>
      <module className="oracle.ocsg.pte.impl.vcs.px21_sms.VCSSmsModule"</pre>
title="SMS"/>
    </visible>
  </vcs>
```

Reconfiguring the Default VCS MBean Attributes

The MBean attributes that are settable in the VCS are configured with default values when the ATE starts. You can change these default values in your custom configuration.

To reconfigure a default VCS MBean attribute:

- 1. Create a <vcs> element in the **startup-configuration.xml** file, or use an existing <vcs> element.
- 2. Create an <mbeans> element inside the <vcs> element, or use an existing <mbeans> element.
- **3.** For every attribute for which you want to change the default value, insert an <mbean> element inside the <mbeans> element.

Each <mbean> element has

- A name attribute for the MBean name of the VCS.
- An attribute attribute for the VCS attribute.
- A value attribute for the default value.

Table 37–2 lists the valid MBean name values for the name attribute for VCS modules that support configurable attributes.

Table 37-2 VCS MBean Names

vcs	MBean Name
Terminal Location	px21_tl
Terminal Status	px21_ts
Payment	px30_payment
Third Party Call	px21_tpc

Valid values for the attribute attribute are the names displayed in the Configuration tab of the VCS in the ATE. Some VCSs do not have any configurable attributes.

4. Save the file.

Attributes that you do not specify in an <mbean> element retain their default values.

The application developer can modify these defaults from the Configuration tab of a visible VCS for the duration of an ATE session, but those changes do not persist. The next time the ATE starts up, the default values configured in the **startup-configuration.xml** file are used.

The following example sets the default value for the Terminal Location VCS's MaximumCount attribute to 7 and the default value for the Terminal Status VCS's NotificationFrequency attribute to 8.

```
<mbeans>
 <mbean name="px21_tl" attribute="MaximumCount" value="7"/>
 <mbean name="px21_ts" attribute="NotificationFrequency" value="8"/>
</mbeans>
```

Customizing the Account Manager

The ATE is configured with a default account that applications use to access the VCS. The credentials for this account are:

- User Name=domain_user
- Password=domain_user

The user name and password are included in the SOAP header or HTTP basic authentication credentials in the application's requests.

Showing and Hiding the Account Manager

By default, the default account is visible in the Account Manager when the ATE starts.

You can configure whether the Account Manager panel should be displayed or hidden.

To show or hide the **Account Manager** panel:

- 1. Create an <account> element in the startup-configuration.xml file, or use an existing <account> element.
- **2.** Do one of the following:

- To hide the **Account Manager** panel, set the <account> element's visible
- To show the **Account Manager** panel, set the <account> element's visible attribute to true.
- Save the file.

Creating Accounts

You can create additional accounts for applications to use as credentials for requests sent to a VCS.

To create an account:

- 1. Create an <account> element in the **startup-configuration.xml** file, or use an existing <account> element.
- **2.** Create a <users> element inside the <account> element, or use an existing <users>
- 3. For every account that you want to create, insert a <user> element inside the <users> element.

Each <user> element has a name attribute for the user name and a password attribute for the password.

4. Save the **startup-configuration.xml** file.

The following example creates two application accounts and hides the **Account** Manager panel. Applications can send requests using either set of credentials.

```
<account visible="false">
  <users>
    <user name="dev1" password="plm9zag"/>
    <user name="dev2" password="cde4rfv"/>
 </users>
</account>
```

Accounts are read when the ATE is installed. See "When Configuration Elements Are Read" for more information.

Customizing the SLA Manager

You can customize the following characteristics of the VCS's service level agreement (SLA) Manager:

- Showing and Hiding the SLA Manager
- **Creating Policy Enforcements**

By default, the **SLA Manager** panel is visible when the ATE starts.

Showing and Hiding the SLA Manager

To show or hide the **SLA Manager** panel:

- 1. Create an <sla> element in the **startup-configuration.xml** file, or use an existing <sla> element.
- **2.** Do one of the following:.
 - To hide the **SLA Manager** panel, set the <sla> element's visible attribute to false

- To show the **SLA Manager** panel, set the <sla> element's <visible> attribute
- **3.** Save the file.

Creating Policy Enforcements

You can provide policy enforcements in the ATE to test how applications handle policy restrictions. These restrictions would be enforced by actual service-level agreements when the application is deployed.

To create policy enforcements:

- 1. Create an <sla> element in the **startup-configuration.xml** file, or use an existing <sla> element.
- 2. Create an <enforcements> element inside the <sla> element, or use an existing <enforcements> element.
- **3.** Do one of the following:
 - To enable all enforcements, set the enabled attribute of the <enforcements> element to true.
 - To disable all enforcements, set the enabled attribute of the <enforcements> element to false.

You cannot enable or disable individual enforcements.

4. For every value enforcement, create a <value> element inside the <enforcements> element.

Set the path, operation, and value attributes of the <value> element to define the value enforcement. See "Managing Value Enforcements" for more information about these attributes.

5. For every rate enforcement, create a <request> element inside the <enforcements> element.

Set the name, count, timeAmount, and timeUnit attributes of the <request> element to define the rate enforcement. See "Managing Rate Enforcements" for more information about these attributes.

6. Save the file.

The following example creates two value enforcements and one rate enforcement, enables those enforcements, and shows the **SLA Manager** in the ATE.

```
<sla visible="true">
    <enforcements enabled="true">
      <value path="sendMessage.subject" operation="contains" value="world"/>
      <value path="sendMessage.charging.currency" operation="does_not_contain"</pre>
value="euro"/>
      <request name="sendSms" count="5" timeAmount="10" timeUnit="seconds"/>
    </enforcements>
  </sla>
```

When the **SLA Manager** panel is visible, the application developer can create additional value and rate enforcements that apply for the duration of the session. The developer can also modify or delete the enforcements that are currently configured. Any modifications the application developer makes are applicable only for the duration of the SDK session. Only those enforcements configured in the **startup-configuration.xm**l file are persistent when the ATE is restarted.

Enforcements are read when the ATE is installed. See "When Configuration Elements Are Read" for more information.

Showing And Hiding Payment Accounts Panels

You can configure whether the Payment Account and Payment Account Detail panels should be displayed or hidden.

These panels are treated as a unit, which means that you must hide both panels or show both panels.

To show or hide the **Payment Account** and **Payment Account Detail** panels:

- 1. Create a <payment> element in the **startup-configuration.xml** file, or use an existing <payment> element.
- **2.** Do one of the following:.
 - To hide the **Payment Account** and **Payment Account Detail** panels, set the <payment> element's visible attribute to false.
 - To show the **Payment Account** and **Payment Account Detail** panels, set the <payment> element's visible attribute to true.

Showing And Hiding Payment Accounts Pane

ATE Endpoints

This appendix lists the endpoints needed to point your application toward the Application Test Environment (ATE) in Oracle Communications Services Gatekeeper.

In this chapter, the values for *host* and *port* are the host name and port of the system on which Services Gatekeeper is installed. To specify the ATE endpoints in your application, replace ate_host with the host name or IP address of the system running the ATE.

ATE Endpoints for SOAP-Based Interfaces

This section lists the ATE endpoints that correspond to Services Gatekeeper endpoints for SOAP-based application interfaces.

Session Manager

Table A-1 Endpoints for SOAP SessionManager Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/session_manager/SessionManager
ATE	http://ate_host:13444/jaxws/SessionManager

Parlay X 2.1 Short Messaging Service/SMPP

Table A-2 Endpoints for SOAP SendSms Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/sms/SendSms
ATE	http://ate_host:13444/jaxws/vcs/px21_sms/SendSms

Table A-3 Endpoints for SOAP ReceiveSms Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/sms/ReceiveSms
ATE	http://ate_host:13444/jaxws/vcs/px21_sms/ReceiveSms

Table A-4 Endpoints for SOAP SmsNotificationManager Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/sms/SmsNotificationManager
ATE	http://ate_host:13444/jaxws/vcs/px21_ sms/SmsNotificationManager

Parlay X 2.1 MultiMedia Messaging Service

Table A-5 Endpoints for SOAP SendMessage Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/multimedia_ messaging/SendMessage
ATE	http://ate_host:13444/jaxws/vcs/px21_mms/SendMessage

Table A-6 Endpoints for SOAP MessageNotificationManager Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/multimedia_ messaging/MessageNotificationManager
ATE	http://ate_host:13444/jaxws/vcs/px21_ mms/MessageNotificationManager

Table A-7 Endpoints for SOAP ReceiveMessage Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/multimedia_ messaging/ReceiveMessage
ATE	http://ate_host:13444/jaxws/vcs/px21_mms/ReceiveMessage

Parlay X 2.1 Terminal Location

Table A-8 Endpoints for SOAP TerminalLocation Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/terminal_ location/TerminalLocation
ATE	http://ate_host:13444/jaxws/vcs/parlayx21/terminal_ location/TerminalLocation

Endpoints for SOAP TerminalLocationNotificationManager Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/terminal_ location/TerminalLocationNotificationManager
ATE	http://ate_host:13444/jaxws/vcs/parlayx21/terminal_ location/TerminalLocationNotificationManager

Parlay X 2.1 Terminal Status

Table A-10 Endpoints for SOAP TerminalStatus Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/terminal_ location/TerminalStatus
ATE	http://ate_host:13444/jaxws/vcs/parlayx21/terminal_status/TerminalStatus

Table A-11 Endpoints for SOAP TerminalStatusNotificationManager Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/terminal_ location/TerminalStatus
ATE	http://ate_host:13444/jaxws/vcs/parlayx21/terminal_ status/TerminalStatusNotificationManager

Parlay X 3.0 Payment

Table A-12 Endpoints for SOAP Payment AmountCharging Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx30/payment/AmountCharging
ATE	http://ate_ host:13444/jaxws/vcs/parlayx30/payment/AmountCharging

Table A-13 Endpoints for SOAP Payment ReserveAmountCharging Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx30/payment/ReserveAmountCharging
ATE	http://ate_ host:13444/jaxws/vcs/parlayx30/payment/ReserveAmountCha rging

Table A-14 Endpoints for SOAP Payment VolumeCharging Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx30/payment/VolumeCharging
ATE	http://ate_ host:13444/jaxws/vcs/parlayx30/payment/VolumeCharging

Table A-15 Endpoints for SOAP Payment ReserveVolumeCharging Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx30/payment/ReserveVolumeCharging
ATE	http://ate_ host:13444/jaxws/vcs/parlayx30/payment/ReserveVolumeCha rging

Parlay X 2.1 Third Party Call

Table A-16 Endpoints for SOAP Third Party Call Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/parlayx21/third_party_call/ThirdPartyCall
ATE	http://ate_host:13444/jaxws/vcs/parlayx21/third_party_call/ThirdPartyCall

EWS Binary SMS

Table A-17 Endpoints for EWS Binary SMS Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/ews/binary_sms/BinarySms
ATE	http://ate_host:13444/jaxws/vcs/ews/binary_ sms/BinarySMS

Table A-18 Endpoints for EWS Binary SMS Notification Manager Interface

Destination	Endpoint
Services Gatekeeper	http://host:port/ews/binary_ sms/BinarySmsNotificationManager
ATE	http://ate_host:13444/jaxws/vcs/ews/binary_ sms/BinarySMSNotificationManager

ATE Endpoints for RESTful Interfaces

This section lists the ATE endpoints that correspond to Services Gatekeeper endpoints for RESTful application interfaces.

Session Manager

Table A–19 Endpoints for RESTful Get Session Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/sessions
ATE	http://ate_host:13444/rest/session_manager/sessions

Table A-20 Endpoints for RESTful Get Session Remaining Lifetime, Destroy a Session Operations

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/session/\${sessionId}
ATE	http://ate_host:13444/rest/session_ manager/session/\${sessionId}

Short Messaging

Table A-21 Endpoints for RESTful Send SMS Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/sms/messages
ATE	http://ate_host:13444/rest/sms/messages

Table A-22 Endpoints for RESTful Send SMS Logo Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/sms/logos
ATE	http://ate_host:13444/rest/sms/logos

Table A-23 Endpoints for RESTful Send SMS Ringtone Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/sms/ringtones
ATE	http://ate_host:13444/rest/sms/ringtones

Table A-24 Endpoints for RESTful Get Received SMS Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/sms/receive-messages/\${registrationIdentfier}
ATE	http://ate_ host:13444/rest/sms/receive-messages/\${registrationIden tfier}

Table A-25 Endpoints for RESTful Get SMS Delivery Status Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/sms/delivery-status/\${requestIden tfier}
ATE	<pre>http://ate_ host:13444/rest/sms/delivery-status/\${requestIdentifier }</pre>

Table A-26 Endpoints for RESTful Start Sms Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/sms/notification/
ATE	http://ate_host:13444/rest/sms/notification

Table A-27 Endpoints for RESTful Stop Sms Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/sms/notification/\${correlator}
ATE	http://ate_ host:13444/rest/sms/notification/\${correlator}

Multimedia Messaging

Table A-28 Endpoints for RESTful Send Message Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/multimedia_messaging/messages/
ATE	http://ate_host:13444/rest/multimedia_ messaging/messages

Table A-29 Endpoints for RESTful Get Received Messages Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/multimedia_ messaging/receive-messages/
ATE	http://ate_host:13444/rest/multimedia_ messaging/receive-messages

Table A-30 Endpoints for RESTful Get Message Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/multimedia_ messaging/message/\${messageRefIdentifier}
ATE	http://ate_host:13444/rest/multimedia_ messenging/message/\${messageRefIdentifier}

Table A-31 Endpoints for RESTful Get Message Delivery Status Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/multimedia_ messaging/delivery-status/\${requestIdentifier}
ATE	http://ate_host:13444/rest/multimedia_ messenging/delivery-status/\${requestIdentifier}

Table A-32 Endpoints for RESTful Start MMS Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/multimedia_messaging/notification
ATE	http://ate_host:13444/rest/multimedia_ messenging/notification

Table A-33 Endpoints for RESTful Stop MMS Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/multimedia_ messaging/notification/\${correlator}
ATE	http://ate_host:13444/rest/multimedia_ messenging/notification/\${correlator}

Terminal Location

Table A-34 Endpoints for RESTful Get Location Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/terminal_ location/location?query=\${query}
ATE	http://ate_host:13444/rest/terminal_location/location

Table A-35 Endpoints for RESTful Get Terminal Distance Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/terminal_ location/distance?query=\${query}
ATE	http://ate_host:13444/rest/terminal_location/distance

Table A-36 Endpoints for RESTful Start Periodic Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/terminal_ location/periodic-notification
ATE	http://ate_host:13444/rest/terminal_ location/periodic-notification

Table A-37 Endpoints for RESTful Start Geographic Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/terminal_ location/geographic-notification
ATE	http://ate_host:13444/rest/terminal_ location/geographic-notification

Table A–38 Endpoints for RESTful End Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/terminal_ location/notification/\${correlator}
ATE	http://ate_host:13444/rest/terminal_ location/notification/\${correlator}

Terminal Status

Table A-39 Endpoints for RESTful Get Status Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/terminal_ status/status?query=\${query}
ATE	http://ate_host:13444/rest/terminal_status/status

Endpoints for RESTful Start Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/terminal_ status/status-notification
ATE	http://ate_host:13444/rest/terminal_ status/status-notification

Table A-41 Endpoints for RESTful End Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/terminal_ status/notification/\${correlator}
ATE	http://ate_host:13444/rest/terminal_ status/notification/\${correlator}

Payment

Table A-42 Endpoints for RESTful Charge Amount Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/payment/charge-amount
ATE	http://ate_host:13444/rest/payment/charge-amount

Table A-43 Endpoints for RESTful Refund Amount Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/payment/refund-amount
ATE	http://ate_host:13444/rest/payment/refund-amount

Table A-44 Endpoints for RESTful Charge Split Amount Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/payment/charge-split-amount
ATE	http://ate_host:13444/rest/payment/charge-split-amount

Table A-45 Endpoints for RESTful Reserve Amount Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/payment/reserve-amount
ATE	http://ate_host:13444/rest/payment/reserve-amount

Table A-46 Endpoints for RESTful Reserve Additional Amount Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/payment/reserve-additional-amount
ATE	http://ate_ host:13444/rest/payment/reserve-additional-amount

Table A-47 Endpoints for RESTful Charge ReservationOperation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/payment/charge-reservation
ATE	http://ate_host:13444/rest/payment/charge-reservation

Table A-48 Endpoints for RESTful Release Reservation Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/payment/release-reservation
ATE	http://ate_host:13444/rest/payment/release-reservation

Table A-49 Endpoints for RESTful Charge Amount Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/payment/charge-amount
ATE	http://ate_host:13444/rest/payment/charge-amount

Table A-50 Endpoints for RESTful Volume Charging Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/payment/volume-charging
ATE	http://ate_host:13444/rest/payment/volume-charging

Table A-51 Endpoints for RESTful Reserve Volume Charging Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/payment/reserve-volume-charging
ATE	http://ate_ host:13444/rest/payment/reserve-volume-charging

Third Party Call

Table A-52 Endpoints for RESTful Make Call Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/third_party_call/calls
ATE	http://ate_host:13444/rest/third_party_call/calls

Table A-53 Endpoints for RESTful Get Call Information Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/third_party_call/call/\${callIdentifier}
ATE	http://ate_host:13444/rest/third_party_call/call/\${callIdentifier}

Table A-54 Endpoints for RESTful Cancel Call Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/third_party_call/cancel-call/\${callIdentifier}
ATE	http://ate_host:13444/rest/third_party_call/cancel-call/\${callIdentifier}

Table A-55 Endpoints for RESTful End Call Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/third_party_call/end-call/\${callIdentifier}
ATE	http://ate_host:13444/rest/third_party_call/end-call/\${callIdentifier}

Binary SMS

Table A-56 Endpoints for RESTful Send Binary SMS Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/binary_sms/messages
ATE	http://ate_host:13444/rest/binary_sms/messages

Table A-57 Endpoints for RESTful Start Binary SMS Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/binary_sms/notification
ATE	http://ate_host:13444/rest/binary_sms/notification

Table A–58 Endpoints for RESTful Stop Binary SMS Notification Operation

Destination	Endpoint
Services Gatekeeper	http://host:port/rest/binary_ sms/notification/\${correlator}
ATE	http://ate_host:13444/rest/binary_ sms/notification/\${correlator}

ATE Endpoints for Example Communication Service

The ATE provides the following endpoints to test the communications service example that is provided for platform development. This example is described in Services Gatekeeper Extension Developer's Guide, another document in this set.

Table A-59 Endpoint for Platform Development Studio Example Send Data Interface

Destination	Endpoint
ATE	http://ate_host:13444/jaxws/SendData

Table A-60 Endpoint for Platform Development Studio Example Notification Manager Interface

Destination	Endpoint
ATE	http://ate_host:13444/jaxws/NotificationManager

Virtual Communication Services Exception Codes

This appendix lists the exceptions codes generated by the Application Test Environment (ATE) Virtual Communication Services (VCSs) in Oracle Communications Services Gatekeeper Software Development Kit (SDK).

Exceptions with an SVC prefix indicate an error against the service. Exceptions with a POL prefix indicate a violation of a policy enforcement. See "Managing Service-Level Agreements" for information about setting policy enforcements in the VCS.

Short Messaging Exception Codes

The following exceptions are generated by the Short Messaging VCS.

SendSms.sendSms

SendSms.sendSms

Exception ID: SVC0001

Exception Type: service error

Cause: Any problem sending the SMS.

SendSms.getSmsDeliveryStatus

SendSms.getSmsDeliveryStatus

Exception ID: SVC0002

Exception Type: invalid input error

Cause: No delivery status available for the given request identifier.

ReceiveSms.getReceivedSms

ReceiveSms.getReceivedSms

Exception ID: SVC0001

Exception Type: service error

Cause: Any problem retrieving an SMS.

SmsNotificationManager.startSmsNotification

SmsNotificationManager.startSmsNotification

Exception ID: SVC0005

Exception Type: duplicate correlator

Cause: Duplicate correlator used when starting a notification.

Multimedia Messaging Exception Codes

The following the exceptions are generated by the Multimedia Messaging VCS.

SendMessage.sendMessage

SendMessage.sendMessage

Exception ID: SVC0001

Exception Type: service error

Cause: Any problem sending the MMS.

SendMessage.getMessageDeliveryStatus

SendMessage.getMessageDeliveryStatus

Exception ID: SVC0002

Exception Type: invalid input error

Cause: The requestIdentifier is invalid.

ReceiveMessage.getMessage

ReceiveMessage.getMessage

Exception ID: SVC0002

Exception Type: invalid input error

Cause: The messageRefIdentifier is invalid.

ReceiveMessage.getReceivedMessage

ReceiveMessage.getReceivedMessages

Exception ID: SVC0002

Exception Type: invalid input error

Cause: The registrationIdentifier is invalid.

MessageNotificationManager.startMessageNotification

MessageNotificationManager.startMessageNotification

Exception ID: SVC0005

Exception Type: duplicate correlator

Cause: The same correlator is registered multiple times.

MessageNotitifcationManager.stopMessageNotification

MessageNotificationManager.stopMessageNotification

Exception ID: SVC0002

Exception Type: invalid input error Cause: The correlator is invalid.

Terminal Location Exception Codes

The following exceptions are generated by the Terminal Location VCS.

TerminalLocation.getLocation

TerminalLocation.getLocation

Exception ID: SVC0002

Exception Type: invalid input error

Cause: Address is null.

TerminalLocation.getLocation

Exception ID: SVC0004

Exception Type: invalid address error

Cause: No terminal with specified address.

TerminalLocation.getLocationForGroup

Exception ID: POL0003

Exception Type: too many addresses error

Cause: Too many addresses specified.

TerminalLocation.getLocation

Exception ID: POL0230

Exception Type: requested accuracy not supported

Cause: The requested Accuracy or acceptable Accuracy is too low.

TerminalLocation.getTerminalDistance

TerminalLocation.getTerminalDistance

Exception ID: SVC0002

Exception Type: invalid input error

Cause: Address is null, or latitude is not in [-90, 90] range, or longitude is not in [-180,

180] range.

TerminalLocation.getTerminalDistance

Exception ID: SVC0004

Exception Type: invalid address error

Cause: No terminal with specified address.

TerminalLocationNotificationManager.startGeographicalNotification

TerminalLocationNotificationManager.startGeographicalNotification

Exception ID: SVC0002

Exception Type: invalid input error

Cause: No callback endpoint or correlator provided, or latitude is not in [-90, 90]

range, or longitude is not in [-180, 180] range.

TerminalLocationNotificationManager.startGeographicalNotification

Exception ID: SVC0004

Exception Type: invalid address error Cause: No valid addresses provided.

TerminalLocationNotificationManager.startGeographicalNotification

Exception ID: SVC0005

Exception Type: duplicate correlator

Cause: The same correlator is registered multiple times.

TerminalLocationNotificationManager.startGeographicalNotification

Exception ID: POL0003

Exception Type: too many addresses error

Cause: Too many addresses provided.

TerminalLocationNotificationManager.startGeographicalNotification

Exception ID: POL0004

Exception Type: unlimited notifications not supported

Cause: Count equals zero.

TerminalLocationNotificationManager.startGeographicalNotification

Exception ID: POL0005

Exception Type: too many notifications requested

Cause: Count is too high.

TerminalLocationNotificationManager.startGeographicalNotification

Exception ID: POL0009

Exception Type: invalid frequency error

Cause: Invalid frequency requested.

TerminalLocationNotificationManager.startGeographicalNotification

Exception ID: POL0230

Exception Type: requested accuracy not supported

Cause: The requested Accuracy or acceptable Accuracy is too low.

TerminalLocationNotificationManager.startGeographicalNotification

Exception ID: POL0231

Exception Type: geographic notification error

Cause: Geographic notification is not available.

TerminalLocationNotificationManager.startPeriodicNotification

TerminalLocationNotificationManager.startPeriodicNotification

Exception ID: SVC0002

Exception Type: invalid input error

Cause: No callback endpoint or correlator provided.

TerminalLocationNotificationManager.startPeriodicNotification

Exception ID: SVC0004

Exception Type: invalid address error

Cause: No terminal with specified address.

TerminalLocationNotificationManager.startPeriodicNotification

Exception ID: SVC0005

Exception Type: duplicate correlator

Cause: The same correlator is registered multiple times.

TerminalLocationNotificationManager.startPeriodicNotification

Exception ID: POL0003

Exception Type: too many addresses error

Cause: Too many addresses provided.

TerminalLocationNotificationManager.startPeriodicNotification

Exception ID: POL0009

Exception Type: invalid frequency error

Cause: Invalid frequency requested.

TerminalLocationNotificationManager.startPeriodicNotification

Exception ID: POL0232

Exception Type: periodic notification error

Cause: Periodic notification is not available.

TerminalLocationNotificationManager.endNotification

TerminalLocationNotificationManager.endNotification

Exception ID: SVC0002

Exception Type: invalid input error

Cause: Invalid correlator.

Terminal Status Exception Codes

The following exceptions are generated by the Terminal Status VCS.

TerminalStatus.getStatus

TerminalStatus.getStatus

Exception ID: SVC0002

Exception Type: invalid input error

Cause: Address is null.

TerminalStatus.getStatus

Exception ID: SVC0004

Exception Type: invalid address error Cause: No valid addresses provided.

TerminalStatus.getStatusForGroup

TerminalStatus.getStatusForgroup

Exception ID: SVC0002

Exception Type: invalid input error

Cause: Address is null.

TerminalStatus.getStatusForGroup

Exception ID: SVC0004

Exception Type: invalid address error Cause: No valid addresses provided.

TerminaStatus.getStatusForGroup

Exception ID: POL0003

Exception Type: too many addresses error Cause: Too many addresses provided.

TerminalStatusNotificationManager.startNotification

TerminalStatusNotificationManager.startNotification

Exception ID: SVC0002

Exception Type: invalid input error

Cause: No callback endpoint or correlator provided, or latitude is not in [-90, 90]

range, or longitude is not in [-180, 180] range.

TerminalStatusNotificationManager.startNotification

Exception ID: SVC0004

Exception Type: invalid address error Cause: No valid addresses provided.

TerminalStatusNotificationManager.startNotification

Exception ID: SVC0005

Exception Type: duplicate correlator

Cause: The same correlator is registered multiple times.

TerminalStatusNotificationManager.startNotification

Exception ID: POL0003

Exception Type: too many addresses error

Cause: Too many addresses provided.

TerminalStatusNotificationManager.startNotification

Exception ID: POL0004

Exception Type: unlimited notifications not supported

Cause: Count equals zero.

TerminalStatusNotificationManager.startNotification

Exception ID: POL0005

Exception Type: too many notifications requested

Cause: Count is too high.

TerminalStatusNotificationManager.startNotification

Exception ID: POL0009

Exception Type: invalid frequency error Cause: Invalid frequency requested.

TerminalStatusNotificationManager.startNotification

Exception ID: POL0200

Exception Type: busy criterion not supported

Cause: isBusyAvailable is set to false and criteria include busy.

TerminalStatusNotificationManager.endNotification

TerminalStatusNotificationManager.endNotification

Exception ID: SVC0002

Exception Type: invalid input error Cause: No valid correlator provided.

Third Party Call Exception Codes

The following exceptions are generated by the Third Party Call VCS.

ThirdPartyCallImpl.cancelCallRequest

ThirdPartyCallImpl.cancelCallRequest

Exception ID: SVC0002

Exception Type: invalid input value for call identifier

Cause: Call identifier is null.

ThirdPartyCallImpl.cancelCallRequest

Exception ID: SVC0260

Exception Type: call already connected

Cause: The specified call has already connected and can not be canceled.

ThirdPartyCallImpl.endCall

ThirdPartyCallImpl.endCall

Exception ID: SVC0002

Exception Type: invalid input value for call identifier

Cause: Call identifier is null.

ThirdPartyCallImpl.endCall

Exception ID: SVC261

Exception Type: call already terminated

Cause: The specified call has already terminated.

ThirdPartyCallImpl.getCallInformation

ThirdPartyCallImpl.getCallInformaton

Exception ID: SVC0001

Exception Type: service error

Cause: Called party or callee party status is invalid.

ThirdPartyCallImpl.getCallInformaton

Exception ID: SVC0002

Exception Type: invalid input value for call identifier

Cause: Call identifier is null.

ThirdPartyCallImpl.makeCall

ThirdPartyCallImpl.makeCall

Exception ID: SVC0002

Exception Type: invalid input value for call identifier

Cause: Call identifier is null.

ThirdPartyCallImpl.sendMessage

ThirdPartyCallImpl.sendMessage

Exception ID: SVC0001

Exception Type: service error

Cause: Called party or callee party status is invalid.

ReceiveMessage.makeCall

ReceiveMessage.makeCall

Exception ID: SVC0004

Exception Type: invalid input value

Cause: Called party or callee party address is invalid.

Payment Exception Codes

The following exceptions are generated by the Payment VCS.

AmountCharging.ChargeAmount

AmountCharging.ChargeAmount

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

AmountCharging.ChargeAmount

Exception ID: SVC0007

Exception Type: invalid charging information Cause: The charging information is invalid.

AmountCharging.ChargeAmount

Exception ID: SVC0270

Exception Type: charge failed Cause: The charge failed.

AmountCharging.RefundAmount

AmountCharging.RefundAmount

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

AmountCharging.RefundAmount

Exception ID: SVC0007

Exception Type: invalid charging information Cause: The charging information is invalid.

AmountCharging.RefundAmount

Exception ID: SVC0270

Exception Type: charge failed

Cause: The charge failed.

AmountCharging.ChargeSplitAmount

AmountCharging.ChargeSplitAmount

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

AmountCharging.ChargeSplitAmount

Exception ID: SVC0007

Exception Type: invalid charging information Cause: The charging information is invalid.

AmountCharging.ChargeSplitAmount

Exception ID: SVC0270

Exception Type: charge failed

Cause: The charge failed.

AmountCharging.ChargeSplitAmount

Exception ID: SVC0271

Exception Type: invalid sum of percent allocations

Cause: The sum of the percentage allocations does not equal 100.

AmountCharging.ChargeSplitAmount

Exception ID: POL0250

Exception Type: too many end-user identifiers

Cause: The number of end-user identifiers exceeds defined policy.

AmountCharging.ChargeSplitAmount

Exception ID: POL0251

Exception Type: split charging not supported

Cause: Split charging is not supported by defined policy.

VolumeCharging.ChargeVolume

VolumeCharging.ChargeVolume

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

VolumeCharging.ChargeVolume

Exception ID: SVC0270

Exception Type: charge failed

Cause: The charge failed.

VolumeCharging.RefundVolume

VolumeCharging.RefundVolume

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

VolumeCharging.RefundVolume

Exception ID: SVC0270

Exception Type: charge failed

Cause: The refund of the volume charge failed.

ReserveAmountCharging.ReserveAmount

ReserveAmountCharging.ReserveAmount

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

ReserveAmountCharging.ReserveAmount

Exception ID: SVC0007

Exception Type: invalid charging information Cause: The charging information is invalid.

ReserveAmountCharging.ReserveAmount

Exception ID: SVC0270

Exception Type: charge failed Cause: The charge failed.

ReserveAmountCharging.ReserveAdditionalAmount

ReserveAmountCharging.ReserveAdditionalAmount

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

ReserveAmountCharging.ReserveAdditionalAmount

Exception ID: SVC0007

Exception Type: invalid charging information Cause: The charging information is invalid.

ReserveAmountCharging.ReserveAdditionalAmount

Exception ID: SVC0270

Exception Type: charge failed

Cause: The charge failed.

ReserveAmountCharging.ChargeReservation

ReserveAmountCharging.ChargeReservation

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

ReserveAmountCharging.ChargeReservation

Exception ID: SVC0007

Exception Type: invalid charging information Cause: The charging information is invalid.

ReserveAmountCharging.ChargeReservation

Exception ID: SVC0270

Exception Type: charge failed

Cause: The charge failed.

ReserveAmountChargingReleaseReservation

ReserveAmountCharging.ReleaseReservation

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

VolumeCharging.ChargeSplitVolume

VolumeCharging.ChargeSplitVolume

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

VolumeCharging.ChargeSplitVolume

Exception ID: SVC0270

Exception Type: charge failed

Cause: The charge failed.

VolumeCharging.ChargeSplitVolume

Exception ID: SVC0271

Exception Type: invalid sum of percent allocations

Cause: The sum of the percentage allocations does not equal 100.

VolumeCharging.ChargeSplitVolume

Exception ID: POL0250

Exception Type: too many end-user identifiers

Cause: The number of end-user identifiers exceeds defined policy.

VolumeCharging.ChargeSplitVolume

Exception ID: POL0251

Exception Type: split charging not supported

Cause: Split charging is not supported by defined policy.

ReserveVolumeCharging.ReserveVolume

ReserveVolumeCharging.ReserveVolume

Exception ID: SVC0001

Exception Type: service error

Cause: Any problem reserving the charge volume.

ReserveVolumeCharging.ReserveVolume

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

ReserveVolumeCharging.ReserveVolume

Exception ID: POL0001

Exception Type: policy error

Cause: Policy error

ReserveVolumeCharging.ReserveAdditionalVolume

ReserveVolumeCharging.ReserveAdditionalVolume

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

ReserveVolumeCharging.ChargeReservation

ReserveVolumeCharging.ChargeReservation

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

ReserveVolumeCharging.ChargeReservation

Exception ID: SVC0270

Exception Type: charge failed

Cause: The charge failed.

ReserveVolumeCharging.ReleaseReservation

ReserveVolumeCharging.ReleaseReservation

Exception ID: SVC0002

Exception Type: invalid input value

Cause: The user ID or some other parameter value is invalid.

Binary SMS Exception Codes

The following exceptions are generated by the Short Messaging VCS.

SendBinarySms.sendMessage

SendBinarySms.sendMessage

Exception ID:

Exception Type:

Cause: Any problem sending the binary SMS.

BinarySmsNotificationManager.startMessageNotification

BinarySmsNotificationManager.startMessageNotification

Exception ID:

Exception Type: duplicate correlator

Cause: Duplicate correlator used when starting a notification.

${\bf Binary SmsNotification Manager. stop Message Notification}$

Exception ID:

Exception Type: invalid correlator

Cause: The correlator is invalid.