

SUBSPACE RESONATOR RADIO

Host Quick Guide – Voicemeeter Wiring + Go Live Flow

A. Wire Voicemeeter Before You Play

One-time setup. Quick check every time before you open the console.

1

Rekordbox output device

Preferences > Audio > set output device to "Voicemeeter Input" (same name on Standard, Banana, and Potato).



2

Voicemeeter mixer

That strip's fader is up (not muted) and routed to bus B1.



3

Browser AUDIO INPUT dropdown

On the host console, pick "Voicemeeter Output (VB-Audio Voicemeeter VAIO)", this is what listeners will hear.

B. Go-Live Flow

Follow top to bottom on the host console at /radio.html#admin.

1

Step 1

Open /radio.html#admin and log in as host.



2

Step 2

Click ENABLE AUDIO ACCESS (first time only).



3

Step 3

Pick Voicemeeter Output in the AUDIO INPUT dropdown.



4

Step 4

Play a test track in Rekordbox, confirm the INPUT LEVEL meter moves.



5

Step 5

Adjust GAIN if the meter is too quiet or clipping red.

6

Step 6

Type in the BROADCAST TITLE.



7

Step 7

Leave LISTENER BUFFER on default unless you've had cuts before.



8

Step 8

Click GO LIVE and wait for CONNECTING...



9

Step 9

Confirm ON AIR badge + OUTPUT LEVEL meter + listener count.



10

Step 10

When finished, click END BROADCAST.

SUBSPACE RESONATOR RADIO

Preflight Checklist

C. Tick Every Box Before You Announce

- ☐ Rekordbox output device = Voicemeeter Input
- ☐ Voicemeeter fader for that strip is up, routed to B1
- ☐ Browser AUDIO INPUT dropdown = Voicemeeter Output
- ☐ Test track playing, INPUT LEVEL meter moves in host console
- ☐ Broadcast title typed in
- ☐ DJ device and restreamer PC on power, sleep/lock disabled
- ☐ Internet stable, no VPN, no other big uploads running
- ☐ Clicked GO LIVE, ON AIR badge confirmed before announcing

If it cuts out mid-broadcast:

On plain WebRTC (restreamer off), a listener's phone screen-lock or sleep stops their audio. That is a known platform limit, not a bug. Run the deep-buffer restreamer (section E) and listeners ride through screen-lock and weak signal. Either way keep the DJ device and the restreamer PC awake and on power for the whole set.

SUBSPACE RESONATOR RADIO

Host Quick Guide – Spotify Desktop App Setup

D. Stream Spotify Desktop App to Voicemeeter

Own tracks, non-commercial community radio use. Windows 11 only (per-app output routing). One-time setup, then reuse.

1

Windows Volume Mixer, per-app output

Settings > System > Sound > Volume mixer > find Spotify > Output device dropdown > set to “Voicemeeter Input (VB-Audio Voicemeeter VAIO)”. Only Spotify moves to Voicemeeter, headphones and everything else stay on your normal output device.



2

Voicemeeter mixer

Strip receiving Spotify: fader up, not muted, routed to bus B1. Optional: also route to A1 to monitor locally through headphones while broadcasting.



3

Host console AUDIO INPUT dropdown

On the host console at /radio.html#admin, pick “Voicemeeter Output (VB-Audio Voicemeeter VAIO)”, same device as the Rekordbox flow. This is what listeners will hear.



4

Test before going live

Play a track in Spotify, confirm the INPUT LEVEL meter moves in the host console. Open /radio in a second browser/tab as a listener and confirm you hear it before clicking GO LIVE for real.

Windows 10 note

Per-app output device picker is Windows 11 only. On Windows 10, set the system default playback device to Voicemeeter Input instead, headphones/system sounds will also route through Voicemeeter until you switch it back.

SUBSPACE RESONATOR RADIO

Host Quick Guide – Deep-Buffer Restreamer

E. Deep-Buffer Restreamer (recommended)

Gives listeners a smooth stream that survives weak signal and a phone screen-lock. Off = plain WebRTC, site unchanged.

1

Before Go Live: start the restreamer

Double-click start-restreamer.bat. A black window opens and stays open. Leave it open the whole show.



2

Go Live as normal

Run the Voicemeeter + Go-Live flow on pages 1-2 exactly as always.



3

Wait for the deep buffer to turn on

Watch the black window until it prints "streamUrl published: ...", about 30 seconds after Go Live. That is the deep buffer turning on.



4

Now send the guest link

Guests get instant sound and then upgrade to the deep buffer on their own. Anyone already waiting upgrades too.



5

End of show

Click END BROADCAST, then close the black window. Everyone falls back to plain WebRTC, no site change.

DJ from your phone or another computer

The restreamer PC and the DJ device are separate. Go Live from any device with internet (phone browser, second laptop). The restreamer finds your show by its Cloudflare session id, not by which device you are on. Only rule: one PC must run the black window the whole show.

Keep the restreamer PC awake

Set Windows sleep to Never while plugged in. If that PC sleeps or crashes, listeners drop back to plain WebRTC on their own, they are never left in silence. If it crashes the window restarts it in 3 seconds.