

Trade Lifecycle, Exit & Runner Engine

GSPS Implementation Specification Pack • Prepared for Claude Code • August 28, 2026 • Draft implementation directives; requires securities/compliance counsel review before live personalized recommendations or execution.

Trade-plan object

Every executable GSPS plan must persist a versioned plan object before entry. A signal without complete lifecycle fields is not tradeable.

Field group	Required fields
Identity	plan_id, strategy_version, signal_id, user_id, instrument, market, timeframe, generated_at, expires_at
Coordinates	entry trigger, entry limit tolerance, invalidation, stop type, TP1, TP2, Master Profit, runner rule
Risk	approved quantity, fractional capability, planned dollar risk, allocation, total-open-risk snapshot
Evidence	regime, Rules Alignment Score, individual criteria, data timestamps, event/liquidity status
State	watchlist, qualified, armed, entered, TP1, TP2, master-achieved, runner, closed, expired, invalidated
Audit	all plan edits, user actions, price events, notifications, executions/imported fills

Novice target structure

Marker	Typical target from entry	Default action
TP1	4–6%	Realize configured partial; reassess protection
TP2	7–8%	Realize additional partial when credible target exists
Master Profit	9–10% exceptional Novice extension	Protect Master Profit as minimum runner floor after conditions met
Runner	Only where residual quantity and trend conditions support it	Trail without lowering Master Profit floor

Targets are never assigned solely by fixed percentage. They must be constrained by credible support/resistance, volatility, expected holding period, liquidity, and the strategy's validated target model. If a first credible target offers less than 4% for Novice, reject or downgrade the setup.

Master Profit and runner rules

- TP1 and TP2 should be modeled as limit-based partial exits where supported.
- Runner is allowed only if the residual quantity is operationally meaningful. Fractional shares enable percentage-based scaling; otherwise use an all-in/all-out fallback when units are too few.
- Activate Master-Profit Floor only after a configured closed bar satisfies the Master Profit condition; do not activate merely on a transient print unless a user-selected intrabar method is explicitly supported.
- Once activated, the Master-Profit Floor may ratchet upward but never downward.
- If price gaps through the floor, record actual fill versus planned floor; do not represent the floor as a guaranteed fill.
- Define and display order type semantics: alert-only, stop-market, stop-limit, close-confirmed alert. Broker support is required before any order automation.

Lifecycle transitions and expiry

WATCHLIST -> QUALIFIED -> ARMED -> ENTERED -> TP1_REACHED -> TP2_REACHED -> MASTER_REACHED -> RUNNER -> CLOSED
Any pre-entry state -> EXPIRED when trigger does not occur by expires_at

Any active state -> INVALIDATED when stop/invalidation rule is met
Cooldown affects new-entry transition only; it never blocks CLOSE / REDUCE / PROTECT.

- Signals must expire after a defined number of closed operating-timeframe bars.
- Entry must not occur after excessive price extension beyond the planned trigger tolerance.
- Any post-entry material plan modification must create a new audit version; risk may not be increased without re-evaluation and user confirmation.
- Daily/overnight gap rules must use actual available price data and show planned versus realized risk.

User education requirements

- Show why entry occurred, what invalidates it, what each profit marker means, and what must happen to continue holding.
- Distinguish planned maximum loss from possible execution loss due to gaps/slippage.
- Show the quantity/partial-exit math before entry, especially for small accounts.
- After close, generate a structured review: plan adherence, actual versus planned entry/exit, rule state, and lesson tags.