

Configure an event pull connector

- Release version: Australia
-
- Updated March 12, 2026
-
- ⌚ 3 minutes to read

Configure event pull connectors that require a script, connector definition, and connector instance to pull events from external devices. These connectors automate the data retrieval process, ensuring the seamless integration of external events into your system for efficient monitoring and management.


Before you begin

Role required: evt_mgmt_admin

Procedure

1. Navigate to Workspaces > Service Operations Workspace.
2. From the bottom of the navigation pane, select the AIOps configuration center icon . The ITOM AIOps configuration center page appears. The configuration center is a centralized workspace. Use it to configure and manage AIOps features from a single place.
3. On the ITOM AIOps configuration center page, under the Setup > Integrations section, select Manage Installed integrations.
4. In the Browse Integrations tab, select the All integrations drop-down list and select Pull. Only pull connector tiles are displayed.

Figure 1. Pull connectors



5. Select a pull connector tile.

If a pop-up menu opens, select the data to track from that connector and select Continue.

Figure 2. Pull connectors details page

The screenshot shows the 'Nagios US - West1' pull connector details page. At the top, there's a header with the Nagios logo and the title 'Nagios US - West1'. To the right of the title are buttons: 'Cancel', 'Save', 'Test and Save', and 'Activate'. Below the header, there are two tabs: 'Details' (selected) and 'Events'. The 'Details' tab contains a form with the following fields: 'Connector name *' (filled with 'Nagios US - West1'), 'Tags' (empty), 'Description' (placeholder 'Enter description'), 'Assignment group' (dropdown menu showing 'All groups'), 'Host IP *' (filled with '1.1.1.1'), and 'Credentials *' (dropdown menu showing 'public'). At the bottom of the form is a link for 'Advanced settings'.

6. In the Details tab, in the Connector name field, enter a unique name for the connector type.

7. **Optional:** In the Tags field, enter tags to help locate and identify connectors of this type on the Express List.

To add additional tags, select the plus icon () next to the Tags field. The Add tags window opens.

a. In the Key field, enter a tag key.

b. In the Value field, enter a tag value.

c. Select Add.

8. **Optional:** In the Description field, enter brief information about this connector.

9. **Optional:** From the Assignment group drop-down list, select the group or team that is responsible for managing and maintaining the connector.

10. In the Host IP field, enter the IP address that is used to select the appropriate MID Server for communicating with the event source host.

You can use the host name instead of the host IP.

11. From the Credentials drop-down list, select the valid credentials to access the event source host.

To create a new credential, select Create new credentials and continue with the process.

12. **Optional:** If you want to customize configurations to meet specific requirements, select Advanced settings and fill in the form.

Field	Description
Connected MID Server	Determine whether you want to have the system choose the optimal MID Server or choose a specific MID Server yourself. Perform only if you must make modifications to the MID Server otherwise leave it empty and let the system choose the optimal MID Server.
Event collection schedule (seconds)	Enter the frequency in seconds that indicates how often the system should check for new events from

Field	Description
	the external event source. The value can't be lower than the minimum schedule property, which by default is 120 seconds.
Protocol	Defines the communication protocol used for retrieving events from external devices.
severity_by_state_type	Determines the severity level assigned to events based on their state type.
time_zone	Specifies the time zone used for recording and displaying event timestamps.
offset_min	Sets the time offset for event retrieval to ensure accurate synchronization.
Port	Verify the default values for your connector type such as port details or time formats and modify them as necessary. Default values from your connector are filled-in. Specifies the port number used for communication with external devices.
max_fetch_interval_min	Limits the maximum interval between event fetch operations.
initial_sync_in_days	Sets the duration for the initial synchronization process when retrieving historical data.

13. **Optional:** Test the connector before activating it by selecting Test and Save.

14. To save the connector, select Save.

15. To activate the pull connector, select Activate.

The pull connector is activated and its tile is displayed in the Installed Integrations tab.

What to do next

To confirm the successful configuration of the pull connector and the flow of events into the system, select the Related events tab. If the setup is successful, proceed to Add automation to establish an alert automation. For details on Related events tab, see Review integration and configuration health and for information on alert automation, see Alert automation in Service Operations Workspace for ITOM.