

Configure Solarwinds metric pull connector

- Release version: Australia
-
- Updated March 12, 2026
-
- ⌚ 3 minutes to read

Configure a metric pull connectors that require a script, connector definition, and connector instance to pull metrics from external sources. These connectors automate the data retrieval process, ensuring the seamless integration of external metrics into your system for efficient monitoring and performance analysis.

Before you begin

Role required: evt_mgmt_admin


About this task

Note:

The new UI for configuring metric pull connector is currently available only for the SolarWinds Metric Connector. For all other metric connectors, the configuration continues to use the Platform Table UI.

Procedure

1. Navigate to Workspaces > Service Operations Workspace.
2. From the bottom of the navigation pane, select the AIOps configuration center icon .
The ITOM AIOps configuration center page appears. The configuration center is a centralized workspace. Use it to configure and manage AIOps features from a single place.
3. On the ITOM AIOps configuration center page, under the Setup > Integrations section, select Manage Installed integrations.
4. In the Browse Integrations tab, select the All integrations drop-down list and select Metrics > Pull.



Only metric pull connector tiles are displayed.

5. Select a pull connector tile.

If a pop-up menu opens, select the data to track from that connector and select Continue.

The screenshot shows the 'Solarwinds Metrics' configuration page. The 'Provide details' section is active, showing fields for Name, Data source, and Description. The Name field is filled with 'Solarwinds Metrics', the Data source is 'SolarWinds', and the Description is 'Pulls metrics from Solarwinds platform'. A 'next' button is visible.

6. In the Provide details section, enter the following information and select Next.

- In the Name field, enter a unique name for the connector type.
- In the Data source field, the external source for retrieving metrics is auto-populated based on the tile type you select.
- In the Description field, enter brief information about this connector.

7. In the Set data retrieval method section, enter the following information:

- In the Hostname/Host IP field, enter the IP address that is related to the Solarwinds server.
- From the Credentials drop-down list, select the valid credentials to access the event source host.
- In the Metrics collection schedule (seconds) field, enter the time interval (in seconds) at which the connector retrieves metrics from the source host.
- In the MID Server field, select a MID Server that collects metric data from external tools and securely sends it to ServiceNow.

If none are available, ensure one is installed, running, and has the required capabilities.

Note:

You can select multiple MID Servers. The system randomly assigns one as the primary and uses the others as backups.

8. **Optional:** If you want to customize configurations to meet specific requirements, select Advanced settings and fill in the form.

Field	Description
Max rows per query	Frequency in seconds that indicates how often the system should check for new metrics from the external event source. The value can't be lower than the minimum schedule property, which by default is 120 seconds.
Max fetch interval (in minutes)	Limits the maximum interval between event fetch operations.
Offset (in minutes)	Sets the time offset for event retrieval to ensure accurate synchronization.
Port	Specifies the port number used for communication with external devices. Verify the default values for your connector type such as port details or time formats and modify them as necessary. Default values from your connector are filled-in.
Protocol	Defines the communication protocol used for retrieving events from external devices.
Debugging	◦ Debug: Provides detailed logs for troubleshooting. ◦ Log payload: Displays raw log data. Use only for debugging, as it can quickly fill the MID Server logs.

9. **Optional:** Test the connector before activating it by selecting Test and Save.
10. To save the connector, select Save.
11. To activate the pull connector, select Activate.
- The metric pull connector is activated and its tile is displayed in the Installed Integrations tab. When you open the tile, you can find the Overview, Details, and Data retrieval method tabs.
- The Overview tab allows you to verify that the connector is running and collecting data. It also offers options to improve system settings, such as refining alert definitions or enhancing binding configurations.



SolarWinds Metrics

Metrics Active

DeleteSaveTest and saveDeactivate

OverviewDetailsData retrieval method



This integration is up-and-running
If you want to adjust the types of metrics that are currently monitored go to [Connector metrics](#)

Metric to CI binding
100%
[How to improve](#) [Adjust enrich automation](#)

Promoted anomaly alerts
8
[How to configure](#)

Sample metrics 96
Last refreshed just now.

Metric Type Id	Metric Identifier	Configuration Item	Resource Id	Anomaly Detection Action Level
PercentDiskUsed	Vendor:Windows; NodeID:10; Node:INC0088673-02; ...	inc0088673-02	Virtual Memory	Bounds
PercentDiskUsed	Vendor:Windows; NodeID:6; Node:prtgnewsrv; SysN...	prtgnewsrv	Virtual Memory	Bounds
PercentDiskUsed	Vendor:Linux; NodeID:11; Node:v-kubemaster; Sys...	v-kubemaster	Virtual Memory	Bounds
OutAveragebps	Vendor:Linux; NodeID:11; Node:v-kubemaster; Sys...	v-kubemaster	vetha78fc7c4	Bounds
OutPercentUtil	Vendor:Linux; NodeID:11; Node:v-kubemaster; Sys...	v-kubemaster	vetha78fc7c4	Bounds

The Details tab allows you to update the connector's general information (such as name or description) and displays any errors encountered during its operation.



SolarWinds Metrics

Metrics Active

DeleteSaveTest and saveDeactivate

OverviewDetailsData retrieval method

Provide details
Give your integration a recognizable name and specify how it will connect to your system.

Name * ?
SolarWinds Metrics

Data source ?
SolarWinds

Description ?
Enter description

The Data Retrieval Method tab contains the connector settings (such as host, port, and credentials) and may provide additional details for issues like MID Server errors.



SolarWinds Metrics

Metrics Active

DeleteSaveTest and saveDeactivate

OverviewDetailsData retrieval method

Set data retrieval method
How to extract the data from SolarWinds?

Hostname / Host IP * ?
10.196.33.15

Credential * ?
solrwind_cred

Event collection schedule (in seconds) * ?
60

MID Server * ?
ma8ltz_rp2

Advanced settings

Max fetch interval (in minutes) ?
180

Max rows per query ?
5000

Offset (in minutes) ?
0

Port ?
17774

Protocol ?
☒ https (secured) ☐ http (not secured)

Debugging ?
☒ Debug ☒ Log payload