

Configure the Dynatrace metrics connector instance

- Release version: Australia
-
- Updated March 12, 2026
-
- ⌚ 2 minutes to read

Configure the Dynatrace connector instance to receive Metric Intelligence raw data from the Dynatrace server.

Before you begin

To activate metric collection, ensure that the MID Server that retrieves metrics is configured with the Metric Intelligence extension and that the extension is in Started mode. See [Manually configure the Metric Intelligence extension](#).

- Create an access token in Dynatrace with Read Metrics (metrics.read) scope permissions, to enable fetching metric data. This token is used in the connector to call the Dynatrace REST API.
- Configure the Service graph connector for Dynatrace. This is configured in the instance and discovers Dynatrace CIs. For details on configuring this connector, see [Configure Service Graph Connector for Observability - Dynatrace using guided setup](#).

Role required: evt_mgmt_admin

About this task

By default, the Dynatrace service graph connector discovers CIs and supports metric collection for the following entity types:

- HOST
- APPLICATION
- SERVICE
- PROCESS_GROUP_INSTANCE

Configure other entity metrics for collection when creating event rules for CI binding.

Procedure

1. Navigate to Event Management > Integrations > Connector Instances.
2. Select New and create a connector instance.
For details on the connector instance fields displayed on the page, see Dynatrace connector instance form.
3. Select and hold (or right-click) the form header and select Save.
The connector instance values are added to the form and the parameters that are relevant to the connector appear.
4. **Optional:** In the Connector Instance Values section, you can edit the values of the mandatory Dynatrace parameters.
For details on the connector instance value parameters, see Dynatrace connector instance value parameters.
5. In the MID Servers for Connectors section, add a MID Server for the Dynatrace connector to use.
6. In the Related Links section, select Configure metrics to collect.
Only metrics with the value Active=true are collected by the instance.
7. Configure the metrics you want the instance to collect with the value Active=true.
Metrics with the value Active=false are not collected by the instance.
8. **Optional:** Select New to create new metrics.
Configure the fields on the Connector instance metrics - New record (sn_em_connector_instance_metric) page.

Table 1. Connector instance metrics page - New record

Field	Description
Metric name	Display name for the metric to be configured in the ServiceNow instance.
Metric connector instance	Set by default to Dynatrace connector instance. All metrics are collected for the Dynatrace connector instance.
Metric type	The name of the Dynatrace entity type which the metric belongs to.
Metric ID	The Dynatrace metric ID of the metric being collected.
Active	Select for the metrics to collect.

- Ensure that the CIs related to the metrics exist in the instance.
 - Create an event rule to perform CI binding, as needed. For details, see Create or edit an event rule.
9. Select Test Connector to verify the connection between the MID Server and the connector.

10. After a successful test, select the Active check box and then select Update.