

Configure PRTG connector

- Release version: Australia
-
- Updated March 12, 2026
-
- ⌚ 3 minutes to read

Configure the PRTG connector instance to receive alerts from a Paessler PRTG Network Monitor source.

Before you begin

Role required: evt_mgmt_admin

Supported version: 21.3.71.

Procedure

1. Navigate to All > Event Management > Integrations > Connector Instances.
2. Click New and create a connector instance with the following details:

Field	Value
Name	Descriptive name for the PRTG connector.
Description	Description for the use of the PRTG event collection instance.
Host IP	Specify the PRTG IP address.
Credential	Either select the required credentials from the list or click New and create the required credentials. If you create the credentials, save them using a unique and recognizable name, for example, PRTGOPS.
Event collection last run time	The last run time value is automatically updated.
Last event collection status	The last run time status is automatically updated.
Event collection schedule (seconds)	The frequency in seconds that the system checks for new events from PRTG.
Last error message	The last error message is automatically updated.

Field	Value
Connector definition	Select PRTG.
Connector Instance Values section	The parameters that are specific to PRTG display here when the form is saved.
MID Servers (MID Server for Connectors section)	Optional. Name of a MID Server. If no MID Server is specified, an available MID Server that has a matching IP range is used. In the MID Servers for Connectors section, specify a MID Server that is up and valid. You can configure several MID Servers. If the first is down, the next MID Server is used. If that MID Server is not available, the next is selected, and so on. MID Servers are sorted according to the order that their details were entered into the MID Server for Connectors section.

3. Right-click the form header and select Save.

The connector instance values are added to the form and the parameters that are relevant to the connector appear.

4. In the Connector Instance Values section, specify the PRTG values.

a. add_columns.

Specify which columns to be returned by the connector. Separate the names with a comma and without a space between the names. The output is stored in the Additional information field of the event. Default value `false`. If `false` is specified, only the default list of columns is retrieved: parent, name, type, objid, tags, message, status, priority, datetime, actions, baselink, basetype, modifiedby.

Note:

Only columns names that are applicable to the Message content type can be specified.

b. date_format.

The format date and time. Default format `M/d/yyyy/ h:mm:ss a`. If you receive an event whose date is in a different format, modify this value to match the format of the incoming event. If you do not, the event will not be processed correctly.

For example, if an event arrives on June 27, 2019 at 11:25 AM with a listed date of `2019/06/27/ 11:25:00 a`, modify the `date_format` value to `yyyy/M/d/ h:mm:ss a` to match the format of the received event.

In the `date_format`, `a` represents AM, and `p` represents PM.

c. In the days_from field, specify the number of days for which events must be collected at the first collection cycle.

Default value 7 days.

d. debug.

Default value `false`.

e. port.

Default value 80.

f. protocol.

The default protocol type is `http`.

g. `prtg_api_fetched_events_num`.

Maximum number of events, per query, that can be fetched from the PRTG client into the MID Server. Default number: 50,000.

h. `time_zone`.

The default time zone is the GMT time zone; update this value to the PRTG time zone. For example, if PRTG is sending events according to the EDT time zone, update this value to GMT-4 (abbreviations such as EDT are not supported).

5. Right-click the form header and select Save.

6. Click Test Connector to verify the connection between the MID Server and the connector.

7. If the test fails, follow the instructions that the error issues to correct the problem and then run another test.

If this message appears: `Connection test failed: Failed to connect to PRTG on test connector. Invalid API Key`, then enter the API Key for the specific user to be able to read the PRTG events.

Note:

Use a network tool, such as ping, to verify credential correctness and network connectivity from the MID Server to PRTG.

8. After a successful test, select the Active check box and then click Update.