



Common Component

[Badge](#)[Banner](#)[Bottom Navigation](#)[Bottom Sheet](#)[Buttons](#)[Chips](#)[Controls](#)[Dialog](#)[Empty](#)[Text Inputs](#)[List Header](#)[Search Bar](#)[Page Indicator](#)[Popup](#)[Profile](#)[Progress Indicator](#)[Spinner](#)[Tabs](#)[Top Navigation](#)[Video Player](#)

Contents Component

[Card](#)[Image Grid](#)[List](#)


Chatroom Component

[Flex Message](#)

Bottom Sheet

Bottom sheet is a surface fixed at the bottom of the screen which includes content related to the previous screen.

Anatomy



1. Sheet

is a surface containing content related to the previous screen.

2. Scrim (Optional)

is a dark background that emphasizes the tasks on the bottom sheet, it is divided into Modal / Non-Modal depending on the scrim.

Scrim  = Modal

Scrim  = Non-Modal (Interactive)

3. Header area (Optional)

serves as a navigating bar and its space is divided into Left / Center / Right.

Left: Text, Icon Button

Center: Title

Right: Text, Icon Button

4. Contents area

can be freely configured like an ordinary screen. If the content exceeds the height of the sheet, scrolling becomes possible.

5. Button area (Optional)


is an area where the Floating Fullpage Button can be displayed.

6. Handlebar (Optional)

if a handlebar exists, the "Expandable Sheet" will be displayed for users.

Types

It is divided into the modal type and interactive type depending on the scrim.




Modal Type



This type cannot execute other tasks until those on the bottom sheet are completed or canceled.
A scrim needs to be used behind the bottom sheet.

Interactive Type




This type can interact with the previous screen, unlike the modal type. Do not use a scrim to check the previous screen even if the tasks on the bottom sheet are not complete.

Interaction

Expandable

You can use the handlebar to expand the bottom sheet.



Handlebar	✓ Required
Close Button	✓ ✗ Using X button is recommended
How to Dismiss	Tapping an item that triggers action Tapping the Scrim Swiping the sheet down Via Close Button

- If you drag the handlebar up from the default height, exceeding its threshold, you can expand it to a set height. You can extend its full-height depending on the content.
- If you scroll up (drag) the content area beyond the uppermost part of the sheet, you can expand the sheet in the same way as when expanding through the handlebar. (Optional)
- You can dismiss by dragging the content area of the sheet while the scroll remains at 0 (at the uppermost part of the content).

Not Expandable

This is divided into cases in which the sheet is dismissed and is not dismissed through the gesture of dragging the unexpandable bottom sheet down, and an appropriate measure is applied according to the content.

Dismissible	Not dismissible


Handlebar	Not Required	Not required
Close Button	Using X button is recommended	Using X button is recommended
How to Dismiss	Tapping an item that triggers action Tapping the Scrim Swiping the sheet down Via Close Button	Tapping an item that triggers action Tapping the Scrim Via Close Button Where it is inappropriate to dismiss through a gesture depending on the content, "Pull-to-dismiss" may not be applied.

- You can dismiss this by dragging the content area of the sheet while the scroll remains at 0 (at the uppermost part of the content).
- Where it is inappropriate to dismiss through a gesture depending on the content, "Pull-to-dismiss" may not be applied.

With Keyboard


Non-Scrollable


Among the tasks of the bottom sheet, when importing a keyboard, the sheet will move up according to the height of the keyboard.



Scrollable

When the entire height of the bottom sheet cannot be displayed due to the height of the imported keyboard, scrolling will be enabled in the content area in order to check the content within the sheet.






- when this happens, make sure to affix it at the top of the bottom sheet to dismiss.
- if the entire height of the bottom sheet is moved, moving "Input" further from the keyboard, the person in charge of each service can adjust the scroll properly to make sure "Input" is placed right above the keyboard, bringing the two closer together.


Expanded view

When expanding an expandable bottom sheet while the keyboard is present, it can be expanded to the maximum height with the keyboard still present. The same applies to returning the sheet to its original size from the state in which it was expanded to its maximum height.




Handlebar

Based on the location where the handlebar is placed, it can be used to adjust the layout of the screen. Therefore, a handlebar located at the top of the sheet means that the sheet to which the handlebar belongs and the area above that can be relocated. This is irrelevant regarding whether or not the handlebar and pull-to-dismiss functions are available.



- If there is handlebar, it is necessary to expand it through a gesture, and to dismiss through.
- If there no handlebar, it will be impossible to expand with a gesture, but it can be dismissed depending on the circumstance.

The handlebar is composed of three stages including grab, steer, and release.




- Grab is a stage of grabbing the handlebar to adjust the height of the sheet. Because the size of the handlebar is not large, even if you grab the entire header area, the handlebar is recognized as being grabbed, and this also applies in cases where there is a button in the header. The button function when the action is a tap and if the action is a drag the handlebar grab will function.
- Steer is the stage of adjusting the height of the sheet subsequent to the grab stage. After grabbing and before release, you can freely adjust the sheet up to the permitted height.
- Release is the stage of completing the relocation task after adjusting the height. The sheet is relocated to the pre-set height closest to the coordinate at the moment of raising the handlebar.

Usage

Contents area usage


General

You can omit the header area and immediately start configuring the content area.



Date picker case

Date picker is a template created and provided by LINE Design System Team. When selecting date picker, the system's default date picker can be displayed at the bottom or the content area can be displayed in the date picker area. In the latter case, a button that has depth in the sheet and that can be moved to the previous depth should be provided.




Header area usage

The header area can include a navigation bar by default. Additionally, the header area may include components such as a search bar or tabs that can control the content area depending on user intervention.

Navigation Bar

The header area can include a navigation bar.



- An "X" button is placed on the right by default. However, if it is used in conjunction with a button that progresses the tasks on the right, move it to the left. Therefore, the "X" button can be placed anywhere in terms of design. However, if it is to be located directionally with two or more buttons, irrespective of whether it is on the left or the right, it should be placed in the most peripheral area.
- The "<"(Back) button must be placed in the far left.




Navigation bar

Further details regarding the navigation bar are available on the navigation bar.

Search Bar

The header area can include a search bar. The content searched in the header area are displayed in the content area.



- If the "X" or "Cancel" button is placed on the right, pressing this button will end the searched task and return to the pre-search state.




Search Bar

Further details on the search bar are available in Search type in

Input.

Tabs

The header area can include a text tab and a box tab. When selecting a tab, the content are will be modified.



Tabs


Further details regarding tabs are available in Tabs.

Button area usage

The button area can include buttons and checkboxes by default. The “Switch” component has the UX of being immediately executed upon selection and thus it is not appropriate for sheets that have a provided action button.

Button

Buttons follow the guidelines for the “Fullpage Button” component by default, and can be used in the following manner.




Box Button

Further details regarding fullpage buttons are available on Fullpage Buttons.

Button + Checkbox

Checkboxes and descriptions can be provided at the top of the button. It is recommended that you do not exceed three checkboxes.





Checkbox

Further details regarding checkboxes are available in [Checkbox](#)

Layout

iPhone 8

iPhone X

Controls


Type

☒ Basic view

☐ Expanded view

- The basic view can be set to a range between 0% and 100%, excluding the safe area such as status bar. The height of the bottom sheet is determined depending on the height of the content by default.
- The expanded view is fixed at a 100% height, excluding the safe area such as the status bar. Where the height of the bottom sheet exceeds the maximum height of the device, the height will not expand any more and internal scrolling will be enabled.


Landscape mode





- By default, the height of the entire bottom sheet is set depending on the height of the content, and the same applies to the horizontal mode.
- When the height of the content is altered due to differences in the width of devices (when the device does not have a standard resolution), the height of the bottom sheet may also vary.
- Where the height of the bottom sheet exceeds the maximum height of the screen, a scroll is created when it is converted into horizontal mode. When this occurs, the scroll perspective is set to "0" and the uppermost part of the content will be displayed first.
- If a floating button is being used in the button area, its location must be fixed regardless of mode conversion or scrolling, according to the characteristics of buttons with a fixed location.

Design Spec



The width value should be set so that it is identical to the screen width without any margin. The value of the corner radius is 14 and cannot be modified.