

Overlays

- Popup
- Snackbar
- Toast Overlay
- Tooltip
- Bottom Sheet
- Pulldown Menu

Systems

- LIFF View

Title

True

Title Text

Enter a description text

Button

False

Enter a Two line long description text

Button

Select whether to include a title or not.
Title is included by default.

Description

True

Title Text

Enter a description text

Button

False

Title Text

Button

Select whether to include a description or not.
Description is included by default.

Left Item

Avatar

Title Text

Enter a description text

Button

Service

Title Text

Service	
Icon	
Slot	
None	

Select one from five types as per need.
None is set as default.

Option Name	Description
Avatar	Component to represent a user with an image or username. Refer to the avatar for more information.
Service	Use a service-related image.
Icon	Icons can be changed, and a specific or arbitrary action can be assigned. LAICON is recommended. Refer to the iconography for more information
Slot	Slot is used to add an image or graphic element in addition to provided types.
None	Do not use the left item.

Right Item

Action Button	
Arrow	
None	

Select one from three types. Action button is set as default.


Option Name	Description
Action Button	Confirm or execute a user action. Refer to the action button for more information.
Arrow	Button to move to another page such as read more.

None

Do not use the right item.

Behavior


Appear



Come up from the bottom of the screen after user action.

Disappear


Auto Disappear (Default)



Disappear after 3 seconds without user action. The waiting time can be selected between 4 and 10 seconds.


Dismissed by User Action






Immediately disappear with user action. Refer to the Dismiss Touchable Area below for the area of touch.

Dismiss Touchable Area




- With a button, the button and area excluding the margin between text are defined as touchable area.
- Without a button, the entire area is defined as touchable area.

Usage




Title + Description	1 Line
---------------------	--------

- Message for users can be included in the text area.
- Recommended to allow up to 1 line for the title and 2 lines for the description.




- Left item related to the message can be used, but the area does not provide a specific feature or act as a button.
- Use the message area to provide a guide for user action and move to the related page when tapping the snackbar.
- Recommended to use an icon relevant to the message.




- Provide an action button on the right with a text button or icon.
- The entire snackbar acts as a link when no action button is added.
Provide simple feedback information and allow users to move to a relevant page.






Do

Use it instead of a pop-up for simple feedback to user action.




Don't

Don't use a pop-up for simple notice.




Do

Recommended to give a margin of 16 px from the safe area.




Don't

Don't interrupt the safe area in case of components with the safe area such as iPhone X+.
As for iPhone X, use 34 pt as home indicator section.




Do

Give a margin of at least 16 px from the bottom of the screen.




Don't

Don't provide it without a margin from the bottom.




Do


Give a margin from the bottom navigation.
Allow a margin of at least 16 px.



Don't

Don't interrupt the bottom navigation area.






Don't

Don't use two or more snackbars at the same time. When two or more snackbars are called, the second snackbar should appear after the first snackbar disappears.


Design Specs

Placement



Value	Description
	Changeable
Bottom	Default: 16px


Resizing



Fixed Padding

	Value	Description
1	Flexible Width	Width is adjusted based on the width of the screen. (i. e. 100% of the screen width)
2	Auto Height	Height is automatically adjusted based on the number of text lines.
3	Title	Fixed padding cannot be changed.

Example 1. The Height Value Changes Depending on The Length of The Description Text




Example 2. The Text Area and Text Area Size Change Depending on The Length of The Button Label




Example 3. Change Text Area width According to Snack Bar Width Size





Styles



Element	Properties
1 Container	- Background: Unchangeable - Size: Unchangeable - Color: Unchangeable - Default: Idsg-opacity-black-85
2 Left Item	Follows each items rule below.
3 Title	- Typhography: Changeable - Size: Unchangeable - Color: Changeable - Default: Idsg-color-white
	Typhography: Changeable

- 4

Description
- Size: Unchangeable

• Color: Changeable


◦ Default: Idsg-opacity-white-40

◦ Only Description: Idsg-color-white

- 5

Right Item
- Follows each items rule below.

Options



Element	Properties
Avatar	• Size: Unchangeable
Service	• Size: Unchangeable
Icon	• Iconography: Changeable ◦ Contained: Unchangeable ◦ Outlined: Unchangeable • Size: Unchangeable • Color: Changeable ◦ Default: Idsg-color-gray-350
Slot	• Size: Unchangeable
Action Button	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Changeable ◦ Default: Idsg-color-brand-primary
	• Iconography: Unchangeable

Arrow

- Size: Unchangeable
- Color: Changeable
 - Default: ldsg-color-gray-350