



Buttons

Action Button

Floating Action Button

Icon Button

Contents

Avatar

Tag

Image Grid

Skeleton

Video Player

Indicators

Badge

Page Controller

Page Indicator

Progress Indicator

Inputs

Checkbox

Chip

Radio Button

Slider

Stepper

Switch

Text Area

Text Input

Pulldown

Navigations

Tab

Tab - Expanded Tab List

Side Drawer

Footer

Top Navigation


Segmented Control

Bottom Navigation

Video Player


The video player is used for controlling videos, such as playing them.

Anatomy



1. Container
2. Headline (Optional)
3. Center Area (Optional)
4. Toolbar
5. Dimmer

Element Patterns and Types




Overlays

- Popup
- Snackbar
- Toast Overlay
- Tooltip
- Bottom Sheet
- Pulldown Menu

Systems


- LIFF View



The video player provides two types of themes.

Element Pattern	Description
Theme A	Basic control functions, such as playback and pause, are provided in the center area. Optimized for the mobile environment.
Theme B	Basic control functions, such as playback and pause, are provided in the toolbar. Optimized for the PC environment.

Scene



The video player shows different screens depending on the context. You can select the scene you want to use.

Option Name	Description
Before Playing	The screen displayed before playing a video.
AD	The screen showing an ad before playing the video. Select whether to use the screen depending on the ad option.
Playing	The screen when playing the video.
Seek	The screen when moving to a specific position while playing a video.
Ended	The screen when a video ends.
Setting	The screen for playback settings, such as subtitles, resolution, and playback rate.
Subtitle	Shows subtitles in the video player when enabled.
Error	Dislaved when an error occurred (e.g. Unable to play the video)

Embeds the video content in the video player area.

Thumbnail Shows the thumbnail image and length of the video.

Loading A screen displayed while loading the video.

PIP Mode Shows the video in the corner of the device screen when browsing content outside of the video player area.

Headline

Light

THIS IS A VIDEO TITLE

+

+

+

Controls

Profile Image

True

False

Title

Only Title

Title + Description

Title + Sponsor Name

Title + Live

Title + Description + Live

Title + Sponsor Name + Live

None

Select whether to provide the profile image.
Customize the slot depending on the context.
For more information about the slot options, see the Child Elements section below.

Option Name	Description
Only Title	Used to provide the title alone.
Title + Description	Used to provide additional information about the video.
Title + Sponsor Name	Used for the ad screen only.
Title + Live	Used for the live video only. For more information about the live options, see the Child Elements section below.
Title + Description + Live	Used to provide additional information about the live video.
Title + Sponsor Name + Live	Used for the ad screen for live videos only.
None	No options are used.


Toolbar

Light


Controls

Theme

Theme A




Customize the slot depending on the context.
For more information about the slot options, see the Child Elements section below.



Theme A: Select whether to show the play time on track.
Theme B: Use the previous/next video option depending on the Play/Pause status.

Control

Play




Next

☒ Enabled

Theme A: Select whether to show the play time with the play button.
Use the previous/next video option depending on the Play/Pause status.

Seek

Light



Controls

Theme

☒ Theme A

☐ Theme B

Element Pattern

☒ Video Track Move

☐ Tap To Seek


☐ Volume Value

Move to a specific position while playing the video.

Option Name	Description
Video Track Move	Drag the thumb of the track to change the current time.
Tap To Seek	Double tap the left/right side of the screen to change the current time.
Volume Value	Use the up/down key of the keyboard to change the volume on the PC.

Ended

Light



Controls

Theme A

☒ Theme A

☐ Theme B

Element Pattern

☒ Cancel Label (With Autoplay)

☐ Replay Label

☐ Replay Label + Outlink Label


☐ Recommended Video

You can play the next video or see the recommended video list at the end of the video.

Option Name	Description
Cancel Label (With Autoplay)	Autoplay enabled: Play the next video automatically.
Replay Label	Autoplay disabled: Show the Replay button.
Replay Label + Outlink Label	Autoplay disabled: Move to different page by using the Replay button or Outlink button. The button name can be set in the service.
Recommended Video	Go to another video via the recommended video list. For more information about the recommended video options, see the Child Elements section below.

Error


Play Error



Country Error




Network Error



Three error screens are provided.

Option Name	Description
Play Error	Unable to play the video due to an error.
Country Error	Unable to play the video in this country.
Network Error	Unable to play the video due to a network error. Select the Retry button to refresh the video player.

PIP Mode




Use the Tab to play or pause the video in the corner of the device's screen.
An error screen will be displayed when the player is unable to play the video.



Four image ratios are provided.
We recommend you follow the guidelines when creating an image file.
For more information, refer to Do & Don't in the Usage section.

Child Elements


Live Option






The live tag is provided by default in the live video.
Select the playtime and options (viewers and players) depending on the status of the live video.

Recommended Video Option




Four image ratios are provided.
We recommend you follow the guidelines when creating an image file.
For more information, refer to Do & Don't in the Usage section.
Use a thumbnail with or without the Play icon.



The left/right button option is provided for the recommended video list.
Use the See More button to go to a different page for less than three images.
The button name can be set in the service.

Slot Option




Option Name	Description
Resolution	Go to the screen for setting the resolution. The resolution button will be changed to that with the selected resolution value. Select the arrow direction for each component (headline/toolbar).
Subtitle	Caption On/Off: Set to Off by default. Not available in the live video.
Playback Rate	Go to the screen for setting the playback rate.
Share (TBD)	Share the video from the settings screen or bottom sheet.
More	Go to the screen for setting the video.
Screen	Choose the screen option: Full/Default.
Volume	Control the volume using Mute/Unmute depending on the volume. Set to Mute by default. The No Sound icon will be displayed for videos without sound.
Seek	Skip back and forward by 15 seconds. The skip length can be entered by the user. (Default: 15)
Replay	Replay the video.
Outlink	Go to different page.
PIP Mode	Turn on the PIP mode to play the video outside the video player area.
See More	Used for the ad screen only. Redirect the user to the linked ad page.
Current Time / Duration	Can be used in Theme B. The current/total play time of the video will be displayed.

Behavior


Theme A Theme B

Show/Hide



All controls are only operated within the video player. You can tap anywhere to show the control UI.

States



The display options for Hover and Press are as follows.
Hover is used for PC web only.

Control

Full Screen

Full Screen



Switch to full-screen mode to use the native player (iOS) or expand the device's screen size (Android). The video size is adjusted based on the maximum width if the device direction is changed.


AD Skip



This area will change to a Skip button depending on the ad duration. However, this area may not be available depending on the ad platform policy.

Seek

Video Track Drag&Drop




Double Tap




Drag the Thumb of the track or double-tap the left or right side of the screen to change the current time. The Skip length for the double-tap action can be entered by the user. (Default: 15)

Volume


Headline



Toolbar



Hover the cursor over the volume button to show the volume slider. Control the volume using the slider. The location of the volume slider depends on the component (Headline/Toolbar).




Use the up/down key of the keyboard to change the volume.
The volume can be increased or decreased by 5%.

Appear & Disappear - Key press


Press the volume key to control the volume.
If you Hold/Hit the key, it will be animated faster than pressing.

Ended




The video player plays the next video automatically or shows the Replay/Outlink button at the end of the video depending on the auto-play settings.

Appear - Auto Play on/off




Move around the recommended video list by swiping the screen or using the left and right buttons.

Setting




Click the See More button to show the settings as an Overlay.


Subtitle



Two lines of subtitles are provided depending on the width, and they can be turned On or Off with the Caption button.


PIP Mode






Turn on PIP mode to play the video in the corner of the device screen using the PIP button.
Press and drag to move the video player to any location within the device screen.
Tap the screen to play or pause the video and close PIP mode to go back to the default screen.

Usage




Caution

Please do not use the play time option for both the video track and the play button.




Caution

Pay attention to the use of the video track when playing an ad.
By default, the video track will not be provided.
Depending on the service ad platform, you can select whether to provide the track.





Do


Recommended video thumbnails that exceed the video player size are dimmed.



Don't


The number of icons should not be greater than that of the slots provided.






Don't

Multiple items within the Slot option cannot be selected.



Do

The See More button can only be used for ads.



Do

The current and total playtime option is used in Theme B only.


Design Specs

Resizing



All themes in the video player are designed to be responsive to the device.
Select from Small, Medium, or Large for the device width.
Depending on the service, fixed type video players can be used with specified themes and sizes.

Width Size	Option Name	Description
0px ~ 1024px	Small	Used in the mobile device.
1025px ~1799px	Medium	Used in the tablet device.
1800px~	Large	Used in PC.




1 Flexible Width

The title length should not exceed one line.
Consider the space between the title and icon, the left and right margins, and the video player width.

Element	Description
1 Flexible Width	Possible to set for each service. Be careful not to exceed the device width.
2 Flexible Height	Possible to set for each service. It is recommended to set the height based on the image ratio.


Placement

PIP Mode



The width and height of the video player in PIP mode can be set within 100% (width) and 70% (height) of the device, excluding the left and right margins (16).
The height of the home indicator should be included in the 70% of the height (iOS).
It is recommended to customize it using the same ratio as the default video player.


Recommended Video Option



- The width and height of the custom thumbnail can be set within 100% (width) and 70% (height) of the video player, excluding the left and right margins (12).
- The height of the recommended video title and Toolbar should be included in the 70% of the height.

Styles


Container



Element	Properties
1 Container	• Width: Flexible Width, 100% • Height: Flexible Height, 100% • Background Color: Unchangeable

- Default: Idsg-color-black


Headline




Element		Properties
1	Profile Image	• Follows avatar rules
2-1	Title	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
2-2	Description	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-gray-150
		Tag • Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable Live Time • Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
3	Live	Audience • Iconography: Unchangeable


		◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white • Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
		Tag • Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable Live Time • Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
4	Replay	Audience • Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white • Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
		Tag • Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-gray-150
5	Sponsor Name	Description • Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-gray-150
6	Option Slot	• Follows slot option items rule below

Toolbar





Element		Properties
1-1	Current Time	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: ldsg-color-white
1-2	Duration	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: ldsg-color-white
2	Video Track	• Follows slider rules
3	Option Slot	• Follows slot option items rule below
4-1	Previous Video Button	• Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: ldsg-color-white
4-2	Next Video Button	• Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: ldsg-color-white
5	Play/Pause Button	• Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: ldsg-color-white



Element		Properties
1-1	Previous Video Button	• Iconography: Unchangeable
		◦ Size: Unchangeable
1-2	Next Video Button	• Iconography: Unchangeable
		◦ Size: Unchangeable

		◦ Default: Idsg-color-white
2	Play/Pause Button	• Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
3	Duration	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
4-1	AD Count	• Background: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-opacity-black-50 • Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Description Default: Idsg-color-white ◦ Number Default: Idsg-color-lightgreen-500
4-2	Skip Button	• Background: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-opacity-black-50 • Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
5	Play Position	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
6	Position Gap	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
7	Volume Meter	• Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white

- Typography: Changeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white

8-1 Seek


- Background: Unchangeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-opacity-white-20


8-2 Backward/Forward 15 sec

- Iconography: Unchangeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white
- Typography: Changeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white

9 Backward/Forward 15 sec

- Iconography: Unchangeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white





Element	Properties
1 Progress	Follows progress indicator rules
2 Action Button	- Typhography: Changeable - Size: Unchangeable - Color: Unchangeable - Default: Idsg-color-white
3 Replay/Out-link Button	- Iconography: Unchangeable - Size: Unchangeable - Color: Unchangeable - Default: Idsg-color-white - Typhography: Changeable - Size: Unchangeable - Color: Unchangeable - Default: Idsg-color-white
4 Left/Right Button	- Background: Unchangeable - Size: Unchangeable - Color: Unchangeable - Default: Idsg-opacity-black-80 - Iconography: Unchangeable - Size: Unchangeable - Color: Unchangeable - Default: Idsg-color-white

5	Recommended Videos Title	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
6	Service See More Button	• Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white • Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
7	Subtitle	• Background: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-opacity-black-40 • Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
8	Error Icon	• Iconography: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-gray-400
9	Error Description	• Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-gray-400
10	Duration	• Background: Unchangeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-opacity-black-50 • Typography: Changeable ◦ Size: Unchangeable ◦ Color: Unchangeable ◦ Default: Idsg-color-white
11	Loading	• Follows progress indicator rules

2 Setting

- Size: Unchangeable
- Color: Unchangeable
 - Default: Idsg-opacity-black-50
 - Pressed: Idsg-opacity-white-10
- Typography: Changeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Lable Default: Idsg-color-gray-350
 - Values Default: Idsg-color-white

3 Back Button

- Iconography: Unchangeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-opacity-white-50

4 Setting Option

- Typography: Changeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white
 - Selected: Idsg-color-lightgreen-500

5 Setting

- Background: Unchangeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-opacity-black-60
 - Pressed: Idsg-opacity-white-10
- Typography: Changeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Lable Default: Idsg-color-gray-350
 - Values Default: Idsg-color-white


6 Back Button

- Iconography: Unchangeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-gray-350

7 Lable

- Background: Unchangeable
 - Typography: Changeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-gray-350

Slot Option



Element

Properties

Resolution

- Iconography: Unchangeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white
- Typography: Changeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white

Subtitle

- Iconography: Unchangeable
 - Contained: Unchangeable
 - Outlined: Unchangeable
- Size: Unchangeable
- Color: Unchangeable
 - Default: Idsg-color-white

Playback Rate

- Iconography: Unchangeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white

Share

- Iconography: Unchangeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white

		Iconography: Unchangeable
		Size: Unchangeable
		Color: Unchangeable
		Default: Idsg-color-white
		Iconography: Unchangeable
		Size: Unchangeable
		Color: Unchangeable
		Default: Idsg-color-white
		Iconography: Unchangeable
		Size: Unchangeable
		Color: Unchangeable
		Default: Idsg-color-white
		Iconography: Unchangeable
		Size: Unchangeable
		Color: Unchangeable
		Default: Idsg-color-white
		Iconography: Unchangeable
		Size: Unchangeable
		Color: Unchangeable
		Default: Idsg-color-white
		Iconography: Unchangeable
		Size: Unchangeable
		Color: Unchangeable
		Default: Idsg-color-white
		Iconography: Unchangeable
		Size: Unchangeable
		Color: Unchangeable
		Default: Idsg-color-white
		Iconography: Unchangeable
		Size: Unchangeable
		Color: Unchangeable
		Default: Idsg-color-white
		Background: Unchangeable
		Size: Unchangeable
		Color: Unchangeable
		Default: Idsg-opacity-black-50
		Iconography: Unchangeable
		Size: Unchangeable
		Color: Unchangeable
		Default: Idsg-color-white

- Typography: Changeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white

Current Time/Duration

- Typography: Changeable
 - Size: Unchangeable
 - Color: Unchangeable
 - Default: Idsg-color-white
-