
DBA2 DAY03



I	力	容

上午	09:00 ~ 09:30	作业讲解和回顾	
	09:30 ~ 10:20	MHA集群概述	
	10:30 ~ 11:20		
	11:30 ~ 12:00	如果 M L L A 佳 RY	
下午	14:00 ~ 14:50	部署MHA集群	
	15:00 ~ 15:50		
	16:10 ~ 17:00	测试配置	
	17:10 ~ 18:00	总结和答疑	





2019/1/10 P



MHA介绍

Tedu.cn 达内教育

MHA简介

- MHA (Master High Availability)
 - 由日本DeNA公司youshimaton开发
 - 是一套优秀的实现MySQL高可用的解决方案
 - 数据库的自动故障切换操作能做到在0~30秒之内
 - MHA能确保在故障切换过程中保证数据的一致性,以达到真正意义上的高可用



MHA组成

- MHA Manager (管理节点)
 - 可以单独部署在一台独立的机器上,管理其他节点
 - 也可以部署在一台slave节点上
- MHA Node (数据节点)
 - 运行在每台MySQL服务器上



知识讲解



MHA工作过程

2019/1/10 F









MHA工作过程

- 由Manager定时探测集群中的master节点
- 当master故障时, Manager自动将拥有最新数据的 slave提升为新的master
- 关键点
 - 1)从宕机崩溃的master保存二进制日志事件
 - 2)识别含有最新更新的slave
 - 3)应用差异的中继日志 (relay log) 到其他的slave
 - 4)应用从master保存的二进制日志事件
 - 5)提升一个slave为新的master
 - 6)使其他的slave连接新的master进行复制

+*





IP规划



知识讲解

角色	IP地址	主机名
Master主节点服务器	192.168.4.51	master51
备用1主节点服务器	192.168.4.52	master 52
备用2主节点服务器	192.168.4.53	master53
第1台 slave服务器	192.168.4.54	slave54
第2台 slave服务器	192.168.4.55	slave55
MHA_manager服务器	192.168.4.56	mgm56
VIP地址	192.168.4.100	

+†



准备集群环境

Tedu.cn 达内教育

安装软件包

· 所有主机上安装Perl依赖包

[root@db108 share]# ls perl-*.rpm perl-Config-Tiny-2.14-7.el7.noarch.rpm perl-Mail-Sender-0.8.23-1.el7.noarch.rpm perl-MIME-Types-1.38-2.el7.noarch.rpm perl-Email-Date-Format-1.002-15.el7.noarch.rpm perl-Mail-Sendmail-0.79-21.el7.art.noarch.rpm perl-Parallel-ForkManager-1.18-2.el7.noarch.rpm perl-Log-Dispatch-2.41-1.el7.1.noarch.rpm perl-MIME-Lite-3.030-1.el7.noarch.rpm [root@db108 share]# yum -y install perl-*.rpm

• 在所有数据节点上授权监控用户

mysql> grant all on *.* to root@'%' identified by '123456';

++

知识

讲

知识讲解

安装软件包(续1)

· 在所有数据库服务器上安装mha-node包

```
# yum -y install perl-DBD-mysql perl-DBI
# rpm -ivh mha4mysql-node-0.56-0.el6.noarch.rpm
```

• 在管理主机上安装mha_node 和 mha-manager包

PPT

```
# yum -y install perl-DBD-mysql perl-DBI
# rpm -ivh mha4mysql-node-0.56-0.el6.noarch.rpm

# yum -y install perl-ExtUtils-* perl-CPAN-*
# tar -zxf mha4mysql-manager-0.56.tar.gz
# cd mha4mysql-manager-0.56
# perl Makefile.PL
# make
# make install
```





配置ssh密钥对认证登陆

- · 所有节点之间互相以root秘钥对认证登录
- 管理主机以root秘钥对认证登录所有数据节点主机

```
[root@server0 ~]# ssh-keygen
[root@server0 ~]# ssh-copy-id root@192.168.4.X
```





配置master主节点

master51 数据库服务器配置文件

vim /etc/my.cnf
[mysqld]
plugin-load =
"rpl_semi_sync_master=semisync_master.so;rpl_semi_sync_slave=
semisync_slave.so"
rpl-semi-sync-master-enabled = 1
rpl-semi-sync-slave-enabled = 1
server_id=51
log-bin=master51
binlog-format="mixed"

systemctl restart mysqld



知

识

八讲解



配置master主节点(续1)

• 添加主从同步授权用户

mysql> set global relay_log_purge=off;

//不自动删除本机的中继日志文件

mysql> grant replication slave on *.* to repluser@"%" identified by "123456";



配置备用1主节点

• 备用1 master52 数据库服务器配置文件

PPT

mysql> set global relay_log_purge=off

vim /etc/my.cnf
[mysqld]
plugin-load =
"rpl_semi_sync_master=semisync_master.so;rpl_semi_sync_slave=
semisync_slave.so

rpl-semi-sync-master-enabled = 1
rpl-semi-sync-slave-enabled = 1
server_id=52
log-bin=master52

binlog-format="mixed"



知识

八讲解



配置备用1主节点(续1)

• 备用1 master52 数据库服务器配置文件

mysql> set global relay_log_purge=off

mysql> change master to

- -> master_host="192.168.4.51",
- -> master_user="repluser",
- -> master_password="1234546",
- -> master_log_file="master51.000001",
- -> master_log_pos=441;

Query OK, 0 rows affected, 2 warnings (0.04 sec)

mysql> start slave; Query OK, 0 rows affected (0.01 sec)



知识

讲解

配置备用2主节点(续1)

• 备用2 master53 数据库服务器配置文件

PPT

mysql> set global relay_log_purge=off;

mysql> change master to

- -> master_host="192.168.4.51",
- -> master_user="repluser",
- -> master_password="123456",
- -> master_log_file="master51.000001",
- -> master_log_pos=441;

Query OK, 0 rows affected, 2 warnings (0.04 sec)

mysql> start slave; Query OK, 0 rows affected (0.01 sec)



知识

八讲解



配置2台 slave服务器

· 从库 slave54 数据库服务器配置文件

vim /etc/my.cnf [mysqld] server_id=54

mysql> change master to

- -> master_host="192.168.4.51",
- -> master_user="repluser",
- -> master_password="123456",
- -> master_log_file="master51.000001",
- -> master_log_pos=441;

Query OK, 0 rows affected, 2 warnings (0.04 sec)

mysql> start slave; Query OK, 0 rows affected (0.01 sec)



知识

讲解



配置2台 slave服务器(续1)

从库 slave54 数据库服务器配置文件

```
# vim /etc/my.cnf
[mysqld]
server_id=55
mysql> change master to
```

- - -> master host="192.168.4.51",
 - -> master_user="repluser",
 - -> master_password="123456",
 - -> master_log_file="master51.000001",
 - -> master_log_pos=441;

Query OK, 0 rows affected, 2 warnings (0.04 sec)

```
mysql> start slave;
Query OK, 0 rows affected (0.01 sec)
```



知 识 八讲解



配置管理主机

- 管理节点主机配置文件
 - 参考 mha4mysql-manager-0.56 /samples/conf/app1.cnf 样板文件建立

```
# vim /etc/mha_manager/app1.cnf
[server default]
```

manager_workdir=/etc/mha_manager manager_log=/etc/mha_manager/manager.log

master_ip_failover_script=/usr/local/bin/master_ip_failover

//自动failover的切换脚本

```
ssh user=root
ssh_port=22
repl user=repluser
repl password=123456
user=root
password=123456
```

//主从同步用户名 //主从同步密码 //数据库用户名 //密码

知识

讲解

配置管理主机(续2)




知识讲解

[server4] hostname=192.168.4.54 port=3306 no_master=1

[server5] hostname=192.168.4.55 port=3306 no_master=1 //不竞选master

//不竞选master







测试主从同步状态

- 在管理节点上查看集群状态
 - masterha_check_repl --conf=管理节点主配置文件

masterha_check_repl --conf=/etc/masterha/app1.cnf
Wed Jan 24 02:02:46 2018 - [info] Alive Servers:
Wed Jan 24 02:02:46 2018 - [info] 192.168.4.51(192.168.4.51:3306)
Wed Jan 24 02:02:46 2018 - [info] 192.168.4.52(192.168.4.52:3306)
Wed Jan 24 02:02:46 2018 - [info] 192.168.4.54(192.168.4.53:3306)
Wed Jan 24 02:02:46 2018 - [info] 192.168.4.54(192.168.4.55:3306)
Wed Jan 24 02:02:46 2018 - [info] 192.168.4.55(192.168.4.55:3306)



知

识讲解





启动MHA_Manager(续1)

• 查看状态 : masterha_check_status

[root@host56 ~]# masterha_check_status --conf=/etc/mha/app1.cnf app1 (pid:19513) is running(0:PING_OK), master:192.168.4.51

PPT

• 停止服务 : masterha_stop

masterha_stop --conf=/etc/mha/app1.cnf Stopped app1 successfully. [root@host56 bin]#



知

紀识讲解



测试高可用配置



修改故障切换脚本

• 修改 master_ip_failover 脚本,设置如下内容



知

识讲解

查看VIP地址



• 当主库服务器宕机后,在备用1 主节点查看VIP地址

```
# ip addr show | grep vip地址
```

• 手动配置vip地址

```
# ifconfig ethX:1 x.x.x.x/32
```

案例3:测试MHA集群

PPT

- 1. 查看MHA集群状态
- 2. 测试节点之间的SSH登录
- 3. 测试集群VIP的故障切换功能



课堂练习