


Quantum Vol-Delta Trader Manual

Dear Trader,

We hope you gain valuable insights using Quantum Vol-Delta. This manual will help you quickly get up to speed and leverage the full potential of Volume Delta to make more informed trading decisions.



Note: To ensure Quantum Vol-Delta functions correctly and delivers optimal results, make sure Tick Replay is enabled during use.




1. Overview

Quantum Vol-Delta is built on the **difference between buying and selling pressure (Delta)** for each candle.

It is calculated as $\text{Buy Volume} - \text{Sell Volume}$. A positive value indicates that buying volume dominates, while a negative value indicates that selling volume dominates.


Key components of the indicator:

From each histogram bar, you can identify 2 pieces of information: the Delta volume of the candle and the individual Buy or Sell volume within that candle.




In the image above, the part labeled 1 within the histogram bar represents the candle's **Delta volume**, while the part labeled 2 shows the candle's **Buy or Sell volume**.

- **Threshold: Positive Moderate:** This is the low positive Delta volume threshold used to identify emerging buying pressure.
- **Threshold: Negative Moderate:** This is the low negative Delta volume threshold used to identify emerging selling pressure.



- **Threshold: Positive Strong:** This is the high positive Delta volume threshold used to identify strong buying pressure.
- **Threshold: Negative Strong:** This is the high negative Delta volume threshold used to identify strong selling pressure.



- **Volume Average Buy (Green Zone):** This represents the average buying volume over a given period.
- **Volume Average Sell (Pink Zone):** This represents the average selling volume over a given period.





- **Strong Delta Signal** (Large blue/pink dot): Appears when the difference between Buy and Sell volume exceeds the Positive/Negative Strong threshold. This signal indicates that significant buying or selling pressure has emerged.





- **Moderate Delta Signal** (Small blue/pink dot): Appears when the difference between Buy and Sell volume exceeds the Positive/Negative Moderate threshold. This signal indicates that buying or selling pressure has started to emerge.





2. Parameters

Parameters

Volume Base

BidAskPrice_RealVolume

Volume Filter: Enabled

☐

Volume Filter: Size Minimum

1

Volume Filter: Size Maximum

999

Period: Volume

30

Period: Delta

20

Threshold: Ratio Strong-Moderate

3

Signal Filter: Enabled

☐

2.1. Volume Base

Volume Base

BidAskPrice_RealVolume

- **BidAskPrice_RealVolume**

This mode should be used for instruments with real volumes (**futures & stocks**).

Buy volume & sell volume are defined as follows:

- **Buy Volume:** If the price of a tick is greater than or equal to the ask price, the real volume of the tick is categorized as buy volume and added to the total buy volume of the bar that the tick belongs to.

- **Sell Volume:** If the price of a tick is less than or equal to the bid price, the real volume of the tick is categorized as sell volume and added to the total sell volume of the bar that the tick belongs to.

In this mode, if Tick Replay is enabled, the indicator functions on both **historical & real-time data**. Please visit https://ninjatrade.com/support/helpGuides/nt8/en-us/?tick_replay.htm for instructions on how to enable Tick Replay.

If Tick Replay is disabled, the indicator functions only on **real-time data** and there are no calculations on historical data. Any actions that lead to chart reloading will erase all calculations.

- **UpDownTick_RealVolume**

This mode should be used for instruments with real volumes (**futures & stocks**).

Buy volume & sell volume are defined as follows:

- **Buy Volume:** If a tick is up or remains up, the real volume of the tick is categorized as buy volume and added to the total buy volume of the bar that the tick belongs to.
- **Sell Volume:** If a tick is down or remains down, the real volume of the tick is categorized as sell volume and added to the total sell volume of the bar that the tick belongs to.

In this mode, the indicator functions on both **historical & real-time data**. However, please be advised that historical and real-time calculations of the same bar may not be 100% identical, due to technical limitations.

- **UpDownTick_UnitVolume**

This mode is the one & only choice for instruments without real volumes (**forex, CFDs, indices**).

Buy volume & sell volume are defined as follows:

- **Buy Volume:** If a tick is up or remains up, a unit volume (1) is credited as buy volume for the tick and added to the total buy volume of the bar that the tick belongs to.
- **Sell Volume:** If a tick is down or remains down, a unit volume (1) is credited as sell volume for the tick and added to the total sell volume of the bar that the tick belongs to.

In this mode, the indicator functions on both **historical & real-time data**. However, please be advised that historical and real-time calculations of the same bar may not be 100% identical, due to technical limitations.

2.2. Volume Filter

Volume Filter: Enabled	☒
------------------------	-------------------------------------

- "Volume Filter: Enabled": When this feature is enabled or disabled, the indicator will calculate (or ignore) Delta based only on trades with volumes within the range defined by Volume Filter: Size Minimum and Volume Filter: Size Maximum.

- **Volume Filter: Size Minimum**

Volume Filter: Size Minimum	1
-----------------------------	---

- "Volume Filter: Size Minimum": This parameter sets the minimum volume of a trade (contract/lot/share) that will be included in the Delta calculation.

Example: If you set **Volume Filter: Size Minimum = 3** and enable Volume Filter, trades with a volume smaller than 3 will be excluded. The indicator will calculate Delta only from trades with a volume ≥ 3 .

- **Volume Filter: Size Maximum**

Volume Filter: Size Maximum	999
-----------------------------	-----

- "Volume Filter: Size Maximum": This parameter sets the maximum volume of a trade (contract/lot/share) that will be included in the Delta calculation.

Example: If you set **Volume Filter: Size Maximum = 999** and enable Volume Filter, trades with a volume greater than 999 will be excluded. The indicator will calculate Delta only from trades with a volume ≤ 999 .

2.3. Period: Volume

Period: Volume	30
----------------	----

- "Period: Volume": This parameter sets the number of candles used to calculate the average Buy/Sell volume thresholds.

Example: If **Period: Volume = 30**, the indicator will calculate the Buy Volume Average and Sell Volume Average based on the last 30 candles.

2.4. Period: Delta

Period: Delta	20
---------------	----


- "Period: Delta": This parameter sets the number of candles used to calculate the Moderate Delta volume threshold.

Example: If **Period: Delta = 20**, the indicator will calculate the Positive/Negative Moderate Delta volume thresholds based on the last 20 candles.

2.4. Threshold: Ratio Strong-Moderate

Threshold: Ratio Strong-Moderate	3
----------------------------------	---

- "Threshold: Ratio Strong-Moderate": This parameter defines the multiplier used to calculate the Positive/Negative Strong Delta thresholds.



Example: As shown in the illustration above, **Threshold: Positive Moderate = 61.36**. If we set **Threshold: Ratio Strong-Moderate = 3**, this means:

$$\text{Threshold: Positive Strong} = \text{Positive Moderate} \times 3 = 61.36 \times 3 = 184.08$$


2.4. Signal Filter: Enabled

Signal Filter: Enabled	☐
------------------------	--------------------------

- "Threshold: Ratio Strong-Moderate": This parameter toggles the advanced signal filter on or off.
When enabled, Quantum Vol-Delta will display **positive Delta signals** only on green candles with clear, decisive price action, where buying volume exceeds the average Buy Volume threshold.

Conversely, **negative Delta signals** will appear only on red candles with strong, decisive price action, where selling volume exceeds the average Sell Volume threshold.

When disabled, the indicator will display all Delta signals based solely on the thresholds, without considering candle structure or average volume.



As illustrated in the image above, after enabling the filter, negative Delta signals will appear only when all of the following conditions are met: high negative Delta volume, selling volume exceeding the average Sell Volume, and a red candle showing decisive price action.

In another example, although the negative Delta volume and Sell Volume both exceed their average thresholds, the price shows indecision with a wick-heavy candle. As a result, the signal is not triggered.

3. Dedicated NinjaScript Signals

You can rely on the signals below to build your own strategy:

- ***Signal_Strong Positive/Negative: 3 = Strong Bullish, -3 = Strong Bearish***
- ***Signal_Moderate Positive/Negative: 2 = Moderate Bullish, - 2 = Moderate Bearish***

Below is the example condition for this indicator based on the **Signal_Trade**:

If Signal_Trade equals to 3 or 2, you can enter long here.

If Signal_Trade equal to -3 or -2, you can enter short here.

Please follow the link below to find more information about Strategy Builder.

<https://youtu.be/mtMNjOQtQE>