



This manual will help you understand its capabilities, including the core features introduced in Version 1 and the major enhancements added in Version 2.




1. Interface


Captain Optimus Strong v2 is designed with a clean and intuitive interface, focusing on the core functional areas that support the trade execution process.

1.1 Control Panel

The Control Panel consists of the following sections:



- Row 1




"Captain Optimus Strong v2" button: Opens the system's strategy configuration window.

- Row 2
 - "CANCEL" button: Cancels all pending orders.


- "CLOSE" button: Closes all open positions and cancels all active orders.
- Row 3
 - "LONG" button: When enabled, the system automatically places a **Buy** order upon detecting a bullish signal.
 - "SHORT" button: When enabled, the system automatically places a **Sell** order upon detecting a bearish signal.
- Row 4:

Specifies the number of contracts to trade. The contract quantity displayed on the Control Panel can be configured in the "Quantity" section under "General".




- Row 5:

"Reference Price": Specifies the base price from which the offset is applied.




- "Close_SignalBar": Uses the signal bar's closing price as the reference price.

- "Open_SignalBar": Uses the signal bar's opening price as the reference price.
 - "High_SignalBar": Uses the signal bar's high price as the reference price.
 - "Low_SignalBar": Uses the signal bar's low price as the reference price.
 - "Median_SignalBar": Uses the average of the signal bar's high and low prices as the reference price.
 - "Typical_SignalBar": Uses the average of the signal bar's high, low, and closing prices as the reference price.
 - "Weighted_SignalBar": Uses the weighted average of the signal bar's high, low, and closing prices as the reference price.
- Row 6:



- "Order: Type": Selects the order type.
 - MKT: Market order.
 - STP: Pending Stop order.
 - SLM: Pending Stop-Limit order.
 - LMT: Pending Limit order.
 - MIT: Pending Market-If-Touched order.



- "Reference Price: Offset Value": The offset (from the reference price) for the **Captain Optimus Strong v2** system to calculate the actual order price. The offset is measured in Tick.

Example: Consider a Buy order with offset = 2 ticks.

- Order type = LMT/MIT: actual order price is 2 ticks BELOW the reference price.
- Order type = SLM/STP: actual order price is 2 ticks ABOVE the reference price.

Additionally, a negative offset can be used, as explained in section **5. Remaining parameters in the General section**.

- Note:
 - When using the "MKT" (Market Order) type, the system will automatically ignore the functions of both "Reference Price" and "Reference Price: Offset Value".
 - Conversely, when using order types other than "MKT", the system will activate this function to determine the position of the pending order based on the Reference Price and the Offset Value relative to the close price of the signal bar.

- Row 7:

Select ATM strategies for the system.

- Note: This area is only for selecting ATM strategies for the system, not for editing them. Refer to section 3.2 for editing.

- Row 8:

Selects the trading account for Captain Optimus Strong v2.

- Row 9:

"ANALYZE" button: Opens the Captain Optimus Strong v2 backtest results.

1.2 Strategy Setup Window

Clicking the "**Captain Optimus Strong v2**" button on the Control Panel opens the **Strategy Setup Window**.

The screenshot shows the "Captain Optimus Strong v2" window with the following sections:

- Indicators:** A search bar with "Start typing to search" and a "Clear" button. Below it is a list of indicators: ADL, ADX, ADXR, APZ, Aroon, AroonOscillator, ATR, and BarTimer.
- Entry Configured:** A section titled "Entry Configured" showing "Solar Wave by ninZa.co (NQ 09-26 (1 Minute))".
- Exit Configured:** A section titled "Exit Configured" showing "Mode: Consensus Ended - Indicator - New Hit Bar" and "Min Consensus (Bars): 3".
- Properties:** A section titled "Properties" with various settings: Input (Close), Offset: Multiplier Trend (2), Offset: Multiplier Stop (4), Offset: ninZaATR Period (100), Reference Price: Period (2), Reference Price: Close Weight (1), Slowdown Scan (Bars) (5), Weak-Weak Split (Bars) (10), Pullback: Early (checked), Pullback: Split (Bars) (10), Plot (Signal: Trend), Value: Bullish (= 1), and Value: Bearish (= -1).
- Signal Bar Condition:** A section titled "Signal Bar Condition" with settings: Bar Direction: Buy (Any), Bar Direction: Sell (Any), Bar Min (0), and Bar Max (10).

At the bottom of the window are buttons for "Generate Strategy", "Cancel", and "OK".

The Strategy Setup Window consists of the following main sections:

- **Indicators:** Displays the available indicators that can be used as signal sources for the system.


The screenshot shows the "Indicators" section with a search bar containing "solar" and a "Clear" button. Below the search bar, the following indicators are listed:

- ninZaSolarWave
- RenkoKings_SolarWaveRK

You can search for an indicator using the Search box. A trading strategy may use one or multiple indicators, depending on your trading logic.

Once an indicator is selected, add it to either Entry Configured or Exit Configured using one of the following methods:


- Entry Configured: Double-click the indicator, or select it and click **Add** in the Entry Configured section to configure entry signals.
- Exit Configured: Press Ctrl while double-clicking the indicator, or select it and click **Add** in the Exit Configured section to configure exit signals.
- **Entry Configured:** Displays and stores the indicators configured as signal sources for the Entry Module.



After an indicator is added to Entry Configured, selecting it displays its corresponding settings in the Properties section for further configuration.

This section provides a clear overview of which signals are currently being used by the Entry Module to generate entry orders.

- **Exit Configured:** Displays, configures, and stores the indicators used as signal sources for the Exit Module.



After an indicator is added to **Exit Configured**, selecting it displays its corresponding settings in the **Properties** section for further configuration.

This section provides a clear overview of which signals are currently being used by the Exit Module to generate exit orders.

- **Mode:** Selects how the system processes Exit signals. The following modes are available:
 - **Consensus Ended:** Exits the position when the consensus condition ends.

- **Indicator:** Exits the position based on the configured indicator signal.
 - **Both:** Exits the position when either the Consensus Ended or Indicator condition is met.
 - **Disabled:** Disables the Auto Exit function.
- **Min Consensus (Bars):** Specifies the minimum number of consecutive bars for which the Exit consensus condition must remain active before the system confirms an exit signal when Mode is set to Consensus Ended.

Example:

If **Min Consensus (Bars)** is set to **3**, the consensus background (green or pink) must remain visible for at least 3 consecutive bars before the system triggers an exit. If the background appears for only **1 or 2 bars** and then disappears, the system will not treat it as a valid exit signal.


Why is this important?

Some trading strategies may generate signals that last for only a single bar. Without this confirmation mechanism, the system could enter and exit a position on the same bar.

The Min Consensus (Bars) parameter helps prevent this by ensuring that the consensus background remains active for the required number of consecutive bars before an exit is triggered.

- **Properties:** Displays the detailed settings for the currently selected indicator, including:
 - Configuring the indicator's parameters.
 - Selecting the input data source (e.g., Close, Open, High, or Low).
 - Selecting the Plot or Signal that Captain Optimus Strong v2 will read.
 - Defining the encoded values for Bullish and Bearish signals.

- Configuring the comparison operator used to evaluate the signal, including =, >,




The operators in the Properties section allow the system to evaluate signals using more specific conditions rather than simply reading a fixed signal value. Among these operators, **start** and **end** are key enhancements introduced in Captain Optimus Strong v2, allowing the system to detect precisely when a signal state begins and when it ends.


Example:

Suppose Plot is set to **Signal: Trend**. The system will read this plot and determine the Bullish and Bearish states according to the configuration below.

- Start/End with n/a




- If **Bullish Value** is set to start n/a or end n/a, the system treats the beginning or end of a period in which the Signal: Trend plot has no value (N/A) as a Bullish signal.
- If **Bearish Value** is set to start n/a or end n/a, the system treats the beginning or end of a period in which the Signal: Trend plot has no value (N/A) as a Bearish signal.
- Start/End with a specific value



- If **Bullish Value** is set to **start 1** or **end 1**, the system treats the beginning or end of a period in which the Signal: Trend plot has a value of 1 as a Bullish signal.

- If **Bearish Value** is set to **start -1** or **end -1**, the system treats the beginning or end of a period in which the Signal: Trend plot has a value of -1 as a Bearish signal.
- Note: If Bullish Value and Bearish Value are configured with the same start or end operator and the same value (for example, n/a, 1, or -1), both the Bullish and Bearish conditions may be considered valid for the same plot value.
- If the strategy does not include any additional directional signals, the system gives priority to the Bullish signal because it is evaluated first. Since the system cannot open both Long and Short positions simultaneously, only the Bullish signal will be executed.
- If the strategy includes additional directional signals, the system processes both conditions according to the configured signal consensus logic.
- **Template Indicator Input:** Used to save and reuse indicator input configurations.



Template Indicator Input allows you to save the selected indicator along with its associated configuration, so it can be reloaded later for another strategy or trading session.

Introduced in Captain Optimus Strong v2, this feature reduces manual configuration time, minimizes setup errors, and ensures that completed indicator workflows can be reused consistently.

- **Signal Bar Condition:** Used to configure the conditions for identifying the Signal Bar in the Entry Module.

The Signal Bar is the bar used by the system to confirm the timing of an entry after the configured entry conditions have been satisfied.

Signal Bar Condition	
Bar Direction: Buy	Up
Bar Direction: Sell	Down
Bar Min	0
Bar Max	10

The main settings include:

- **Bar Direction: Buy:** Specifies the required bar direction for a **Buy** signal.
- **Bar Direction: Sell:** Specifies the required bar direction for a **Sell** signal.
- **Bar Min:** Specifies the minimum number of bars after a signal is generated before the system begins searching for a Signal Bar.
- **Bar Max:** Specifies the maximum number of bars after a signal is generated during which the system is allowed to search for a Signal Bar.

Available Bar Direction options:


- **Any:** Accepts bars of any direction.
- **Up:** Accepts only bullish bars.
- **Down:** Accepts only bearish bars.

Example: If **Bar Min = 0** and **Bar Max = 10**, the system searches for a Signal Bar from the current bar up to 10 bars after the signal is generated, subject to the selected Bar Direction.

- **Generate Strategy:** Generates a strategy from the current configuration.

After completing the configuration in the Strategy Setup Window, including Entry Configured, Exit Configured, Properties, and Signal Bar Condition, click Generate Strategy to create the strategy.

Once the generation process is complete, the system displays a confirmation message along with the file path where the strategy has been saved. You can use the default location or choose a different save location if needed.



The generated strategy can be used for 2 primary purposes:

- **Backtesting in NinjaTrader Strategy Analyzer:** Evaluate the strategy using NinjaTrader's standard backtesting environment.

Fully automated trading: Deploy the strategy for fully automated trade execution, reducing the need for manual intervention on the chart.

Note: Fully automated trading: Deploy the strategy for fully automated trade execution, reducing the need for manual intervention on the chart.

This helps ensure that the generated strategy accurately reflects the intended trading logic and avoids unexpected behavior caused by missing conditions, incorrect signal configurations, or unapplied settings.

2. Execution workflow

Captain Optimus Strong v2 operates through 3 core modules:

- **Entry Module:** Processes the conditions required to enter a trade.
- **Exit Module:** Processes the conditions required to exit a position.
- **Management Module:** Manages risk, trading status, and operational limits.

These three modules work together throughout the trade execution process. An Entry signal is executed only when the entry conditions are satisfied and the Management Module

permits trading. Once a position has been opened, the Exit Module and Management Module continue monitoring the trade to determine when to exit the position, cancel pending orders, suspend trading, or protect the account according to the configured settings.

This section explains how Captain Optimus Strong v2 uses these configurations to manage and execute the trading workflow.

2.1 Entry Module

The **Entry Module** is responsible for managing the trade entry process in Captain Optimus Strong v2.

After the input indicators have been configured in Entry Configured, the system reads the selected Plot or Signal defined in Properties. It then processes the input signals, checks for signal overlap, identifies the Signal Bar, verifies the remaining entry conditions, and finally submits the order according to the configured settings.

- **Entry Signal Detection**

Each indicator is configured through the following components in the Properties section:

- The Plot or Signal to be read by the system.
- The encoded values representing Bullish and Bearish signals.
- The condition operator, such as =, >, <, >=, <=, !=, between (btw.), start, and end.

When an indicator satisfies the configured conditions, the system recognizes it as a valid Bullish or Bearish signal.

However, when a strategy uses multiple input indicators, Captain Optimus Strong v2 does not evaluate each signal independently. Instead, it verifies whether the signals confirm the same market direction within the same time window. This forms the basis of the Consensus Signal Logic.

- **Consensus Signal Logic** enables the system to evaluate multiple input signals simultaneously.

Rather than relying on a single indicator, Captain Optimus Strong v2 monitors the state of all indicators configured in Entry Configured. When multiple signals satisfy their configured conditions within the same time window and point to the same market direction, the system treats them as a signal consensus.



When multiple signals are simultaneously valid in the same direction, the system establishes a consensus state:

- If multiple **Bullish** signals are valid simultaneously, the system establishes a **Bullish Consensus**.
- If multiple **Bearish** signals are valid simultaneously, the system establishes a **Bearish Consensus**.
- If the signals no longer remain valid in the same direction, the corresponding consensus state ends.

Example: Suppose the strategy uses two indicators as Entry signals:

- **Indicator A** generates a Bullish signal.
- **Indicator B** generates a Bullish signal.

When both Indicator A and Indicator B satisfy their Bullish conditions at the same time, the system establishes a Bullish Consensus. The Entry Module can then proceed to evaluate the Signal Bar Condition to determine whether a valid entry opportunity exists.

If either indicator no longer maintains its Bullish state, the Bullish Consensus ends.

This mechanism serves two primary purposes:

- It enables the Entry Module to confirm trade entries when multiple signal conditions are satisfied simultaneously.
- It enables the Exit Module to exit positions when the consensus state ends.

- **Signal Bar Condition**

After the input signals have been confirmed, the system uses the Signal Bar Condition to determine which bar qualifies as a valid Signal Bar.

The Bar Direction: Buy, Bar Direction: Sell, Bar Min, and Bar Max settings allow you to control when the system is permitted to enter a trade after a signal has been generated.

Example:

If **Bar Min = 0** and **Bar Max = 10**, the system searches for a Signal Bar from the current bar up to 10 bars after the signal is generated.

If Bar Direction: Buy = Up, a Buy signal is confirmed only if the Signal Bar found within the search window is a bullish bar.

This allows Captain Optimus Strong v2 to wait for a more suitable confirmation bar instead of entering a trade immediately after a signal is generated, making trade execution more consistent with the strategy's intended logic.

- **Order Routing**

Once a valid Entry signal has been confirmed, the system submits an order according to the configuration on the Control Panel. The following settings determine how the order is submitted:

- Order Type
- Reference Price
- Reference Price: Offset Value
- Order: SLM Offset
- Quantity
- ATM Strategy
- Account

If Order Type is set to MKT, the system submits a Market Order immediately and ignores the Reference Price and Reference Price: Offset Value settings.

If Order Type is set to LMT, MIT, STP, or SLM, the system first calculates the order price

based on the selected Reference Price and Reference Price: Offset Value, and then submits the pending order.

An Entry signal is considered valid only when all of the following conditions are satisfied

- The input indicator generates a Bullish or Bearish signal that matches the configured criteria.
- The configured condition operator in Properties is satisfied.
- The Signal Bar Condition is satisfied.
- The corresponding LONG or SHORT direction is enabled on the Control Panel.
- The current trading session permits new entries.
- Trade Behavior does not block new orders.
- Money Management and the configured protection mechanisms do not require trading to be suspended.


2.2 Exit Module

Exit Module is responsible for managing the trade exit process in Captain Optimus Strong v2.

It enables the system to respond when the trading conditions are no longer favorable and automatically manages the timing of trade exits according to the configured strategy logic.

- **Integrating ATM Strategy**


When starting Captain Optimus Strong v2, we provide a note containing important information for setting up your ATM strategy. Please read this table carefully.



The ATM Strategy section on the Control Panel is used only to select a preconfigured ATM Strategy.

Creating, modifying, or deleting an ATM Strategy must be performed in NinjaTrader's Chart Trader.

After making any changes to an ATM Strategy in Chart Trader, refresh the chart so that Captain Optimus Strong v2 can synchronize the updated list of available ATM Strategies.



After an Entry order is filled, the ATM Strategy can manage the following trade components:

- Stop-Loss
- Take-Profit
- Breakeven
- Trailing Stop, nếu được thiết lập trong ATM

There are two primary modes:

- **ATM = None:** The user does not use the ATM order management mechanism.
 - If "**None ATM**" Invalidates "**Wait Until Flat**" is enabled, the system closes the current open position when a new signal appears and submits a new order according to the configured settings.
 - This is the default system setting.
 - If "**None ATM**" Invalidates "**Wait Until Flat**" is disabled, open positions must be closed manually, and the system will only submit a new order after all previous positions have been closed.
- **ATM = Custom:** The user uses the order management mechanism provided by an ATM Strategy.

- Stop-Loss and Take-Profit orders are automatically placed according to the ATM configuration.
 - The ATM Strategy manages the entire lifecycle of the trade until the position is closed.
 - If **Wait Until Flat** is enabled, the system only submits a new order after the previous trade has been completed according to the ATM rules.
 - If **Wait Until Flat** is disabled, the system closes the current position when a new signal appears and submits a new order according to the configured settings.
- **Exit by Condition**

Exit by Condition is a mechanism that allows Captain Optimus Strong v2 to automatically close positions when an Exit condition is triggered.

The Auto Exit mechanism is configured in the Exit Configured section of the Strategy Setup Window. In other words, Exit Configured is where users select and configure exit signal sources, while Exit by Condition is the mechanism used by the system to manage position exits based on those configurations.

The available options in Exit by Condition include:

- **Consensus Ended:** Exits the position when the consensus state ends.
 - **Indicator:** Exits the position based on the configured indicator signal.
 - **Both:** Combines both Consensus Ended and Indicator exit conditions.
 - **Disabled:** Disables the Auto Exit mechanism.
- **Exit by Management Module**

In addition to ATM Strategy and Exit by Condition, several mechanisms within the Management Module can directly affect the position exit process.

Within the scope of the Exit Module, the Management Module features related to exits include:

- **"End Sessions Auto Close: Enabled":** Automatically closes open positions when the configured trading session ends, provided that this feature and Session Management are enabled.
- **Money Management:** The system can close positions when predefined money management limits are reached, such as Max Daily Profit or Max Daily Loss,

depending on the selected management mode.

These mechanisms do not generate Exit signals from indicators. Instead, they ensure that positions are closed when required, such as when a trading session ends or when the account reaches a configured money management threshold.

ATM Strategy, Exit by Condition, and Exit by Management Module serve different roles in the exit process:

- ATM Strategy: Manages orders after a position is opened, including Stop-Loss, Profit Target, and other order management rules configured in NinjaTrader.
- Exit by Condition: Handles position exits based on exit signals or conditions configured in Captain Optimus Strong v2.
- Exit by Management Module: Handles position closures according to configured management rules.

This means a position can be closed by the ATM Strategy when a Stop-Loss or Profit Target is triggered. However, the position can also be closed by Exit by Condition or Exit by Management Module if an exit condition occurs before the ATM reaches its Stop-Loss or Profit Target. The position will be closed based on whichever valid exit condition is triggered first.

2.3 Management Module

Management Module is responsible for controlling the operational process of Captain Optimus Strong v2.

The Management Module consists of four main control groups:

- Sessions Management
- Money Management
- Three-Layer Protection System
- Trade Behavior

This module does not generate Entry or Exit signals. Instead, it determines whether the system is allowed to continue trading. The Management Module can affect the entire trading process, including before an order is submitted, while a position is open, and after a trade is completed.

2.3.1 Sessions Management

Configuration Item	Value
Sessions Management: Enabled	☒
Time #1: Enabled	☒
Time #1: Start	190000
Time #1: Duration	40000
Time #2: Enabled	☒
Time #2: Start	30000
Time #2: Duration	40000
Time #3: Enabled	☒
Time #3: Start	80000
Time #3: Duration	40000
End Sessions Auto Close: Enabled	☒

Sessions Management is a configuration group used to control the operating time of the system.

When **Session Management: Enabled** is activated, **Captain Optimus Strong v2** only searches for signals and executes trades within the configured time windows.


- **Time #1: Enable:** Activating this ensures that the Captain Optimus Strong v2 system only enters orders during the selected time frame.
- **Time #1: Start (190000)** → 19 indicates the hour, 00 for minutes, and 00 for seconds.
- **Time #1: Duration:** Setting this parameter to 40000 indicates that the Captain Optimus Strong v2 system will search for and execute transactions from 19:00 ET to 23:00 ET. → Time #1: Duration = 4 hours.
- **Time #2: Enable:** Activating this ensures that the Captain Optimus Strong v2 system only enters orders during the selected time frame.
- **Time #2: Start (30000)** → 3 indicates the hour, 00 for minutes, and 00 for seconds.
- **Time #2: Duration:** Setting this parameter to 40000 indicates that the Captain Optimus Strong v2 system will search for and execute transactions from 3:00 ET to 7:00 ET → Time #2: Duration = 4 hours.
- **"Time #3: Enable:** Activating this ensures that the Captain Optimus Strong v2 system only enters orders during the selected time frame.
- **"End Sessions Auto Close: Enabled":** Activating this option allows Captain Optimus Strong v2 to automatically close all open positions when a configured trading session ends.

A trading session refers to any enabled time window (Time #1, Time #2, or Time #3). When one of these time windows is enabled, the system calculates the session end time based on the configured Start time and Duration. When the configured Duration

expires, Captain Optimus Strong v2 automatically closes all open positions if End Sessions Auto Close: Enabled is activated.

Note: If Sessions Management: Enabled is activated but none of the time windows (Time #1, Time #2, or Time #3) are enabled, End Sessions Auto Close will not have a valid trading session to process and will remain inactive.

2.3.2 Money Management




Money Management	
Enabled	☒
Mode	Based on Account Realized PnL
Max Daily Profit	5000
Max Daily Loss	5000

Money Management is a configuration group used to control daily profit and loss limits.

When activated, the system will automatically monitor and enforce daily profit/loss limits based on the rules you set.

We provide two modes within this feature:



Money Management	
Enabled	☒
Mode	Based on Account Realized PnL
Max Daily Profit	
Max Daily Loss	

Based on Account Realized PnL
Based on Account Realized PnL
Based on Cumulative PnL

- "Based on Account Realized PnL": If this mode is enabled, the Captain Optimus Strong will flatten the current account once the account's Realized PnL reaches the Daily Profit or Daily Loss threshold.
- "Based on Cumulative PnL": If this mode is enabled, Captain Optimus Strong will flatten all current positions on the account when the Cumulative PnL of Captain Optimus Strong alone reaches the established Daily Profit or Daily Loss threshold.
- Note: When you select the Based on Cumulative PnL feature, the system will suggest the End Trading Day Reset Cum. PnL option. This feature allows the system to reset the daily profit/loss management threshold to zero when a new trading day begins, if enabled.

2.3.3 Three-Layer Operational Protection

Captain Optimus Strong v2 introduces a new operational protection mechanism compared to Version 1, designed to reduce situations where trade execution conditions become unfavorable after a signal has been generated.

This mechanism consists of three control layers, each designed for a different stage of the execution process:

- **Skip Entry:** Controls execution conditions before the system submits an order to the market.
- **Pending Order Control:** Manages pending orders that have been submitted but not yet filled.
- **Stop Auto Entry:** Controls whether the system continues entering trades after a consecutive losing streak.

These three protection layers do not generate new trading signals. Instead, they act as validation and limitation mechanisms that control the system's operation. The goal is to ensure that Captain Optimus Strong v2 does not keep pending orders active for too long, does not enter trades under unfavorable execution conditions, and does not continue trading when the strategy is no longer performing effectively.

- **Skip Entry** is a protection mechanism for the entry process. When enabled, the system can ignore an Entry signal if the execution conditions are no longer suitable.

Skip Entry: Enabled	☐
Skip Entry: Slippage (Ticks)	10
Skip Entry: Spread (Ticks)	10

- "Skip Entry: Enabled": Enables or disables the Skip Entry mechanism.
- "Skip Entry: Slippage (Ticks)": Defines the maximum allowed distance between the Signal Bar closing price and the actual Bid/Ask price at the time the order is submitted.

If the actual distance exceeds the configured value, the system ignores the signal and does not submit the order.

Example: If Skip Entry: Slippage (Ticks) = 10 and Skip Entry: Enabled is activated:

- If a Buy signal occurs and the distance between the Signal Bar closing price and the Ask price exceeds 10 ticks, the system will not submit an order for this signal.
- If a Sell signal occurs and the distance between the Signal Bar closing price and the Bid price exceeds 10 ticks, the system will not submit an order for this signal.
- "Skip Entry: Spread (Ticks)": Defines the maximum allowed distance between the actual Bid and Ask prices at the time the order is submitted.

If the actual spread exceeds the configured value, the system ignores the signal and does not submit the order.

Example: If Skip Entry: Spread (Ticks) = 10 and Skip Entry: Enabled is activated, the system will not submit an order if the difference between the Bid and Ask prices exceeds 10 ticks when the signal occurs.

The purpose of Skip Entry is to prevent the system from entering trades under unfavorable market conditions, especially during rapid price movements, widened spreads, or unstable liquidity conditions.

- **Pending Order Control**

Cancel Pending Order: Mode	All
Cancel Pending Order: Bars	9999
Cancel Pending Order: Second	9999
Cancel Pending Order: Ticks	9999

For pending order types, the system can automatically cancel pending orders when the original execution conditions are no longer valid.

- "Cancel Pending Order: Mode": Allows users to select the cancellation mode for existing pending orders on the chart. There are four available modes:

- "Cancel Pending Order: Bars": Cancels a pending order based on the number of bars elapsed since the order was submitted.

Example: If Cancel Pending Order: Bars = 100, the system will cancel the pending order if it has not been filled after 100 bars.

- "Cancel Pending Order: Second": Cancels a pending order based on the number of seconds elapsed since the order was submitted.

Example: If Cancel Pending Order: Second = 100, the system will cancel the pending order if it has not been filled after 100 seconds

- "Cancel Pending Order: Ticks": Cancels a pending order based on the number of ticks the market has moved from the order submission price.

Example: If Cancel Pending Order: Ticks = 100, the system will cancel the pending order if the market moves more than 100 ticks away from the price level where the order was submitted and the order has not been filled.

The purpose of this mechanism is to prevent pending orders from remaining active for too long after the original signal has lost validity or when the market has moved away from the intended trading area.

- **Stop Auto Entry** is a protection mechanism that prevents the system from submitting new orders when the number of consecutive losing trades reaches the configured limit.



A screenshot of a settings panel for 'Stop Auto Entry'. It contains two rows: 'Stop Auto Entry: Enabled' with a checked checkbox, and 'Stop Auto Entry: Loss Streak' with a numeric input field containing the value '5'.

- "Stop Auto Entry: Enabled": Enables or disables the Stop Auto Entry mechanism.
- "Stop Auto Entry: Loss Streak": Defines the maximum number of consecutive losing trades allowed before the system stops submitting new orders.

If the number of consecutive losing trades reaches the configured Stop Auto Entry: Loss Streak value and Stop Auto Entry: Enabled is activated, the system automatically disables the "LONG" / "SHORT" buttons on the Control Panel.


When the "LONG" / "SHORT" buttons are disabled, Captain Optimus Strong v2 will no longer submit new orders, even if new Entry signals are generated.

This mechanism is reset at the start of a new trading day. After the reset, users can manually enable the "LONG" / "SHORT" buttons again if they want to allow the system to resume trading.

Example: If Stop Auto Entry: Loss Streak = 5 and Stop Auto Entry: Enabled is activated, the system automatically disables the "LONG" / "SHORT" buttons after recording 5 consecutive losing trades.

The purpose of Stop Auto Entry is to prevent continued trading after a consecutive losing streak, reduce operational risk, and avoid allowing the system to continue entering trades during periods when the strategy is underperforming.

2.3.4 Trade Behavior



A screenshot of a settings panel titled 'Trade Behavior'. It contains four rows: 'Wait Until Flat' with a checked checkbox, '*None ATM* Invalidates "Wait Until Flat"' with a checked checkbox, 'Multiple Entries Per Direction: Enabled' with an unchecked checkbox, and 'Multiple Entries Per Direction: Max' with a numeric input field containing the value '2'.

Trade Behavior manages trading states and the conditions that allow new entries.

- **Wait Until Flat**

When this feature is enabled, the system only allows new entries when there are no open positions. This helps prevent multiple overlapping positions and ensures that each signal generates only one trade.

- **"None ATM" Invalidates "Wait Until Flat"**

When this feature is enabled and the ATM Strategy is set to None, the Wait Until Flat rule becomes inactive. When a new signal appears, the system automatically closes the current position and submits a new order according to the configured settings.

- **Multiple Entries Per Direction: Enabled**

When this feature is enabled, Captain Optimus Strong v2 allows multiple entries in the same direction according to the limit configured in **Multiple Entries Per Direction: Max**.

If this feature is disabled, the system restricts additional entries in the same direction according to the default Trade Behavior logic.


- **"Multiple Entries Per Direction: Max"**: This setting defines the maximum number of entries allowed in the same direction.

Example: If Multiple Entries Per Direction: Max = 2 and Multiple Entries Per Direction: Enabled is activated, the system can execute up to 2 consecutive entries in the same direction.

After reaching this limit, new signals in the same direction will no longer be processed until the entry condition is reset according to the system's operational logic. This allows users to control the frequency of entries in the same direction and prevents the system from continuously adding positions during the same market phase.

2.4 Generate Strategy & Fully Auto Operation

Generate Strategy is the process of converting the strategy configuration in Captain Optimus Strong v2 into a Strategy that can be used in NinjaTrader.




After the user completes the configuration of Entry Configured, Exit Configured, Properties, Signal Bar Condition, and other related settings, the "Generate Strategy" button creates a Strategy based on the configured logic.

This is a new feature introduced in Captain Optimus Strong v2. It not only supports direct chart-based operation through the Control Panel, but also allows users to convert their configured workflow into a Strategy for fully automated operation and strategy evaluation within the NinjaTrader environment.

The system can be understood through 2 operational modes:

- **Captain Control Panel Mode:** Users operate directly on the chart through the Captain Optimus Strong v2 Control Panel, including enabling/disabling the "LONG" / "SHORT" buttons, selecting Quantity, Order Type, ATM, and Account.
- **Generated Strategy Mode:** Users generate a Strategy from the configured settings and then use this Strategy within NinjaTrader for fully automated operation or backtesting in Strategy Analyzer.



Once the Strategy generation process is complete, the system displays a confirmation message along with the file path where the Strategy file is saved. Users can use the default save location or choose a different location if they do not want to save the file in the suggested directory.

2.5. Backtesting

Backtesting in Captain Optimus Strong v2 allows users to validate strategy logic before deploying it in live trading.

In Version 1, the system already supported Quick Backtest through the "ANALYZE" button on the Control Panel.

In Version 2, Captain Optimus Strong introduces an enhanced Generate Strategy capability, allowing users to evaluate their strategy using NinjaTrader Strategy Analyzer with a more comprehensive testing standard before deploying it for fully automated operation.

2.6 Overview of execution flow

The overall execution flow of Captain Optimus Strong v2 is a sequential processing workflow, which can be described as follows:

Indicator Input: Select an indicator or signal source and configure the conditions used as input data for the system.



Signal Decoding: Reads the encoded signals from the indicator to determine the relevant trading states, including Buy, Sell, Exit, or other configured conditions.



Management Filter: Checks management conditions such as Session Management, daily profit/loss limits, loss streak, trade behavior, and current position status before submitting orders.



Entry Module: If the signal is valid and all management conditions allow trading, the Entry Module confirms the entry action.



Order Routing: The system submits orders to the market according to the selected order type, including Market, Limit, Stop, Stop-Limit, or Market-If-Touched, based on the configured settings.



Position Monitoring: After an order is filled, the system monitors the position status, new signals, exit signals, and related management conditions.



Exit Module / ATM: The position can be closed through Auto Exit, exit signals, ATM Strategy, or other configured exit mechanisms.



Management Control: Checks operational limits and conditions such as Daily Profit, Daily Loss, Loss Streak, the number of entries in each direction, or session-ending conditions.



Trade Completion / Stop Trading Control: When a trade is completed, the system determines whether new trading is still allowed or whether automated trading should be stopped according to the configured protection settings.

3. Strategy configuration workflow

This section guides users through the process of configuring a strategy, performing Quick Backtest, and operating directly with Captain Optimus Strong v2. The Generate Strategy process and backtesting through Strategy Analyzer will be explained in detail in our upcoming video tutorials.

3.1. Open strategy setup window

Step 1: Click the "Captain Optimus Strong v2" button on the Control Panel.

Step 2: The system opens the Strategy Setup Window.

3.2. Add indicator input

Step 1: Search for the indicator you want to use in the Indicators section.

Step 2: Add the indicator to the configuration:

- Double-click the indicator or click Add in Entry Configured to add it as an Entry signal.
- Hold Ctrl and click the indicator, or click Add in Exit Configured to add it as an Exit signal.

Step 3: Select the added indicator in Entry Configured or Exit Configured.

Step 4: Configure the indicator parameters in the Properties section.

3.3. Configure Entry / Exit

Step 1: Select the Plot / Signal that the system will read.

Step 2: Configure the Bullish / Bearish signal values.

Step 3: Select the appropriate condition operator.

Step 4: Configure Exit Configured if the strategy uses Auto Exit.

Step 5: Configure Signal Bar Condition for the Entry Module.

Step 6: Click Apply or OK to activate the configured signals.

Step 7: Verify the signals on the chart before live operation or generating a Strategy.

3.4. Activate the Control Panel

After completing the signal configuration, users should review the main settings before enabling automated trading:

Step 1: Select the Account to be used.

Step 2: Select the appropriate Quantity.

Step 3: Select the desired Order Type.

Step 4: Configure Reference Price and Offset Value if using pending orders.

Step 5: Select an ATM Strategy if using ATM to manage Stop-Loss / Take-Profit.

Step 6: Review the Management settings in the indicator window.

Step 7: Enable LONG / SHORT only after all configurations have been reviewed.

Important note:

Before completing and validating the full configuration, it is recommended to use a demo account to avoid unintended risks on a live account.

When the "**LONG**" / "**SHORT**" buttons are enabled, the system activates automated operation. Users should ensure that all configurations, including Indicator Input, Entry, Exit, Management, and other related settings, have been fully reviewed and correctly applied to prevent unintended order execution.

3.5. Quick Backtest with ANALYZE

Quick Backtest is designed for quickly validating a strategy directly on the chart.

Step 1: Set the Days to Load value in Data Series.

Step 2: Verify the signal accuracy after completing the configuration.

Step 3: Select the account to be used on the Control Panel, either a Demo Account or Sim Account.

Step 4: Enable LONG / SHORT on the Control Panel.

Step 5: Select the exit management method in the ATM Strategy section. There are two available options:


- ATM = None: The position is closed when a new signal appears, and a new position is opened according to the new signal.
- ATM = Custom: The system requires Stop and Target settings. The position is closed only when either the Stop or Target is reached. After the position returns to Flat, the system will evaluate the next available signal.

Step 6: Click ANALYZE on the Control Panel.

Step 7: Review the backtest result table.

Note: Quick Backtest is intended for fast validation of strategy logic and preliminary performance evaluation. For more accurate performance analysis, users can perform a full strategy backtest through Strategy Analyzer.

4. Remaining parameters in the General section



General	
Auto Exit: Consensus Ended	✓
Auto Exit: Indicator	✓
Auto Exit: New Hit Bar	✓
# Of Signal Per Direction	9999
Price Step: Unit	Tick
Order: Type	MKT
Order: SLM Offset	0
Reference Price	Close_SignalBar
Reference Price: Offset Value	2
Quantity: Option 1	1
Quantity: Option 2	2
Quantity: Option 3	3
Quantity: Option 4	4
Round-Turn Commission (Ticks)	0
Skip Entry: Enabled	☐
Skip Entry: Slippage (Ticks)	10
Skip Entry: Spread (Ticks)	10
Stop Auto Entry: Enabled	☐
Stop Auto Entry: Loss Streak	5
Cancel Pending Order: Mode	All
Cancel Pending Order: Bars	9999
Cancel Pending Order: Second	9999
Cancel Pending Order: Ticks	9999
Data Series Behind: Enabled	☐
Data Series Behind: Type	Tick
Data Series Behind: Value	1
Connection Lost Message: Enabled	✓
Screen DPI	100

- "Price Step: Unit": Select between "Tick" or "ForexPip".
- "Order: SLM Offset": The offset of Stop-Limit orders.
- "Data Series Behind: Enabled": This mode must be enabled if you are using indicators that rely on a secondary data series for calculations (e.g., Imbalance Profile Lidar, Imbalance Volume Sensor, SpaceGPS Satellite, Cumulative Delta, Volume Delta, etc.).
 - "Data Series Behind: Type": Choose the type of secondary data series used for calculations by indicators as input data for Captain Optimus Strong, such as Tick, Minute, Range, Volume, or Second.

- "Data Series Behind: Value": The value of the secondary data series that the indicators require for their calculations as input data for Captain Optimus Strong.
 - Most indicators require a secondary data series of 1 Tick for calculations, so you can use the default setting for this mode.