


Captain Optimus Strong Trader Manual

1. Overview


1.1. Key features of Captain Optimus Strong

- The system generates signals based on the analysis of any indicators you choose (there is no limit to the number of indicators you can select). In addition to indicators, you can use other systems to integrate into this system for analysis and signal generation.
- It allows automatic entry into trades when the system's signal appears, with an integrated ATM strategy.
- Traders can set a profit/loss threshold to stop trading for the day.
- It allows backtesting of the strategy signals you create.

1.2. Overview and components of the Control Panel




- Row 1
"Captain Optimus Strong" button: Click to select the input indicators for the system.
- Row 2
 - "CANCEL" button: Click to cancel all pending orders.
 - "CLOSE" button: Click to close all positions and cancel all active orders.
- Row 3
 - "LONG" button: When activated, the system will automatically execute a Buy order when a bullish signal appears.
 - "SHORT" button: When activated, the system will automatically execute a Sell order when a bearish signal appears.
- Row 4:
Select the number of contracts to trade. You can adjust the number of contracts displayed on the control panel in the "Quantity" section under "General".




- Row 5:

"Reference Price": The original price from which we apply the offset.




- "Close_SignalBar": Uses the close price of the signal bar as the reference price.
- "Open_SignalBar": Uses the open price of the signal bar as the reference price.
- "High_SignalBar": Uses the high price of the signal bar as the reference price.
- "Low_SignalBar": Uses the low price of the signal bar as the reference price.
- "Median_SignalBar": Uses the average of the high and low prices of the signal bar as the reference price.
- "Typical_SignalBar": Uses the average of the high, low, and close prices of the signal bar as the reference price.
- "Weighted_SignalBar": Uses the weighted average of the close, low, and high prices of the signal bar as the reference price.



- Row 6:

- "Order: Type": Select among many types of order:

- MKT: Market order.
- STP: Pending Stop order.
- SLM: Pending Stop-Limit order.
- LMT: Pending Limit order.
- MIT: Pending Market-If-Touched order.




- "Reference Price: Offset Value": The offset (from the reference price) for the Captain Optimus Strong system to calculate the actual order price. The offset is measured in Tick.

Example: Consider a Buy order with offset = 2 ticks.

- Order type = LMT/MIT: actual order price is 2 ticks BELOW the reference price.
- Order type = SLM/STP: actual order price is 2 ticks ABOVE the reference price.

Additionally, a negative offset can be used, as explained in section 5.



○ Note:

- When using the "MKT" (Market Order) type, the system will automatically ignore the functions of both "Reference Price" and "Reference Price: Offset Value".
- Conversely, when using order types other than "MKT", the system will activate this function to determine the position of the pending order based on the Reference Price and the Offset Value relative to the close price of the signal bar.

- Row 7: Select ATM strategies for the system.

- Note: This area is only for selecting ATM strategies for the system, not for editing them. Refer to section 3.2 for editing.


- Row 8:

"ANALYZE" button: Click to view the backtest results of Captain Optimus Strong.


2. Installation and activation of the Captain Optimus Strong system

Instructions for installing indicators as input data for the system:

- Step 1: Click the "Captain Optimus Strong" button to add the indicators you want to use as input data for the system.



- Step 2: Select and configure the parameters of the indicators as input data.
 - After clicking the "Captain Optimus Strong" button, a window will appear, as shown in the image below.



- In this window, you can select multiple indicators to use. The selected indicators will be listed in the Configured section, and their configuration parameters will appear in the Properties section. You may use the default settings or customize the parameters of the selected indicators as required.

- Example: As shown in the image below, we have selected the Easy Trend and Ruby River indicators as input data for the system. You can see these two indicators listed in the Configured area. To configure the parameters of a specific indicator, simply click on it in the Configured area. Once selected, the indicator parameters will be displayed in the "Properties" section, where you can make adjustments.

Captain Optimus Strong

Indicators

Start typing to search Clear

- ninZaParabolicSARPro
- ninZaPeriodSequenceMagik
- ninZaPhoenixSqueeze
- ninZaPinocchioBarPro
- ninZaPrevdayCriticalSR
- ninZaPriceFollowing
- ninZaPriceTracker
- ninZaQQEPro
- ninZaQuickDrawing
- ninZaRegularizedEMAPro
- ninZaRenkoStyleTrend
- ninZaRiskRewardMeter
- ninZaRoundNumber
- ninZaRubyRiver
- ninZaSchaffTrendCyclePro
- ninZaSidewayzMA
- ninZaSidewayzRT
- ninZaSidewayzZP
- ninZaSineWMAPro

Configured

- Easy Trend Upgrade by ninZa.co (GC FEB...
- Ruby River by ninZa.co (GC FEB25 (1 Minu...))

add remove up down

Properties

Input: Close

MA Type: EMA

Period: 56

Smoothing: Enabled

Smoothing: Method: EMA

Smoothing: Period: 7

Filter: Enabled

Filter: After Smoot...:

Filter: Multiplier: 0.5

Filter: Unit: ninZaATR

Filter: ninZaATR P...: 100

Signal Quantity Pe...: 3

Signal Split (Bars): 3

Plot: Signal: Trend

Value: Bullish: = 1

Value: Bearish: = -1

Signal Bar Condition

Bar Direction: Buy: Any


Bar Direction: Sell: Any

Bar Min: 0

Bar Max: 10

OK Cancel

- Step 3: Select the signal plot for each indicator chosen as input data for Captain Optimus Strong.
 - In the Properties section, under the "Plot" option, select the signal plot to be used as input for Captain Optimus Strong.




- For indicators that are our products, to determine the appropriate signal type for each purpose, you can refer to the "Dedicated NinjaScript signals" section on the product description page of our websites, such as ninZa.co and Renkokings.com. For indicators from external sources, if you wish to use them, you must have complete information about the "Dedicated NinjaScript signals" of that product to accurately select the signal plot to be used as input for the system.


Signal_Trend: 1 = uptrend, -1 = downtrend

Signal_Pullback: 1 = uptrend pullback, -1 = downtrend pullback, 0 = no pullback

- Example: For the two indicators, EasyTrend and Ruby River, we want to select the trend signal as input. Therefore, we will set the "Plot" option for both indicators to "Signal: Trend" to be used as input for Captain Optimus Strong. Refer to the image below for reference.




- Step 4: Set the conditions to identify the entry candle in the system's automatic order entry mode, in the "Signal Bar Condition" section.




- "Bar Direction: Buy/Sell": Defines the condition for identifying the entry candle.
 - "Any": Any candle after the signal candle.
 - "Up": A Bullish candle following the signal candle.
 - "Down": A Bearish candle following the signal candle.
- "Bar Min - Bar Max": Defines the range for searching the entry candle, from the minimum to the maximum candle, based on the parameters set after the signal candle appears.

- Example: As shown in the image below, with a "Bar Min" value of 3, this means the minimum entry candle will be identified as the third candle after the signal candle (candle 0). With a "Bar Max" value of 10, the maximum entry candle will be the tenth candle after the signal candle. The range between the minimum and maximum candles defines the search area for the entry candle in Captain Optimus Strong.



- Step 5: Click OK to complete the input data setup for Captain Optimus Strong.
- Step 6: After clicking OK, a dialog box will appear, as shown in the image below. At this point, close the dialog box and press F5 to reload the chart.



- After pressing F5, the system interface will appear as shown below, with signals generated from the input data via the selected indicators.



3. Instructions for automatic order entry, order management, and capital management.

3.1. Setting up automatic order entry

After completing the initial setup, to configure Captain Optimus Strong for automatic order entry, follow these steps:


- Step 1: Activate the long / short orders by clicking the "LONG" / "SHORT" buttons, or both buttons simultaneously. When a signal is generated, the system will automatically place an order based on the corresponding buy or sell signal. (Row 3)




- Step 2: Select the number of contracts you wish to trade. (Row 4)
- Step 3: Select the type of order you want to use to enter the market (Row 6).
 - For the MKT order type, you do not need to adjust the parameters in "Reference Price" (Row 5) and "Reference Price: Offset Value" (Row 6).
 - For other order types, based on the price at which you want Captain Optimus Strong to execute the trade, you can adjust "Reference Price" (Row 5) and "Reference Price: Offset Value" (Row 6) according to your needs.

3.2. Integrating ATM Strategy

- When starting Captain Optimus Strong, we provide a note containing important information for setting up your ATM strategy. Please read this table carefully.




- Features related to ATM Strategy Setup: In the General section of the system, there are 2 features: "Wait Until Flat" and "None ATM Ignore Wait Until Flat".




- "Wait Until Flat": When this feature is enabled, the system will maintain the current order as filled at the time you activate the automatic trading mode. The next order will only be executed once the current order ends, either manually stopped or triggered by stop-loss/target.
- "None ATM Ignore Wait Until Flat": When this feature is enabled, and "ATM" is set to "None," the system will exit the current order and enter a new one as soon as a new signal appears, regardless of whether your current position is in a loss or profit. In other words: When the "None ATM Ignore Wait Until Flat" feature is enabled, the "Wait Until Flat" feature will be ignored by the system if "ATM" is set to "None."
- Setting up ATM Strategy:
 - When you select "None" for your ATM strategy setup: The system will automatically enter orders under two conditions.


- Condition 1: When a new signal appears, the system will automatically exit the current order and trigger a new order with the newly appeared signal, regardless of whether the new signal is in the same direction or opposite to the most recent order.




- Condition 2: When you disable the "None ATM Ignore Wait Until Flat" option in General, the system will automatically execute an order based on the first signal after activating the automatic trading feature. This order will only end when you manually stop it, rather than exiting automatically. The system will only open a new order when no active orders remain on the chart.



- When you select "Custom" to set up your own ATM strategy: The system will also enter orders in two cases.




- Case 1: When you have completed the automatic trading setup along with your ATM strategy and enable the "Wait Until Flat" feature in the General section, the system will automatically open a new order based on the new signal. This order will be held until one of the following two goals is reached: stop-loss or take-profit, as defined in your ATM strategy. The system will only open a new order once the previous order has been completed.



- Case 2: When you have completed the automatic trading setup along with your ATM strategy and disable the "Wait Until Flat" feature, the system will close the current order without reaching the stop-loss or take-profit targets defined in your ATM strategy and will automatically open a new order based on the new signal.


3.3. Managing Daily Profit/Loss thresholds

- The Captain Optimus Strong system provides a feature to manage daily profit/loss thresholds. You can enable this feature in the "Money Management" section. This feature helps you control risk and protect profits during trading.




A screenshot of the "Money Management" settings panel. The "Enabled" checkbox is unchecked. The "Mode" dropdown is set to "Based on Account Realized PnL". The "Max Daily Profit" and "Max Daily Loss" input fields are both set to "5000".

- When activated, the system will automatically monitor and enforce daily profit/loss limits based on the rules you set.
 - We provide two modes within this feature:



A screenshot of the "Money Management" settings panel. The "Enabled" checkbox is checked. The "Mode" dropdown menu is open, showing three options: "Based on Account Realized PnL", "Based on Account Realized PnL", and "Based on Cumulative PnL". The first two options are highlighted in blue, and the third is in black. A yellow rectangle highlights the entire dropdown menu.

- "Based on Account Realized PnL": If this mode is enabled, the Captain Optimus Strong will flatten the current account once the account's Realized PnL reaches the Daily Profit or Daily Loss threshold.
- "Based on Cumulative PnL": If this mode is enabled, Captain Optimus Strong will flatten all current positions on the account when the Cumulative PnL of Captain Optimus Strong alone reaches the established Daily Profit or Daily Loss threshold.
- Note: When you select the "Based on Cumulative PnL" feature, the system will suggest the "End Trading Day Reset Cum. PnL" option. This feature allows the system to reset the daily profit/loss management threshold to zero when a new trading day begins, if enabled.



A screenshot of the "Money Management" settings panel. The "Enabled" checkbox is checked. The "Mode" dropdown is set to "Based on Cumulative PnL". The "Max Daily Profit" and "Max Daily Loss" input fields are both set to "5000". The "End Trading Day Reset Cum. PnL" checkbox is checked. A yellow rectangle highlights the "End Trading Day Reset Cum. PnL" checkbox and its label.

- Max Daily Profit: Set the maximum profit you wish to achieve in a day.
 - When this threshold is reached or exceeded, the system will stop trading to secure the profit.
 - This threshold applies to one or more accounts or to the total profit generated by the system, depending on the "Mode" you have selected.
- Max Daily Loss: Set the maximum loss you are willing to accept in a day.
 - When this threshold is reached, the system will stop trading to protect the account from further losses.
 - Similarly, this threshold applies to one or more accounts or to the total profit generated by the system, depending on the "Mode" you have selected.

3.4. Sessions Management:

Sessions Management

Sessions Management: Enabled ☐

Time #1: Enabled ☒

Time #1: Start 190000

Time #1: Duration 40000

Time #2: Enabled ☒

Time #2: Start 30000

Time #2: Duration 40000

Time #3: Enabled ☒

Time #3: Start 80000

Time #3: Duration 40000

Time #1: Enable: Activating this ensures that the Captain Optimus Strong system only enters orders during the selected time frame.

Time #1: Start (190000) → 19 indicates the hour, 00 for minutes, and 00 for seconds.

Time #1: Duration: Setting this parameter to 40000 indicates that the Captain Optimus Strong system will search for and execute transactions from 19:00 ET to 23:00 ET. → Time #1: Duration = 4 hours.

Time #2: Enable: Activating this ensures that the Captain Optimus Strong system only enters orders during the selected time frame.

Time #2: Start (30000) → 3 indicates the hour, 00 for minutes, and 00 for seconds.

Time #2: Duration: Setting this parameter to 40000 indicates that the Captain Optimus Strong system will search for and execute transactions from 3:00 ET to 7:00 ET → Time #2: Duration = 4 hours.

Time #3: Enable: Activating this ensures that the Captain Optimus Strong system only enters orders during the selected time frame.

3.5. Auto Exit

Auto Exit is a feature that allows Captain Optimus Strong to automatically close a trade when the color-coded background ends.

How it works:

- When the pink background ends, the system closes the Sell position.
- When the green background ends, the system closes the Buy position.

This feature helps ensure that trades are exited as soon as the trend is no longer valid, reducing risk and helping protect your profits.

Note: When using the Auto Exit feature, there is one parameter you should pay attention to:


Auto Exit: Min Consensus (Bars) – This parameter defines the minimum number of consecutive bars that the background color must persist before the system executes an exit.

For example, if you set **Min Consensus = 3**, the background color (either green or pink) must appear and remain for at least **3 consecutive bars** for the system to trigger an exit. If the background only appears for 1 or 2 bars and then disappears, the system will not treat it as a valid exit signal.

Why is this important?

Some strategies generate signals that appear on just a single bar. Without this confirmation mechanism, the system might enter and exit a trade within the same bar.

The **Min Consensus** parameter helps prevent that by ensuring the system only exits a trade if the background color is sustained for the required number of bars.




3.6. #Of Signal Per Direction

The **#Of Signal Per Direction** parameter sets the maximum number of consecutive trades allowed in the same direction (Long or Short) that Captain Optimus Strong can execute.


How it works:

For example, if you set **#Of Signal Per Direction = 2**, the system will execute at most two consecutive trades in the same direction (e.g., 2 Long entries). Any further Buy signals after that will be ignored.




4. How to use the backtest feature in Captain Optimus Strong

- You can perform a backtest on the Captain Optimus Strong system to evaluate ATM strategies and the settings for indicators used as input data for the system. This should be done before using the system in live trading.
- Note
 - Currently, the backtest feature only supports market orders (MKT). We will update support for other order types as soon as possible.
 - The backtest duration corresponds to the "Days to load" setting in the "Data Series" window. For example, as shown below, the "Days to load" setting is set to 200 days.




- During the backtest process, commission fees play a crucial role in analyzing the results. They can turn a profitable trade into a loss. Therefore, it is essential to include commission fees when backtesting your strategy. Adjust the corresponding value through the "Round-Turn Commission (Ticks)" setting in the "General" section.



Tip: For instruments like NQ, ES, YM, you can set this value to 1 Tick.

- Steps to Perform a Strategy Backtest:
 - Step 1: Set the duration for the backtest in the "Data Series".

- Step 2: Follow the steps from Section 2 to set up and launch the system with one or more indicators you wish to use, and complete the automatic order entry setup from Section 3.1.
- Step 3: Set up your ATM strategy as described in Section 3.2.
- Step 4: Click the "ANALYZE" button on the control panel to launch the backtest feature.




- Step 5: After clicking the "ANALYZE" button, there are 2 cases:
 - Case 1: If you select the ATM strategy as "None", the system will start the backtest immediately.
 - Case 2: If you select an ATM strategy other than "None", the system will display a new window. Enter the "Stop Loss" and "Profit" values, then click "OK" to proceed with launching the backtest feature.




- Step 6: The system will analyze and display a window providing a summary table of the results from the trading strategy you have set up.

- Example: We selected 3 indicators: Easy Trend, FRAMA Pro, and SuperTrend Pro to build a trading strategy. We used this strategy to perform a backtest with the most recent 100 days of data, with "Stop Loss" set to 100 and "Profit" set to 300. The backtest results for this strategy will be displayed in the backtest window as shown in the images below.

Backtest Window			
Presentation	Overall	Long	Short
Accumulated profit	\$43,200 (8640t)	\$31,255 (6251t)	\$11,945 (2389t)
Gross profit	\$349,830 (69966t)	\$183,885 (36777t)	\$165,945 (33189t)
Gross loss	-\$306,630 (-61326t)	-\$152,630 (-30526t)	-\$154,000 (-30800t)
Commission	\$4,190 (838t)	\$2,125 (425t)	\$2,065 (413t)
Profit factor	1.14	1.20	1.08
Max drawdown	-\$13,330 (-2666t)	-\$12,825 (-2565t)	-\$12,745 (-2549t)
Number of trades	838	425	413
Average trades per day	11.64	5.90	5.74
Win rate	27.9%	28.9%	26.9%
Average reward	\$1,495 (299t)	\$1,495 (299t)	\$1,495 (299t)
Average risk	-\$507.67 (-101.53t)	-\$505.4 (-101.08t)	-\$509.93 (-101.99t)
Average reward : risk	2.94 : 1	2.96 : 1	2.93 : 1
Max winning streak	6	5	6
Max losing streak	17	16	14



5. Remaining parameters in the General section



- "Price Step: Unit": Select between "Tick" or "ForexPip"
- "Order: SLM Offset": The offset of Stop-Limit orders.
- "Reference Price: Offset Non-Negative": If checked, "Reference Price: Offset Value" will be a positive value. If unchecked, "Reference Price: Offset Value" will be a negative value. In this case, you will see the number displayed in the control panel (Row 6) highlighted.
- "Data Series Behind: Enabled": This mode must be enabled if you are using indicators that rely on a secondary data series for calculations (e.g., Imbalance Profile Lidar, Imbalance Volume Sensor, SpaceGPS Satellite, Cumulative Delta, Volume Delta, etc.).
 - "Data Series Behind: Type": Choose the type of secondary data series used for calculations by indicators as input data for Captain Optimus Strong, such as Tick, Minute, Range, Volume, or Second.
 - "Data Series Behind: Value": The value of the secondary data series that the indicators require for their calculations as input data for Captain Optimus Strong.
 - Most indicators require a secondary data series of 1 Tick for calculations, so you can use the default setting for this mode.