Delete

Balance factor of Imbalanced Node X

> 1
(L) Left heavy

Balance factor of Left Child of X
>= 0
(L)
LL

Action
Right Rotate around X.

Balance factor of Left child of X
< 0
(R)
LR

Action
1) Left rotate around X. left
2) Right rotate around X.

Balance factor of Imbalanced Node X
< -1
(R) Right heavy

Balance factor of Right child of X
<= 0
(R)
RR

Action
Left Rotate around X

Balance factor of Right child of X
> 0
(L)
RL

Action
1) Right rotate around X. right
2) Left Rotate around X.

After deleting a node, check the nodes on the path from deletion point to the root.
If balance factor of a node is invalid (< -1 or > 1), then check which child & which subtree is heavier (using B.F.) and accordingly apply rotations.

Difference between Insert & Delete

After insertion, max. 2 rotations are required to balance the tree.

After deletion, the unbalance may propogate upwards, which then requires more than 2 rotations.

1



Delete 12.



NO bal

Delete 37 ✓



NO bal

Delete 25.



R.R



(2)



LL.

BF(ROOT) > 1 AND
BF(ROOT→LEFT) >= 0

Delete. 100, 63, 75



R.



(3)



Delete 50.



R L.

-2

ROOT.

BF(ROOT) < 0. -1

BF(ROOT→RIGHT) > 0.

R L.





(4).



Delete (25).



- L

BF(ROOT) > 1.

L

BF(ROOT→LEFT) < 0.

R.

LR.