

Dokumentacija VyOS usmerjevalnika - startup11

May 7, 2026

1 Osnovne informacije

- **Ime naprave:** startup11-vyos
- **Domena:** startup11.local
- **Uporabnik:** vyos (prijava prek SSH ključa)

2 Omrežni vmesniki

Vmesnik	Opis	IPv4	IPv6
eth0	javni internet	88.200.24.241/25	2001:1470:fffd:a8::2/64
eth1	DMZ	192.168.11.1/24	2001:1470:fffd:a9::1/64
eth2	interna LAN	10.11.0.1/24	2001:1470:fffd:aa::1/64
eth3	IPv6-only	–	fd11:11:11::1/64

3 Default usmeritve (static routes)

```
set protocols static route 0.0.0.0/0 next-hop 88.200.24.129
set protocols static route6 ::/0 next-hop 2001:1470:fffd:a8::1
```

4 NAT (IPv4)

```
# Interna LAN (10.11.0.0/24) -> javni internet
set nat source rule 100 outbound-interface name 'eth0'
set nat source rule 100 source address '10.11.0.0/24'
set nat source rule 100 translation address 'masquerade'

# DMZ (192.168.11.0/24) -> javni internet
set nat source rule 110 outbound-interface name 'eth0'
set nat source rule 110 source address '192.168.11.0/24'
set nat source rule 110 translation address 'masquerade'
```

5 DMZ strežniki (vsi v omrežju 192.168.11.0/24)

5.1 Pregled strežnikov

Ime strežnika	IP naslov	OS	Uporabniško ime
sk11-dmz-linux-01	192.168.11.101	Linux	zanzan01
sk11-dmz-linux-02	192.168.11.102	Linux	zanzan02
sk11-dmz-linux-03	192.168.11.103	Linux	zanzan03
sk11-dmz-linux-04	192.168.11.104	Linux	zanzan04
sk11-dmz-linux-05	192.168.11.105	Linux	zanzan05
sk11-dmz-windows	192.168.11.110	Windows	Administrator

5.2 Splošno geslo

123NajboljseGeslo456!

6 Active Directory (Windows Server)

6.1 Osnovne informacije

Active Directory domena je nastavljena na strežniku **sk11-dmz-windows**. Strežnik deluje kot primarni Domain Controller (PDC) za domeno **startup11.local**.

- **Ime strežnika:** sk11-dmz-windows
- **Domena:** startup11.local
- **NetBIOS ime:** startup11
- **OS:** Windows Server (Core)
- **Vloga:** Domain Controller

6.2 Ustvarjanje uporabnikov v Active Directory

Uporabnike v domeni ustvarjamo s PowerShell ukazi neposredno na Domain Controllerju.

Primer: Ustvarjanje uporabnika

```
$password = Read-Host "Enter password for User" -AsSecureString
New-ADUser -Name "Ime_Priimek" '
    -GivenName Ime '
    -Surname Priimek '
    -SamAccountName imepriimek '
    -UserPrincipalName ime.priimek@startup11.local '
    -Enabled $true '
    -AccountPassword $password '
    -PassThru
```

6.3 Upravljanje uporabnikov

Prikaz vseh uporabnikov v domeni:

```
Get-ADUser -Filter * | Select-Object Name, SamAccountName, Enabled
```

Onemogočanje uporabniškega računa:

```
Disable-ADAccount -Identity "ime"
```

Brisanje uporabniškega računa:

```
Remove-ADUser -Identity "ime" -Confirm:$false
```

6.4 Prijava v domeno

Računalnike (Windows Pro/Enterprise ali Linux s konfiguriranim SSSD) lahko priklopimo v domeno `startup11.local`. Po uspešnem priklopu se uporabniki prijavljajo z:

- **Uporabniško ime:** `startup11\ime` (npr. `startup11\jdoe`)
- **Geslo:** (geslo, nastavljeno ob ustvarjanju uporabnika)

6.5 Dodatne informacije

- Administrator domene: `startup11\Administrator` z enakim geslom kot lokalni Administrator na strežniku