MINGALAR CINEMA

Website User Manual

Every step, from choosing a film to welcoming guests at the door.

CUSTOMERS / CASHIERS / ADMINISTRATORS

Version 1.0

16 October 2026

A practical reference for accounts, bookings, payments, tickets, counter sales, and website management.

Contents

Use the linked section titles or Word’s Navigation pane to find a task.

1. Navigation and account access 3
2. Find a film and a cinema 4
3. Choose a screening and seats 5
4. Pay now or reserve for later 6
5. Find and present your tickets 7
6. Manage your profile and security 8
7. Cashier guide 9
8. Administrator and super administrator guide 10
9. Troubleshooting 14
10. Quick reference 15

Use this guide to create an account, find a screening, reserve or buy seats, present a ticket, and carry out the staff tasks available to your role. Instructions use the English button labels. The customer website also supports Myanmar; a translated label may appear when that language is selected.

Start here

What you want to do	Where to go
Buy or reserve a ticket	Movies → choose a film → Showtimes
Find a cinema or directions	Cinemas → choose a cinema
View a booking or finish payment	My Tickets → select the booking
Update your name, phone, or language	Account menu → Profile
Collect cash or sell a walk-in ticket	Account menu → Cashier dashboard
Manage the cinema website	Account menu → Admin dashboard

1. Navigation and account access

Use the website on your device

- On a computer, use the navigation at the top of the page. On a phone or smaller tablet, the bottom navigation opens Home, Movies, Cinemas, My Tickets, and Profile.
- Select the Mingalar Cinema name to return to Home.
- Select မြန်မာ or **English** to switch the customer website language. Select the sun or moon button to change the appearance.
- After signing in, select your initial in the top corner to open the account menu. Staff dashboard links appear only for eligible staff accounts.
- Keyboard users can move between controls with Tab and activate buttons with Enter or Space. The customer pages include a **Skip to content** link when it receives keyboard focus.

Create an account

1. Select **Log in**, then **Sign up**.
2. Enter your full name and email address. Phone is optional.
3. Create a password of 8–72 characters containing an uppercase letter, a lowercase letter, and a number. Use the password visibility button if you need to check what you entered.
4. Select **Sign up** once and wait for the result.
5. Successful registration signs you in automatically. Email verification is not required before using the account. If you started from a booking, continue with that booking.

Keep the email address and password you chose. These are your normal sign-in credentials when you return. Do not create a second account just because you have logged out.

Sign in and sign out

1. Select **Log in**.
2. Enter the email address and password associated with your account.
3. Select **Log in**. If you were asked to sign in while booking, you return to the protected booking step.
4. To sign out, open your account menu and select **Log out**.

If **Continue with Google** or **Continue with Apple** is displayed, that provider is available. Follow its sign-in prompts and use the same method when returning to that account.

Optional emailed sign-in code: On the login form, select **Log in with an emailed code**, enter your registered email, and select **Send code**. Enter the six-digit code from the message and submit. Codes expire after 10 minutes; **Resend code** requests a replacement. Email delivery must be enabled by the site operator. Normal password sign-in does not require an email code.

Reset a forgotten password

1. On the login page, select **Forgot password?**.
2. Enter your account email and select **Continue**.
3. Open the password-reset email and follow its link.
4. Enter a new password that meets the requirements, then select **Save**.
5. Return to the login page and sign in with your new password.

2. Find a film and a cinema

Browse movies

1. Open **Movies**.
2. Choose **Now Showing** or **Coming Soon**. The selected collection is highlighted.
3. Select a poster or film title to open its detail page.
4. Review the age rating, runtime, genre, synopsis, cast, director, language, subtitles, and formats shown for that film.
5. Select **Trailer** to jump to the trailer when one is available. Select **Showtimes** to jump to booking choices.

If a collection is empty, use the suggested link to the other collection or return later. Coming Soon listings do not guarantee that a screening is available to book.

Browse cinemas and plan a visit

1. Open **Cinemas**, then select a cinema.
2. Check its address, opening hours, facilities, halls, and photographs when available.
3. Select **Call** to use your device's phone handler, or **Get Directions** to open map directions in a new tab.
4. Select **Showtimes** to view films scheduled at that cinema.

A missing map, phone number, photo, or facility list means that information has not been supplied for the cinema. You can still use the showtime controls.

3. Choose a screening and seats

Choose the cinema, date, and time

1. On a film detail page, select the cinema branch you want.
2. Choose a date. On narrow screens, swipe or scroll the row sideways to see more choices.
3. Review the selected cinema and the times shown. The format appears with each available time.
4. Select an available time to open seat selection. Sign in if prompted.

You can also start from a cinema's detail page: choose a date, find the film, and select its time. Opening the film's detail link from that schedule preserves the selected cinema and date.

Past or sold-out times cannot be booked. If no times appear, try another date or cinema. Always check the film, cinema, hall, and screening date/time before choosing seats.

Select seats

1. Use the **SCREEN** marker to understand the room orientation.
2. Select an available seat. Select it again to remove it from your selection.
3. Use the legend to distinguish available, selected, taken, couple, and your already-booked seats. Standard and couple seating depend on the hall layout.
4. Check the selected seat count and total shown at the bottom.
5. Select **Continue** to review your order and payment choices.

You can select up to **5 seats per booking**. A temporary seat-selection hold lasts **10 minutes**; watch the countdown on screen. If it expires, select available seats again. Seat availability updates while you are choosing, so a seat may become unavailable if another customer takes it first.

On a touch device, use two fingers to zoom the seat map and scroll sideways as needed. **Reset zoom** returns to the normal map size. Avoid refreshing or leaving the page unnecessarily while completing a timed selection.

4. Pay now or reserve for later

Review the order

1. Confirm the film, cinema, hall, date/time, seat labels, and subtotal.
2. If you have a promo code, enter it and select **Apply**. Review the accepted discount or the explanation if it is rejected.
3. Choose a payment method and review the final total in Myanmar kyat (MMK).
4. Select the payment or reservation button once. Wait for its result before trying another payment.

Pay by card

1. Select **Credit / Debit Card**, then **Pay**.
2. If a card payment form appears, enter the requested payment details and select **Confirm payment**.
3. Complete any additional instructions from the payment provider.
4. Wait for confirmation. A successful payment opens the ticket page.

Pay with KBZPay

1. Select **KBZPay**, then **Pay**.
2. Scan the payment QR code in the KBZPay app, or select **Open in KBZPay** when that option appears.
3. Complete the payment in the app.
4. Return to the website and wait for confirmation before treating the ticket as paid.

Understand demonstration payments

If the payment page clearly says it is a **simulated sandbox payment** and shows **Simulate successful payment** and **Simulate failed payment**, the website is using a demonstration payment provider. Those buttons test the booking flow and do not charge a real card or KBZPay account. Use only demonstration bookings in this mode. Real card and KBZPay checkout require the site operator to configure those providers.

Reserve & Pay Later

1. Choose **Reserve & Pay Later**, then **Reserve Seats**.
2. Save the booking reference and read the exact payment deadline on the booking page.
3. Before that deadline, open **My Tickets**, select the reservation, and choose **Pay by Card** or **Pay by KBZPay**. Alternatively, give the booking reference to a cinema cashier and pay cash.
4. After payment is confirmed, the booking becomes paid and its admission QR code is available.

A reservation normally has a **2-hour payment window**. The deadline shown on the booking page is the one to follow. An unpaid reservation is not an admission ticket. Expired or cancelled reservations cannot be paid; choose available seats and create a new booking instead. Payment must also be completed in time for the screening.

5. Find and present your tickets

1. Open **My Tickets** while signed in to the account that made the booking.
2. Choose a booking under **Upcoming** or **Past**.
3. Check its status, film, cinema, hall, time, seats, amount, and booking reference.
4. For a paid ticket, show the displayed **ticket QR code** at the cinema entrance.
5. Select **Download Ticket (PDF)** if you want to save or print the ticket.

Status	What it means
Payment pending / PENDING	The booking has not yet been paid. Follow its deadline and payment options.
Confirmed / PAID	Payment is confirmed and the admission QR code is available.
CHECKED_IN	Cinema staff have already checked the ticket in.
Expired, cancelled, or refunded	The booking is no longer an active admission ticket.

The ticket QR is different from a KBZPay payment QR. Only the ticket QR is used for admission. Keep it private and have it ready on your phone or PDF. A booking reference is useful when asking staff to find your booking.

There is no customer cancellation or refund button in the current website. Contact cinema staff with the booking reference if you need help. Cancelled, expired, and refunded bookings are not included in the normal My Tickets lists.

6. Manage your profile and security

Update profile details

1. Open the account menu and select **Profile**.
2. Update your name or phone number and choose English or Myanmar.
3. Select **Save changes** and look for the saved confirmation.

The profile form does not change your sign-in email address. Ask the site operator if you need help with an account email.

Change your password

1. In **Profile → Password**, enter the current password and a new password.
2. Select **Update password**.
3. After the success message, sign in again with your new password. The change signs you out of existing sessions.

An account created through an external sign-in provider may not have a website password to change. Use that provider's account controls instead.

Sign out on all devices

In **Profile → Security**, select **Log out of all devices**. You will need to sign in again. Use this when you have left an account open on a shared device.

7. Cashier guide

These tasks require a CASHIER, ADMIN, or SUPER_ADMIN account. From the account menu, cashiers can open **Cashier dashboard**. Staff with administrator accounts can also open the cashier area directly through the site's cashier route.

Sell a walk-in ticket

1. Open **Cashier → Sell a ticket**.
2. Browse movies, select the requested cinema/date/time, and choose seats as usual.
3. Continue to payment and select **Cash (at counter)**.
4. Enter the customer's name. Phone and email are optional; an email can be used for an e-receipt when delivery is configured.
5. Check the seat labels and amount. Collect the cash, then select **Complete Cash Sale**.
6. On the receipt page, select **Print Ticket (PDF)** and give the ticket to the customer.
7. Select **Sell another ticket** for the next customer.

Cash walk-in sales do not support promo codes. Complete the cash sale only after collecting the correct amount. The receipt includes the admission QR, booking reference, seats, and amount collected.

Collect payment for an online reservation

1. Open **Cashier → Pay a reservation**.
2. Enter the customer's booking reference and select **Look up**. The scanner is also available when the customer has a supported ticket QR.
3. Verify the film, cinema, hall, date/time, seats, total, and status with the customer.
4. If it is a valid pending reservation, collect the cash and select **Confirm Cash Payment**.
5. Check the success message. The customer's ticket is now paid and can be opened in My Tickets.

An unpaid reservation may have a booking reference without an admission QR; enter the reference in that case. Already paid, checked-in, expired, or cancelled bookings must not be collected again. If camera access fails, close the scanner and enter the reference manually.

8. Administrator and super administrator guide

Open **Admin dashboard** from the account menu using an ADMIN or SUPER_ADMIN account. On a computer, use the sidebar to open each management area. On a phone or smaller tablet, select the menu button labelled **Open admin navigation**, choose an area, and the menu closes. **Close admin navigation** or Escape closes an open menu. An authenticator setup is not required to enter the dashboard.

For a new cinema, prepare data in this order: **Branches → Halls → Seat Layout → Movies → Showtimes**. Then check the result on the public movie and cinema pages before customers book.

Dashboard

Open **Dashboard** to review today's sales and tickets, 30-day revenue, revenue by branch/movie, and upcoming showtime occupancy. Paid and checked-in bookings contribute to sales totals. Occupancy covers up to 10 showtimes in the next 24 hours. These are management summaries; the page has no report-export or custom date-range controls.

Movies

1. Open **Movies → + Add Movie**.
2. Enter the title, synopsis, director, runtime, language, release date, and classification. Enter cast and genre as comma-separated lists.
3. Select at least one format: **2D**, **3D**, or **Premium**.
4. Choose **Coming Soon**, **Now Showing**, or **Ended**. Select **Featured on home page** when appropriate.
5. Supply a poster. A banner and YouTube trailer URL are optional.
6. Keep **All branches** selected, or clear it and select the branches where the film is available.
7. Select **Create Movie**. To update a film later, find it in the list, select **Edit**, and choose **Save Changes**.

Search the list by title. A movie with showtimes cannot be deleted; using **Ended** is often the appropriate way to retire it.

Image fields: Movie and promotion image fields accept a pasted image URL or an uploaded JPEG, PNG, or WebP file up to 5 MB. Uploads require configured image storage. If upload is unavailable, use a supported image URL supplied by your organization. There is no built-in image cropper.

Branches

1. Open **Branches → + Add Branch**.
2. Enter the English and Burmese names and addresses, phone, and opening hours.
3. Add latitude/longitude for maps and comma-separated facilities when available.
4. Select **Active** if the branch should appear in the public cinema list, then select **Create Branch**.
5. Use **Edit** to update the branch or clear **Active** to deactivate it.

A branch containing halls cannot be deleted. Deactivation keeps its records. The current branch form has no photograph-upload control, even though existing branch photographs can appear publicly.

Halls and seat layouts

1. Open **Halls → + Add Hall**.
2. Choose a branch, enter the hall name, and set the number of rows and columns.
3. Select **Create Hall**, then open that hall's **Seat Layout**.
4. Select a seat to cycle it through **Standard → Couple → Disabled → Standard**.
5. Use the small column markers to add or remove an aisle gap after that column across the layout.
6. Select **Save Layout**, then review the seating arrangement.

Halls support 1–26 rows and 1–40 columns. Increasing dimensions creates Standard seats. Reducing dimensions is blocked if a removed seat has booking records. A hall with showtimes cannot be deleted. Check the public seat map after a layout change.

Create a single showtime

1. Open **Showtimes → + Add Showtime**.
2. Choose the movie, an eligible branch, and a hall in that branch.
3. Set **Starts At**, the format, and the Standard and Couple prices in Ks.
4. Select **Create Showtime**.
5. To make a change, select **Edit** in the list, then **Save Changes**.

The film must be available at the selected branch. The schedule checks the film runtime plus a 20-minute cleaning buffer; overlapping sessions in the same hall are rejected. Search by movie title or branch name. Deleting a showtime requires confirmation and is blocked if it has pending, paid, or checked-in bookings.

Create a repeating schedule

1. Open **Showtimes → Bulk Create**.
2. Choose the movie, branch, and hall.
3. Enter the inclusive start and end dates. The end date must be on or after the start.
4. Enter comma-separated times in 24-hour format, for example **10:00, 13:00, 16:00**.
5. Set the format and prices, then select **Create Schedule**.
6. Read the created/skipped summary and review the resulting entries in **Showtimes**.

Past sessions are omitted and conflicting sessions are skipped. The same 20-minute cleaning buffer applies. There is no bulk preview or one-click undo; review dates, times, and prices before creating the schedule.

Find, cancel, or refund a booking

1. Open **Bookings**.
2. Search by booking reference, contact email, or phone. Select the booking reference to open its details.
3. Verify the film, branch/hall, screening, seats, customer/contact details, subtotal, discount, total, and payment records.
4. For a **Pending** or **Paid** booking, select **Cancel Booking** and confirm if cancellation is appropriate. Cancellation releases its seats.
5. For a **Paid** or **Checked In** booking, select **Refund** and confirm when authorized under cinema policy.

Refund records the refund in Mingalar Cinema. It does not send money back through the payment provider. Complete the actual money return through the cinema's separate payment/refund process and keep the transaction record. Cancelling a paid booking also does not itself return money.

The current management screen does not edit booked seats or move a booking to another screening. Follow the cinema's approved cancellation/refund and new-booking process when those changes are needed.

Check a ticket in

1. Open **Check-in** and select **Start Camera Scanner**.
2. Allow camera access and scan the customer's **ticket QR code**.
3. Confirm the success message and the film, branch, time, and seats shown.
4. If needed, enter the ticket's QR token/code in the manual field and select **Check In**.

The manual check-in field accepts the QR token/code, **not a booking reference**. Only paid tickets can be checked in. Read warnings for unpaid, unrecognized, or already-used tickets before admitting a customer. Camera scanning depends on browser support and permissions; use manual token entry when available or an approved scanning device. Do not scan a KBZPay payment QR for admission.

Promotions: announcements on Home

1. Open **Promotions → + Add Promotion**.
2. Enter English/Burmese titles and body text, an optional image, and start/end dates.
3. Select **Published**, then **Create Promotion**.
4. Use **Edit** to change an announcement. Clear **Published** to unpublish it.

Published promotions appear on Home only during their active date range. A promotion announcement does not create a discount code; add a code separately when required.

Promo Codes: checkout discounts

1. Open **Promo Codes → + Add Promo Code**.
2. Enter the code and choose a **Percentage** or **Fixed** amount in Ks.
3. Enter the discount amount and, when needed, the minimum spend, total usage limit, and expiry.
4. Select **Active** and save the code.
5. Use the list to review recorded uses, edit the code, or delete it after confirmation.

Codes are normalized to uppercase. A blank usage limit means unlimited total uses; a blank expiry means no expiry. Each customer can redeem a particular code once. Test the code against an appropriate checkout subtotal before advertising it. Cash walk-in sales do not apply promo codes.

Users and account assistance

1. Open **Users** and search by name, email, or phone.
2. Select the user's name to review their account and recent booking history.
3. Select **Disable Account** or **Enable Account**, then confirm, when the account should be blocked or restored.
4. Select **Send Password Reset Email** and confirm when the customer needs a reset. That staff-requested reset link expires after one hour.
5. A super administrator can select **USER**, **CASHIER**, **ADMIN**, or **SUPER_ADMIN** and confirm a role change.

Staff cannot disable their own account or change their own role. Email delivery must be configured for reset messages. Ask the affected user to sign in again after a role or session change if their access has not updated.

Administrator invitations — super administrators

1. Open **Admin Invites**.
2. Enter an email address that does not already have an account.
3. Select **ADMIN** or **SUPER_ADMIN**, then **Send Invite**.
4. The recipient opens the emailed link, enters their full name and a password that meets the normal requirements, and selects **Activate account**.
5. The recipient signs in using that email and password. Administrator authenticator setup is not required.

Invitations expire after 48 hours. The invitation list shows Pending, Accepted, or Expired. Revoke an unaccepted invitation if it should no longer be usable. For an existing account, change its role under **Users** instead of sending an invitation.

Site Settings — changes require a super administrator

1. Open **Site Settings**.
2. Review the brand name/logo text, existing orange/red/crimson colors, hotline, social links, and default language.
3. A super administrator can update the fields and select **Save Settings**. Administrators can inspect the settings.
4. Check the relevant public page after saving. Keep the existing brand colors unless the organization has authorized a brand change.

Audit Log

Open **Audit Log** to review the latest administrative events. Search by action or actor, use the sortable column headings as needed, and use **Prev/Next** to move through the list. Entries show the time, actor, action, and entity reference. This screen does not export an audit report or show a detailed before/after comparison.

Daily staff checks

- Confirm today's films, halls, showtimes, and prices before sales start.
- Check that featured films, active announcements, and advertised promo codes are accurate.
- Review pending customer issues, cash collections, and any required external money returns.
- Sign out before leaving a shared counter or management device.

9. Troubleshooting

What you see	What to do
Incorrect email or password	Check the account email, password visibility, keyboard language, and Caps Lock. Use Forgot password if necessary.
Account temporarily locked or too many attempts	Follow the wait message. Repeated attempts can extend the problem; a disabled account needs administrator help.
No sign-in code or reset email	Check the address, spam folder, and newest message. Request a new code if needed; email delivery must be configured. Password sign-in does not require a code.
Invalid or expired reset link	Return to Forgot password and request a new reset email. The request confirmation does not confirm whether an account exists.
No films or showtimes	Change the collection, date, or cinema. Schedules may not yet have been published.
A seat is unavailable	Choose another available seat. Another customer may have selected it or staff may have disabled it.
Hold expired or Continue is disabled	Select available seats again. At least one seat must be selected before continuing.
Promo code rejected	Read the reason. Check the spelling, validity dates, minimum spend, and usage restrictions.
Payment waiting or interrupted	Check My Tickets before creating another booking or paying again. If a payment was charged but the ticket is not confirmed, give cinema staff your booking reference and payment details.
No ticket QR or PDF yet	Confirm the booking is PAID. Pending reservations need payment; expired bookings need a new reservation.
Ticket is missing	Sign in to the account that made the booking. Check Upcoming and Past. Give cinema staff the reference if further help is needed.
Camera does not open	Allow camera permission in the browser, ensure another app is not using it, or use the available manual entry field.
Access denied to a staff page	Use an authorized staff account. Ask a super administrator to verify your role; signing in again may be required after a change.
Page shows an error	Use its retry option where available. If the error persists, note the action and message and contact the site operator. Check payment status before retrying a purchase.

For booking help, open the cinema's detail page and use its published phone number. Provide the booking reference, film, cinema, screening time, and a brief description of the issue. Do not send passwords, one-time sign-in codes, or full card details.

10. Quick reference

Item	Reference
Normal returning sign-in	Account email and password
New customer registration	Automatically signs in; no email verification step
Maximum seats in one booking	5
Temporary seat-selection hold	10 minutes; follow the on-screen countdown
Reservation payment window	Normally 2 hours; follow the exact displayed deadline
Currency	Myanmar kyat (MMK)
Admission	Paid ticket QR or ticket PDF
Reservation help at the counter	Booking reference
Customer language choices	English and Myanmar
Administrator authenticator setup	Not required to enter the administrator dashboard

Staff role overview

Role	Intended access
USER	Customer browsing, own bookings/tickets, and profile
CASHIER	Customer functions plus cash walk-in sales and reservation cash collection
ADMIN	Cashier access plus cinema management, bookings, check-in, user account actions, and audit review
SUPER_ADMIN	Administrator functions plus administrator invitations, account role changes, and Site Settings changes

Use a separate staff account for each person. Sign out when leaving a shared counter or management device.