```
MACHINE M_Part_Trans
SEES C_Part_Proc_Trans
 VARIABLES
                      partition\_mode
INVARIANTS
                      \verb"inv-part-mode": partition\_mode \in PARTITIONS \rightarrow PARTITION\_MODES
EVENTS
Initialisation
                  begin
                                       act001: partition\_mode := PARTITIONS \times \{PM\_COLD\_START\}
Event partition_mode_transition (ordinary) \hat{=}
                   any
                                       part
                                      newm
                   where
                                      grd001: part \in PARTITIONS
                                      {\tt grd002:} \quad newm \in PARTITION\_MODES
                                      \verb|grd003|: partition\_mode(part) = PM\_IDLE \Rightarrow newm = PM\_WARM\_START \lor newm = PM\_COLD\_START
                                       \texttt{grd004:} \ \ partition\_mode(part) = PM\_COLD\_START \Rightarrow newm = PM\_IDLE \lor newm = PM\_COLD\_START \lor
                                                newm = PM\_NORMAL
                                       \verb|grd005|: partition_mode(part) = PM_WARM_START \Rightarrow newm = PM_IDLE \lor newm = PM_COLD_START \lor
                                                newm = PM\_WARM\_START \lor newm = PM\_NORMAL
                                      {\tt grd006:} \ \ partition\_mode(part) = PM\_NORMAL \Rightarrow newm = PM\_IDLE \lor newm = PM\_COLD\_START \lor
                                                newm = PM\_WARM\_START
                   then
                                       act001: partition\_mode(part) := newm
                  end
END
```

19.03.2023 15:22 Page 1 of 1