5.5.2 Lab – Configure and Verify Extended IPv4 ACLs (Answers)

itexamanswers.net/5-5-2-lab-configure-and-verify-extended-ipv4-acls-answers.html

October 2, 2020

Lab – Configure and Verify Extended IPv4 ACLs (Instructor Version)

	 	·	
Гороlоду			

Addressing Table

Device Interface IP Address Subnet Mask Default Gateway

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/0/1	N/A	N/A	N/A
	G0/0/1.20	10.20.0.1	255.255.255.0	-
	G0/0/1.30	10.30.0.1	255.255.255.0	-
	G0/0/1.40	10.40.0.1	255.255.255.0	-
	G0/0/1.1000	N/A	N/A	-
	Loopback1	172.16.1.1	255.255.255.0	-
R2	G0/0/1	10.20.0.4	255.255.255.0	N/A
S1	VLAN 20	10.20.0.2	255.255.255.0	10.20.0.1
S2	VLAN 20	10.20.0.3	255.255.255.0	10.20.0.1
PC-A	NIC	10.30.0.10	255.255.255.0	10.30.0.1
РС-В	NIC	10.40.0.10	255.255.255.0	10.40.0.1

VLAN Table

VLAN	Name	Interface Assigned
20	Management	S2: F0/5
30	Operations	S1: F0/6
40	Sales	S2: F0/18
999	ParkingLot	S1: F0/2-4, F0/7-24, G0/1-2 S2: F0/2-4, F0/6-17, F0/19-24, G0/1-2
1000	Native	N/A

Objectives

- Part 1: Build the Network and Configure Basic Device Settings
- Part 2: Configure and Verify Extended Access Control Lists

Background / Scenario

You have been tasked with configuring access control lists on small company's network. ACLs are one of the simplest and most direct means of controlling layer 3 traffic. R1 will be hosting an internet connection (simulated by interface Loopback 1) and sharing the default route information to R2. After initial configuration is complete, the company has some specific traffic security requirements that you are responsible for implementing.

Note: The routers used with CCNA hands-on labs are Cisco 4221 with Cisco IOS XE Release 16.9.4 (universalk9 image). The switches used in the labs are Cisco Catalyst 2960s with Cisco IOS Release 15.2(2) (lanbasek9 image). Other routers, switches, and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and the output produced might vary from what is shown in the labs. Refer to the Router Interface Summary Table at the end of the lab for the correct interface identifiers.

Note: Ensure that the routers and switches have been erased and have no startup configurations. If you are unsure contact your instructor.

Instructor Note: Refer to the Instructor Lab Manual for the procedures to initialize and reload devices.

Required Resources

- 2 Routers (Cisco 4221 with Cisco IOS XE Release 16.9.4 universal image or comparable)
- 2 Switches (Cisco 2960 with Cisco IOS Release 15.2(2) lanbasek9 image or comparable)
- 2 PCs (Windows with a terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- · Ethernet cables as shown in the topology

Instructions

Part 1: Build the Network and Configure Basic Device Settings.

Step 1: Cable the network as shown in the topology.

Attach the devices as shown in the topology diagram, and cable as necessary.

Step 2: Configure basic settings for each router.

a. Assign a device name to the router.

router(config)# hostname R1

b. Disable DNS lookup to prevent the router from attempting to translate incorrectly entered commands as though they were host names.

R1(config)# no ip domain lookup

c. Assign **class** as the privileged EXEC encrypted password.

R1(config)# enable secret class

d. Assign **cisco** as the console password and enable login.

R1(config)# line console 0 R1(config-line)# password cisco R1(config-line)# login

e. Assign **cisco** as the VTY password and enable login.

R1(config)# line vty 0 4 R1(config-line)# password cisco R1(config-line)# login

f. Encrypt the plaintext passwords.

R1(config)# service password-encryption

g. Create a banner that warns anyone accessing the device that unauthorized access is prohibited.

R1(config)# banner motd \$ Authorized Users Only! \$

h. Save the running configuration to the startup configuration file.

R1# copy running-config startup-config

Step 3: Configure basic settings for each switch.

a. Assign a device name to the switch.

switch(config)# hostname S1

b. Disable DNS lookup to prevent the router from attempting to translate incorrectly entered commands as though they were host names.

S1(config)# no ip domain-lookup

c. Assign class as the privileged EXEC encrypted password.

S1(config)# enable secret class

d. Assign **cisco** as the console password and enable login.

```
S1(config)# line console 0
S1(config-line)# password cisco
S1(config-line)# login
```

e. Assign **cisco** as the VTY password and enable login.

```
S1(config)# line vty 0 15
S1(config-line)# password cisco
S1(config-line)# login
```

f. Encrypt the plaintext passwords.

```
S1(config)# service password-encryption
```

g. Create a banner that warns anyone accessing the device that unauthorized access is prohibited.

```
S1(config)# banner motd $ Authorized Users Only! $
```

h. Save the running configuration to the startup configuration file.

```
S1(config)# exit
S1# copy running-config startup-config
```

Part 2: Configure VLANs on the Switches

Step 1: Create VLANs on both switches.

a. Create and name the required VLANs on each switch from the table above.

```
S1(config)# vlan 20
S1(config-vlan)# name Management
S1(config-vlan)# vlan 30
S1(config-vlan)# name Operations
S1(config-vlan)# vlan 40
S1(config-vlan)# name Sales
S1(config-vlan)# vlan 999
S1(config-vlan)# name ParkingLot
S1(config-vlan)# vlan 1000
S1(config-vlan)# name Native
S1(config-vlan)# exit
S2(config)# vlan 20
S2(config-vlan)# name Management
S2(config-vlan)# vlan 30
S2(config-vlan)# name Operations
S2(config-vlan)# vlan 40
S2(config-vlan)# name Sales
S2(config-vlan)# vlan 999
S2(config-vlan)# name ParkingLot
S2(config-vlan)# vlan 1000
S2(config-vlan)# name Native
S2(config-vlan)# exit
```

b. Configure the management interface and default gateway on each switch using the IP address information in the Addressing Table.

```
S1(config)# interface vlan 20
S1(config-if)# ip address 10.20.0.2 255.255.255.0
S1(config-if)# no shutdown
S1(config-if)# exit
S1(config)# ip default-gateway 10.20.0.1
S1(config)# end
S2(config)# interface vlan 20
S2(config-if)# ip address 10.20.0.3 255.255.255.0
S2(config-if)# no shutdown
S2(config-if)# exit
S2(config)# ip default-gateway 10.20.0.1
S2(config)# end
```

c. Assign all unused ports on the switch to the Parking Lot VLAN, configure them for static access mode, and administratively deactivate them.

Note: The interface range command is helpful to accomplish this task with as few commands as necessary.

```
S1(config)# interface range f0/2 - 4, f0/7 - 24, g0/1 - 2
S1(config-if-range)# switchport mode access
S1(config-if-range)# switchport access vlan 999
S1(config-if-range)# shutdown
S1(config-if-range)# end

S2(config)# interface range f0/2 - 17, f0/19 - 24, g0/1 - 2
S2(config-if-range)# switchport mode access
S2(config-if-range)# switchport access vlan 999
S2(config-if-range)# shutdown
S2(config-if-range)# end
```

Step 2: Assign VLANs to the correct switch interfaces.

a. Assign used ports to the appropriate VLAN (specified in the VLAN table above) and configure them for static access mode.

```
S1(config)# interface f0/6
S1(config-if)# switchport mode access
S1(config-if)# switchport access vlan 30
S2(config)# interface f0/18
S2(config-if)# switchport mode access
S2(config-if)# switchport access vlan 40
```

b. Issue the show vlan brief command and verify that the VLANs are assigned to the correct interfaces.

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa0/5
10	Management	active	
20	Sales	active	Fa0/6
30	Operations	active	
999	ParkingLot	active	Fa0/2, Fa0/3, Fa0/4, Fa0/7 Fa0/8, Fa0/9, Fa0/10, Fa0/11 Fa0/12, Fa0/13, Fa0/14, Fa0/15 Fa0/16, Fa0/17, Fa0/18, Fa0/19 Fa0/20, Fa0/21, Fa0/22, Fa0/23
			Fa0/24, Gi0/1, Gi0/2
1000	Native	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	
S2# :	show vlab brief		
VLAN	Name	Status	Ports
1	default	active	
10	Management	active	F40/ 1
30	Operations	active	
40	Sales	active	Fa0/18
999	ParkingLot	active	Fa0/2, Fa0/3, Fa0/4, Fa0/5
333	Tarkingese	uoervo	Fa0/6, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Fa0/11, Fa0/12, Fa0/13 Fa0/14, Fa0/15, Fa0/16, Fa0/17
			Fa0/19, Fa0/20, Fa0/21, Fa0/22 Fa0/23, Fa0/24, Gi0/1, Gi0/2

Part 3: Configure Trunking

Step 1: Manually configure trunk interface Fo/1.

a. Change the switchport mode on interface Fo/1 to force trunking. Make sure to do this on both switches.

```
S1(config)# interface f0/1
S1(config-if)# switchport mode trunk
S2(config)# interface f0/1
S2(config-if)# switchport mode trunk
```

b. As a part of the trunk configuration, set the native vlan to 1000 on both switches. You may see error messages temporarily while the two interfaces are configured for different native VLANs.

```
S1(config-if)# switchport trunk native vlan 1000
S2(config-if)# switchport trunk native vlan 1000
```

c. As another part of trunk configuration, specify that VLANs 10, 20, 30, and 1000 are allowed to cross the trunk.

```
S1(config-if)# switchport trunk allowed vlan 20,30,40,1000
S2(config-if)# switchport trunk allowed vlan 20,30,40,1000
```

d. Issue the **show interfaces trunk** command to verify trunking ports, the Native VLAN and allowed VLANs across the trunk.

S1# show interfaces trunk

Port Mode Encapsulation Status Native vlan Fa0/1 on 802.1q trunking 1000

Port Vlans allowed on trunk

Fa0/1 20,30,40,1000

Port Vlans allowed and active in management domain

Fa0/1 20,30,40,1000

Port Vlans in spanning tree forwarding state and not pruned

Fa0/1 20,30,40,1000

S2# show interface trunk

Port Mode Encapsulation Status Native vlan Fa0/1 on 802.1q trunking 1000

Port Vlans allowed on trunk

Fa0/1 20,30,40,1000

Port Vlans allowed and active in management domain

Fa0/1 30,40,1000

Port Vlans in spanning tree forwarding state and not pruned

Fa0/1 30,40

Step 2: Manually configure S1's trunk interface Fo/5.

a. Configure S1's interface Fo/5 with the same trunk parameters as Fo/1. This is the trunk to the router.

S1(config)# interface f0/5
S1(config-if)# switchport mode trunk
S1(config-if)# switchport trunk native vlan 1000
S1(config-if)# switchport trunk allowed vlan 20,30,40,1000

b. Save the running configuration to the startup configuration file.

S1# copy running-config startup-config

c. Issue the show interfaces trunk command to verify trunking.

Part 4: Configure Routing

Step 1: Configure Inter-VLAN Routing on R1.

a. Activate interface Go/o/1 on the router.

R1(config)# interface g0/0/1 R1(config-if)# no shutdown

b. Configure sub-interfaces for each VLAN as specified in the IP addressing table. All sub-interfaces use 802.1Q encapsulation. Ensure the sub-interface for the native VLAN does not have an IP address assigned. Include a description for each sub-interface.

```
R1(config)# interface g0/0/1.20
R1(config-subif)# description Management Network
R1(config-subif)# encapsulation dot1q 20
R1(config-subif)# ip address 10.20.0.1 255.255.255.0
R1(config-subif)# interface g0/0/1.30
R1(config-subif)# encapsulation dot1q 30
R1(config-subif)# description Operations Network
R1(config-subif)# ip address 10.30.0.1 255.255.255.0
R1(config-subif)# interface g0/0/1.40
R1(config-subif)# encapsulation dot1q 40
R1(config-subif)# description Sales Network
R1(config-subif)# ip address 10.40.0.1 255.255.255.0
R1(config-subif)# ip address 10.40.0.1 255.255.255.0
R1(config-subif)# interface g0/0/1.1000
R1(config-subif)# encapsulation dot1q 1000 native
R1(config-subif)# description Native VLAN
```

c. Configure interface Loopback 1 on R1 with addressing from the table above.

```
R1(config)# interface Loopback 1
R1(config-if)# ip address 172.16.1.1 255.255.255.0
```

d. Use the show ip interface brief command to verify the sub-interfaces are operational.

R1# show ip interface brief Interface IP-Address OK? Method Statu GigabitEthernet0/0/0 unassigned YES unset admin GigabitEthernet0/0/1 unassigned YES unset up Gi0/0/1.20 10.20.0.1 YES manual up Gi0/0/1.30 10.30.0.1 YES manual up Gi0/0/1.40 10.40.0.1 YES manual up Gi0/0/1.1000 unassigned YES unset up Serial0/1/0 unassigned NO unset down GigabitEthernet0 unassigned VES unset admin Signed Serialo/1/1 unassigned NO unset down GigabitEthernet0 unassigned YES unset admin OK? Method Status Protocol YES unset administratively down down un up up up up down Serial0/1/1
GigabitEthernet0 down unassigned YES unset administratively down down Loopback1 172.16.1.1 YES manual up

Step 2: Configure the R2 interface go/o/1 using the address from the table and a default route with the next hop 10.20.0.1

```
R2(config)# interface g0/0/1
R2(config-if)# ip address 10.20.0.4 255.255.255.0
R2(config-if)# no shutdown
R2(config-if)# exit
R2(config)# ip route 0.0.0.0 0.0.0.0 10.20.0.1
```

Part 5: Configure Remote Access

Step 1: Configure all network devices for basic SSH support.

a. Create a local user with the username SSH admin and the encrypted password cisco123!

R1(config)# username SSHadmin secret \$cisco123!

b. Use **ccna-lab.com** as the domain name.

R1(config)# ip domain name ccna-lab.com

c. Generate crypto keys using a 1024-bit modulus.

R1(config)# crypto key generate rsa general-keys modulus 1024

d. Configure the first five VTY lines on each device to support SSH connections only and to authenticate to the local user database.

```
R1(config)# line vty 0 4
R1(config-line)# transport input ssh
R1(config-line)# login local
R1(config-line)# exit
```

Step 2: Enable secure, authenticated web services on R1.

a. Enable the HTTPS server on R1.

R1(config)# ip http secure-server

b. Configure R1 to authenticate users attempting to connect to the web server.

R1(config)# ip http authentication local

Part 6: Verify Connectivity

Step 1: Configure PC hosts.

Refer to the Addressing Table for PC host address information.

Step 2: Complete the following tests. All should be successful.

Note: You may have to disable the PC firewall for pings to be successful.

From	Protocol	Destination
PC-A	Ping	10.40.0.10
PC-A	Ping	10.20.0.1
РС-В	Ping	10.30.0.10
РС-В	Ping	10.20.0.1
РС-В	Ping	172.16.1.1
РС-В	HTTPS	10.20.0.1
РС-В	HTTPS	172.16.1.1
РС-В	SSH	10.20.0.1
РС-В	SSH	172.16.1.1

Part 7: Configure and Verify Extended Access Control Lists.

When basic connectivity is verified, the company requires the following security policies to be implemented:

Policy 1: The Sales Network is not allowed to SSH to the Management Network (but other SSH is allowed).

Policy 2: The Sales Network is not allowed to access IP addresses in the Management network using any web protocol (HTTP/HTTPS). The Sales Network is also not allowed to access R1 interfaces using any web protocol. All other web traffic is allowed (note – Sales can access the Loopback 1 interface on R1).

Policy 3: The Sales Network is not allowed to send ICMP echo-requests to the Operations or Management Networks. ICMP echo requests to other destinations are allowed.

Policy 4: The Operations network is not allowed to send ICMP echo-requests to the Sales network. ICMP echo requests to other destinations are allowed.

Step 1: Analyze the network and the security policy requirements to plan ACL implementation.

Answers may vary. The requirements listed above require two extended access lists to be implemented. Following the guidance of placing extended access lists as close to the source of the traffic to be filtered as possible, these ACLs will go on interfaces Go/o/o.3o and Go/o/o.4o.

Step 2: Develop and apply extended access lists that will meet the security policy statements.

Answers may vary. The ACLs should be similar to the following:

```
R1(config)# access-list 101 remark ACL 101 fulfills policies 1, 2, and 3
R1(config)# access-list 101 deny tcp 10.40.0.0 0.0.0.255 10.20.0.0 0.0.0.255 eq 22
R1(config)# access-list 101 deny tcp 10.40.0.0 0.0.0.255 10.20.0.0 0.0.0.255 eq 80
R1(config)# access-list 101 deny tcp 10.40.0.0 0.0.0.255 10.30.0.1 0.0.0.0 eq 80
R1(config)# access-list 101 deny tcp 10.40.0.0 0.0.0.255 10.40.0.1 0.0.0.0 eq 80
R1(config)# access-list 101 deny tcp 10.40.0.0 0.0.0.255 10.20.0.0 0.0.0.255 eq 443
R1(config)# access-list 101 deny tcp 10.40.0.0 0.0.0.255 10.30.0.1 0.0.0.0 eq 443
R1(config)# access-list 101 deny tcp 10.40.0.0 0.0.0.255 10.40.0.1 0.0.0.0 eq 443
R1(config)# access-list 101 deny icmp 10.40.0.0 0.0.0.255 10.20.0.0 0.0.0.255 echo
R1(config)# access-list 101 deny icmp 10.40.0.0 0.0.0.255 10.30.0.0 0.0.0.255 echo
R1(config)# access-list 101 permit ip any any
R1(config)# interface g0/0/1.40
R1(config-subif)# ip access-group 101 in
R1(config)# access-list 102 remark ACL 102 fulfills policy 4
R1(config)# access-list 102 deny icmp 10.30.0.0 0.0.0.255 10.40.0.0 0.0.0.255 echo
R1(config)# access-list 102 permit ip any any
R1(config)# interface g0/0/1.30
R1(config-subif)# ip access-group 102 in
```

Step 3: Verify security policies are being enforced by the deployed access lists.

Run the following tests. The expected results are shown in the table:

From	Protocol	Destination	Result
PC-A	Ping	10.40.0.10	Fail
PC-A	Ping	10.20.0.1	Success
РС-В	Ping	10.30.0.10	Fail
РС-В	Ping	10.20.0.1	Fail
РС-В	Ping	172.16.1.1	Success
РС-В	HTTPS	10.20.0.1	Fail
РС-В	HTTPS	172.16.1.1	Success
РС-В	SSH	10.20.0.4	Fail
РС-В	SSH	172.16.1.1	Success

Device Configs

Router R1

```
R1# show run
Building configuration...
Current configuration : 5264 bytes
version 16.9
service timestamps debug datetime msec
service timestamps log datetime msec
service password-encryption
platform qfp utilization monitor load 80
no platform punt-keepalive disable-kernel-core
hostname R1
boot-start-marker
boot-end-marker
vrf definition Mgmt-intf
 address-family ipv4
 exit-address-family
 address-family ipv6
 exit-address-family
enable secret 5 $1$.Dkb$dhzFCwC9TtcbWur3lMEe10
no aaa new-model
no ip domain lookup
ip domain name ccna-lab.com
login on-success log
subscriber templating
multilink bundle-name authenticated
<output omitted>
no license smart enable
diagnostic bootup level minimal
spanning-tree extend system-id
username SSHadmin secret 5 $1$829R$mk6kzq/CCkw0irnUoa.tM1
redundancy
mode none
interface Loopback1
 ip address 172.16.1.1 255.255.255.0
interface GigabitEthernet0/0/0
 no ip address
negotiation auto
interface GigabitEthernet0/0/1
no ip address
negotiation auto
interface GigabitEthernet0/0/1.20
description Management Network
 encapsulation dot1Q 20
 ip address 10.20.0.1 255.255.255.0
```

```
interface GigabitEthernet0/0/1.30
description Operations Network
encapsulation dot10 30
ip address 10.30.0.1 255.255.255.0
ip access-group 102 in
interface GigabitEthernet0/0/1.40
description Sales Network
encapsulation dot10 40
ip address 10.40.0.1 255.255.255.0
ip access-group 101 in
interface GigabitEthernet0/0/1.1000
description Native VLAN
encapsulation dot1Q 1000 native
interface Serial0/1/0
no ip address
interface Serial0/1/1
no ip address
interface GigabitEthernet0
vrf forwarding Mgmt-intf
no ip address
negotiation auto
ip forward-protocol nd
no ip http server
ip http authentication local
ip http secure-server
ip tftp source-interface GigabitEthernet0
ip access-list extended 101
remark ACL 101 fulfills policies 1, 2, and 3
deny tcp 10.40.0.0 0.0.0.255 10.20.0.0 0.0.0.255 eq 22
       tcp 10.40.0.0 0.0.0.255 10.20.0.0 0.0.0.255 eq www
       tcp 10.40.0.0 0.0.0.255 host 10.30.0.1 eq www
       tcp 10.40.0.0 0.0.0.255 host 10.40.0.1 eq www
deny
       tcp 10.40.0.0 0.0.0.255 10.20.0.0 0.0.0.255 eq 443
       tcp 10.40.0.0 0.0.0.255 host 10.30.0.1 eq 443
deny
       tcp 10.40.0.0 0.0.0.255 host 10.40.0.1 eq 443
denv
deny
      icmp 10.40.0.0 0.0.0.255 10.20.0.0 0.0.0.255 echo
deny icmp 10.40.0.0 0.0.0.255 10.30.0.0 0.0.0.255 echo
permit ip any any
ip access-list extended 102
 remark ACL 102 fulfills policy 4
deny icmp 10.30.0.0 0.0.0.255 10.40.0.0 0.0.0.255 echo
permit ip any any
control-plane
banner motd ^C Authorized Users Only! ^C
line con 0
password 7 094F471A1A0A
transport input none
stopbits 1
line aux 0
stopbits 1
line vty 0 4
password 7 14141B180F0B
login local
 transport input ssh
```

end

Router R2

```
R2# show run
Building configuration...
Current configuration : 1660 bytes
version 16.9
service timestamps debug datetime msec
service timestamps log datetime msec
service password-encryption
platform qfp utilization monitor load 80
no platform punt-keepalive disable-kernel-core
hostname R2
boot-start-marker
boot-end-marker
vrf definition Mgmt-intf
 address-family ipv4
 exit-address-family
 address-family ipv6
exit-address-family
enable secret 5 $1$DKlp$gTX20dmMb.E9aCzmg74EY1
no aaa new-model
no ip domain lookup
ip domain name ccna-lab.com
login on-success log
subscriber templating
multilink bundle-name authenticated
spanning-tree extend system-id
username SSHadmin secret 5 $1$eGZ8$ltf/V6F6X90aLyQmlnyyk/
redundancy
mode none
interface GigabitEthernet0/0/0
no ip address
 negotiation auto
interface GigabitEthernet0/0/1
 ip address 10.20.0.4 255.255.255.0
 negotiation auto
interface Serial0/1/0
no ip address
interface Serial0/1/1
no ip address
interface GigabitEthernet0
vrf forwarding Mgmt-intf
no ip address
negotiation auto
ip forward-protocol nd
```

```
no ip http server
ip http secure-server
ip tftp source-interface GigabitEthernet0
ip route 0.0.0.0 0.0.0.0 10.20.0.1
control-plane
banner motd ^C Authorized Users Only! ^C
line con 0
 password 7 02050D480809
login
 transport input none
 stopbits 1
line aux 0
stopbits 1
line vty 0 4
password 7 070C285F4D06
login local
 transport input ssh
end
```

Switch S1

```
S1# show run
Building configuration...
Current configuration : 3361 bytes
version 15.2
no service pad
service timestamps debug datetime msec
service timestamps log datetime msec
service password-encryption
hostname S1
boot-start-marker
boot-end-marker
enable secret 5 $1$bRO6$r7VHZdiC7uKcY7PkQDRpT.
username SSHadmin secret 5 $1$fvd5$93v97uMBqbiGyyVm25yRO.
no aaa new-model
system mtu routing 1500
no ip domain-lookup
ip domain-name ccna-lab.com
spanning-tree mode rapid-pvst
spanning-tree extend system-id
vlan internal allocation policy ascending
interface FastEthernet0/1
switchport trunk allowed vlan 20,30,40,1000
switchport trunk native vlan 1000
 switchport mode trunk
interface FastEthernet0/2
 switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/3
switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/4
 switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/5
 switchport trunk allowed vlan 20,30,40,1000
 switchport trunk native vlan 1000
 switchport mode trunk
interface FastEthernet0/6
 switchport access vlan 30
switchport mode access
interface FastEthernet0/7
 switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/8
 switchport access vlan 999
```

```
switchport mode access
shutdown
interface FastEthernet0/9
 switchport access vlan 999
 switchport mode access
shutdown
interface FastEthernet0/10
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/11
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/12
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/13
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/14
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/15
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/16
 switchport access vlan 999
 switchport mode access
shutdown
interface FastEthernet0/17
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/18
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/19
 switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/20
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/21
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/22
```

```
switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/23
 switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/24
 switchport access vlan 999
 switchport mode access
 shutdown
interface GigabitEthernet0/1
 switchport access vlan 999
 switchport mode access
 shutdown
interface GigabitEthernet0/2
 switchport access vlan 999
 switchport mode access
 shutdown
interface Vlan1
no ip address
interface Vlan20
ip address 10.20.0.2 255.255.255.0
ip default-gateway 10.20.0.1
ip http server
ip http secure-server
banner motd ^C Authorized Users Only! ^C
line con 0
password 7 094F471A1A0A
login
line vty 0 4
 password 7 094F471A1A0A
login local
transport input ssh
line vty 5 15
 password 7 094F471A1A0A
login
```

Switch S2

```
S2# show run
Building configuration...
Current configuration: 3247 bytes
version 15.2
no service pad
service timestamps debug datetime msec
service timestamps log datetime msec
service password-encryption
hostname S2
boot-start-marker
boot-end-marker
enable secret 5 $1$gA7R$4QXuHJCsrZgVzesdOvPUW.
username SSHadmin secret 5 $1$x0mr$SlSPhEU7XXlV8Hw1.bLd3.
no aaa new-model
system mtu routing 1500
no ip domain-lookup
ip domain-name ccna-lab.com
spanning-tree mode rapid-pvst
spanning-tree extend system-id
vlan internal allocation policy ascending
interface FastEthernet0/1
switchport trunk allowed vlan 20,30,40,1000
switchport trunk native vlan 1000
 switchport mode trunk
interface FastEthernet0/2
 switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/3
switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/4
 switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/5
 switchport access vlan 20
 switchport mode access
interface FastEthernet0/6
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/7
 switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/8
 switchport access vlan 999
```

```
switchport mode access
shutdown
interface FastEthernet0/9
switchport access vlan 999
 switchport mode access
shutdown
interface FastEthernet0/10
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/11
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/12
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/13
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/14
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/15
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/16
 switchport access vlan 999
 switchport mode access
shutdown
interface FastEthernet0/17
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/18
switchport access vlan 40
switchport mode access
interface FastEthernet0/19
switchport access vlan 999
 switchport mode access
shutdown
interface FastEthernet0/20
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/21
switchport access vlan 999
switchport mode access
shutdown
interface FastEthernet0/22
 switchport access vlan 999
```

```
switchport mode access
 shutdown
interface FastEthernet0/23
 switchport access vlan 999
 switchport mode access
 shutdown
interface FastEthernet0/24
 switchport access vlan 999
 switchport mode access
 shutdown
interface GigabitEthernet0/1
 switchport access vlan 999
 switchport mode access
 shutdown
interface GigabitEthernet0/2
 switchport access vlan 999
 switchport mode access
 shutdown
interface Vlan1
no ip address
interface Vlan20
ip address 10.20.0.3 255.255.255.0
ip default-gateway 10.20.0.1
ip http server
ip http secure-server
banner motd ^C Authorized Users Only! ^C
line con 0
password 7 030752180500
login
line vty 0 4
 password 7 030752180500
 login local
transport input ssh
line vty 5 15
 password 7 030752180500
login
end
```

Download PDF & PKT file Completed 100% Score:

[sociallocker id="54558"][/sociallocker]