


# Lab - Implement Multiarea OSPFv3 (Instructor Version)

Instructor Note: Red font color or gray highlights indicate text that appears in the instructor copy only.

# **Answers: 10.1.2 Lab - Implement Multiarea OSPFv3**

# **Topology**



# **Addressing Table**

Device	Interface	IPv4 Address	IPv6 Address	IPv6 Link-Local
R1	G0/0/0	172.16.0.2/30	2001:db8:acad:a001::2/64	fe80::1:2
	G0/0/1	10.10.0.1/30	2001:db8:acad:1001::1/64	fe80::1:1
R2	Lo0	209.165.200.225/27	2001:db8:feed:209::1/64	fe80::2:3
	G0/0/0	172.16.0.1/30	2001:db8:acad:a001::1/64	fe80::2:1

Device	Interface	IPv4 Address	IPv6 Address	IPv6 Link-Local
	G0/0/1	172.16.1.1/30	2001:db8:acad:a002::1/64	fe80::2:2
R3	G0/0/0	172.16.1.2/30	2001:db8:acad:a002::2/64	fe80::3:2
	G0/0/1	10.10.4.1/30	2001:db8:acad:2001::1/64	fe80::3:1
D1	G1/0/11	10.10.0.2/30	2001:db8:acad:1001::2/64	fe80::d1:2
	G1/0/23	10.10.1.0/24	2001:db8:acad:1002::1/64	fe80::d1:1
D2	G1/0/11	10.10.4.2/30	2001:db8:acad:2001::2/64	fe80::d2:2
	G1/0/23	10.10.5.1/24	2001:db8:acad:2002::1/64	fe80::d2:1

## **Objectives**

Part 1: Build the Topology and Configure Basic Device Settings and IP Addressing

Part 2: Configure Traditional OSPFv3 for IPv6 on D1

Part 3: Configure OSPFv3 for Address Families (AF) IPv4 and AF IPv6

Part 4: Verify OSPFv3 AF Part 5: Tune OSPFv3 AF

# **Background / Scenario**

In this lab, you will configure the network with multiarea OSPFv3 routing using the AF feature for both IPv4 and IPv6 in OSPF areas 0, 1 and 2. This lab was specifically designed to use three routers and two Layer 3 switches that support OSPFv3 using AF.

It should be noted that OSPFv3 runs on top of IPv6 and uses IPv6 link local addresses for OSPFv3 control packets. Therefore, it is required that IPv6 be enabled on an OSPFv3 link, although the link may not be participating in any IPv6 AFs. Additionally, OSPFv3 AF for IPv4 unicast is not backwards compatible with OSPFv2.

**Note**: The routers used with CCNP hands-on labs are Cisco 4221 with Cisco IOS XE Release 16.9.4 (universalk9 image). Other routers and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and the output produced might vary from what is shown in the labs.

**Note**: The switches used with CCNP hands-on labs are Cisco Catalyst 3650s with Cisco IOS XE Release 16.9.4 (universalk9 image). Other switches and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and output produced might vary from what is shown in the labs.

**Note**: Ensure that the routers and switches have been erased and have no startup configurations. If you are unsure contact your instructor.

Instructor Note: Refer to the Instructor Lab Manual for the procedures to initialize and reload devices.

## **Required Resources**

- 3 Routers (Cisco 4221 with Cisco IOS XE Release 16.9.4 universal image or comparable)
- 2 Switches (Cisco 3650 with Cisco IOS XE Release 16.9.4 universal image or comparable)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

#### Instructions

# Part 1: Build the Network and Configure Basic Device Settings and Interface Addressing

In Part 1, you will set up the network topology and configure basic settings and interface addressing on routers and switches.

## Step 1: Cable the network as shown in the topology.

Attach the devices as shown in the topology diagram, and cable as necessary.

#### Step 2: Configure basic settings for each router.

a. Console into each device, enter global configuration mode, and apply the basic settings and interface addressing using the following startup configurations for each device.

#### Router R1

```
hostname R1
no ip domain lookup
line con 0
logging sync
exec-time 0 0
 exit
interface g0/0/0
 ip add 172.16.0.2 255.255.255.252
 ipv6 add 2001:db8:acad:a001::2/64
ipv6 add fe80::1:2 link-local
no shut
 exit
interface GigabitEthernet0/0/1
 ipv6 add 2001:db8:acad:1001::1/64
ipv6 add fe80::1:1 link-local
 no shut
 exit
```

#### Router R2

```
hostname R2
no ip domain lookup
line con 0
logging sync
exec-time 0 0
exit
interface g0/0/0
ip add 172.16.0.1 255.255.255.252
ipv6 add 2001:db8:acad:a001::1/64
ipv6 add fe80::2:1 link-local
no shut
exit
```

```
interface GigabitEthernet0/0/1
  ip address 172.16.1.1 255.255.255.252
  ipv6 add 2001:db8:acad:a002::1/64
  ipv6 add fe80::2:2 link-local
  no shut
  exit
int lo0
  ip add 209.165.200.225 255.255.255.224
  ipv6 add 2001:db8:feed:209::1/64
  ipv6 add fe80::2:3 link-local
  exit
```

## **Router R3**

```
hostname R3
no ip domain lookup
line con 0
logging sync
exec-time 0 0
exit
interface g0/0/0
 ip add 172.16.1.2 255.255.255.252
ipv6 add 2001:db8:acad:a002::2/64
 ipv6 add fe80::3:2 link-local
no shut
 exit
interface GigabitEthernet0/0/1
 ip address 10.10.4.1 255.255.255.252
ipv6 add 2001:db8:acad:2001::1/64
 ipv6 add fe80::3:1 link-local
 no shut
 exit
```

#### Switch D1

```
hostname D1
no ip domain lookup
line con 0
exec-timeout 0 0
logging synchronous
exit
interface g1/0/11
no switchport
ipv6 add 2001:db8:acad:1001::2/64
ipv6 add fe80::d1:2 link-local
no shutdown
exit
interface g1/0/23
```

```
no switchport
ipv6 add 2001:db8:acad:1002::1/64
ipv6 add fe80::d1:1 link-local
no shutdown
exit
```

#### Switch D2

```
host D2
no ip domain lookup
line con 0
 logging sync
 exec-time 0 0
 exit
interface gi1/0/11
 no switchport
 ip address 10.10.4.2 255.255.255.252
 ipv6 add 2001:db8:acad:2001::2/64
 ipv6 add fe80::d2:2 link-local
 no shut
 exit
interface gi1/0/23
 no switchport
 ip address 10.10.5.1 255.255.255.0
 ipv6 add 2001:db8:acad:2002::1/64
 ipv6 add fe80::d2:1 link-local
 no shut
 exit
```

b. Save the running configuration to startup-config.

# Part 2: Configure Traditional OSPFv3 for IPv6 on D1

## Step 1: Configure traditional OSPFv3 on D1.

Traditional OSPFv3 implements OSPF routing for IPv6. In this part of the lab, you will configure traditional OSPFv3 for routing IPv6 on D1, which is in the IPv6-only area.

a. OSPFv3 messages are sourced from the router's IPv6 link-local address. Earlier in this lab, IPv6 GUA and link-local addresses were statically configured on each router's interface. The link-local addresses were statically configured to make these addresses more recognizable than being automatically created using EUI-64. Issue the **show ipv6 interface brief** command to verify the GUA and link-local addresses on the router's interfaces.

#### D1# show ipv6 interface brief

```
<output omitted>
GigabitEthernet1/0/11 [up/up]
   FE80::D1:2
   2001:DB8:ACAD:1001::2
<output omitted>
GigabitEthernet1/0/23 [up/up]
   FE80::D1:1
```

```
2001:DB8:ACAD:1002::1 <output omitted>
```

b. IPv6 routing is disabled by default. Enable IPv6 routing using the **ipv6 unicast-routing** command in global configuration mode.

```
D1(config) # ipv6 unicast-routing
```

c. Most Cisco IOS versions have IPv6 CEF enabled by default when IPv6 routing is enabled. Use the show ipv6 cef command to verify whether IPv6 CEF is enabled. If you need to enable IPv6 CEF, use the ipv6 cef command. If IPv6 CEF is disabled you will see the an IOS message similar to "%IPv6 CEF not running".

```
D1# show ipv6 cef
::/0
 no route
::/127
 discard
2001:DB8:ACAD:1001::/64
 attached to GigabitEthernet1/0/11
2001:DB8:ACAD:1001::2/128
 receive for GigabitEthernet1/0/11
2001:DB8:ACAD:1002::/64
 attached to GigabitEthernet1/0/23
2001:DB8:ACAD:1002::1/128
 receive for GigabitEthernet1/0/23
FE80::/10
 receive for Null0
FF00::/8
 multicast
FF02::/16
 receive
```

d. Configure the OSPFv3 process on D1. Similar to OSPFv2, the process ID does not have to match other routers to form neighbor adjacencies, although that is considered best practice. Configure the 32-bit OSPFv3 router ID on each router. Enable OSPFv3 directly on the interfaces using the interface ipv6 ospf pid area area command.

```
D1(config)# ipv6 unicast-routing
D1(config)# ipv6 router ospf 123
D1(config-rtr)# router-id 1.1.1.2
D1(config-rtr)# exit
D1(config)# interface g1/0/11
D1(config-if)# ipv6 ospf 123 area 1
D1(config-if)# exit
D1(config-if)# interface g1/0/23
D1(config-if)# ipv6 ospf 123 area 1
D1(config-if)# ipv6 ospf 123 area 1
D1(config-if)# exit
```

e. The **show ipv6 ospf** command can be used to verify the OSPF router ID. If the OSPFv3 router ID is uses a 32-bit value other than the one specified by the **router-id** command, you can reset the router ID by using the **clear ipv6 ospf** *pid* **process** command and re-verify using the command **show ipv6 ospf**.

```
D1# show ipv6 ospf
Routing Process "ospfv3 123" with ID 1.1.1.2
```

```
Supports NSSA (compatible with RFC 3101)
Supports Database Exchange Summary List Optimization (RFC 5243)
Event-log enabled, Maximum number of events: 1000, Mode: cyclic
Router is not originating router-LSAs with maximum metric
Initial SPF schedule delay 50 msecs
Minimum hold time between two consecutive SPFs 200 msecs
Maximum wait time between two consecutive SPFs 5000 msecs
Initial LSA throttle delay 50 msecs
Minimum hold time for LSA throttle 200 msecs
Maximum wait time for LSA throttle 5000 msecs
Minimum LSA arrival 100 msecs
LSA group pacing timer 240 secs
Interface flood pacing timer 33 msecs
Retransmission pacing timer 66 msecs
Retransmission limit dc 24 non-dc 24
EXCHANGE/LOADING adjacency limit: initial 300, process maximum 300
Number of external LSA 0. Checksum Sum 0x000000
Number of areas in this router is 1. 1 normal 0 stub 0 nssa
Graceful restart helper support enabled
Reference bandwidth unit is 100 mbps
RFC1583 compatibility enabled
       Number of interfaces in this area is 2
       SPF algorithm executed 5 times
       Number of LSA 12. Checksum Sum 0x0486C1
       Number of DCbitless LSA 0
       Number of indication LSA 0
       Number of DoNotAge LSA 0
       Flood list length 0
```

f. The **show ipv6 protocols** command can be used to verify general OSPFv3 information such as areas and enabled interfaces.

```
D1# show ipv6 protocols

IPv6 Routing Protocol is "connected"

IPv6 Routing Protocol is "ND"

IPv6 Routing Protocol is "ospf 123"

Router ID 1.1.1.2

Number of areas: 1 normal, 0 stub, 0 nssa

Interfaces (Area 1):

GigabitEthernet1/0/23

GigabitEthernet1/0/11

Redistribution:

None
```

# Part 3: Configure OSPFv3 for AF IPv4 and AF IPv6

OSPFv3 with the address family (AF) unifies OSPF configuration for both IPv4 and IPv6. Each OSPFv3 AF is a single process, so you may have two processes per interface, but only one process per AF. OSPFv3 messages are sent over IPv6 which requires that IPv6 routing is enabled and that the interface has a link-local IPv6 address. This is the requirement even if only the IPv4 AF is configured.

In this section you will configure OSPFv3 with AF for the IPv4 and IPv6 address families on R1, R2, R3, D1 and D2.

## Step 1: Configure OSPFv3 with AF on R1.

a. After enabling IPv6 unicast routing, configure OSPFv3 with AF on R1 using the **router ospfv3** *pid* command. Use the **?** to see the address families available.

```
R1(config)# ipv6 unicast-routing
R1(config)# router ospfv3 123
R1(config-router)# address-family ?
  ipv4 Address family
  ipv6 Address family
```

b. Next, specify the AF for IPv4 and use the ? to see the available options.

```
R1(config-router)# address-family ipv4 ?
unicast Address Family modifier
vrf Specify parameters for a VPN Routing/Forwarding instance
```

c. Enter the AF for IPv4 unicast using the command address-family ipv4 unicast. Use the ? to examine the options in AF configuration mode. Some of the more common configuration commands are highlighted. Use the router-id command to configure the router ID for the IPv4 AF.

```
R1(config-router) # address-family ipv4 unicast
R1(config-router-af) # ?
Router Address Family configuration commands:
```

adjacency Control adjacency formation

aajaconoj	omerer adjacome, rermacrem
area	OSPF area parameters
authentication	Authentication parameters
auto-cost	Calculate OSPF interface cost according to bandwidth
auto-cost-determination	Calculate OSPF interface cost according to bandwidth
bfd	BFD configuration commands
compatible	Compatibility list
default	Set a command to its defaults
default-information	Control distribution of default information
default-metric	Set metric of redistributed routes
discard-route	Enable or disable discard-route installation
distance	Define an administrative distance
distribute-list	Filter networks in routing updates
event-log	Event Logging
exit-address-family	Exit from Address Family configuration mode
graceful-restart	Graceful-restart options
help	Description of the interactive help system
ignore	Do not complain about specific event
interface-id	Source of the interface ID
limit	Limit a specific OSPF feature
local-rib-criteria	Enable or disable usage of local RIB as route
	criteria
log-adjacency-changes	Log changes in adjacency state
manet	Specify MANET OSPF parameters

max-lsa

Maximum number of non self-generated LSAs to accept

```
max-metric
                           Set maximum metric
 maximum-paths
                           Forward packets over multiple paths
 mpls
                           MPLS Traffic Engineering configs
                           Negate a command or set its defaults
 no
  passive-interface
                           Suppress routing updates on an interface
 prefix-suppression
                           Enable prefix suppression
 process-min-time
                           Percentage of quantum to be used before releasing
                           CPU
 queue-depth
                           Hello/Router process queue depth
  redistribute
                           Redistribute information from another routing
                           protocol
  router-id
                           router-id for this OSPF process
  shutdown
                           Shutdown the router process
                           Modify snmp parameters
  snmp
                           Enable or disable OSPF statistics options
  statistics
                           Configure IP address summaries
  summary-address
  summary-prefix
                           Configure IP address summaries
                           Adjust routing timers
 timers
R1(config-router-af)#
R1(config-router-af) # router-id 1.1.1.1
```

d. Exit the IPv4 AF configuration mode and enter the AF IPv6 configuration mode. The exit-address-family (or a shorter version of exit) command is used exit address family configuration mode. Issue the address-family ipv6 unicast command to enter the IPv6 AF. For the IPv6 AF, use the router-id command to configure the router ID. It isn't necessary to configure a different router ID for IPv6 AF but it is a valid option. The exit command is used to return to global configuration mode.

```
R1(config-router-af)# exit-address-family
R1(config-router)# address-family ipv6 unicast
R1(config-router-af)# router-id 1.1.1.1
R1(config-router-af)# exit-address-family
R1(config-router)# exit
```

e. OSPFv3 is enabled directly on the interfaces for both IPv4 and IPv6 AFs using the **ospfv3** *pid* [ **ipv4** | **ipv6** ] **area** *area-id* interface command. Use this command to enable OSPFv3 on both of R1's interfaces.

```
R1(config)# interface g0/0/0
R1(config-if)# ospfv3 123 ipv4 area 0
R1(config-if)# ospfv3 123 ipv6 area 0
R1(config-if)# exit
R1(config)# interface g0/0/1
R1(config-if)# ospfv3 123 ipv4 area 1
R1(config-if)# ospfv3 123 ipv6 area 1
```

#### Step 2: Configure OSPFv3 with AF IPv4 and AF IPv6 on R2.

Enable IPv6 unicast routing and configure the OSPFv3 with AF for both IPv4 and IPv6 on R2, similar to the configuration for R1.

```
R2(config)# ipv6 unicast-routing
R2(config)# router ospfv3 123
```

```
R2(config-router-af)# router-id 2.2.2.1
R2(config-router-af)# exit-address-family
R2(config-router)# address-family ipv6 unicast
R2(config-router-af)# router-id 2.2.2.1
R2(config-router-af)# exit-address-family
R2(config-router)# exit

R2(config-router)# exit

R2(config)# interface g0/0/0
R2(config-if)# ospfv3 123 ipv4 area 0
R2(config-if)# ospfv3 123 ipv6 area 0
R2(config-if)# exit
R2(config-if)# exit
R2(config-if)# ospfv3 123 ipv4 area 0
R2(config-if)# ospfv3 123 ipv4 area 0
R2(config-if)# ospfv3 123 ipv4 area 0
R2(config-if)# ospfv3 123 ipv6 area 0
```

R2(config-router) # address-family ipv4 unicast

#### Step 3: Configure OSPFv3 with IPv4 AF and IPv6 AF on R3.

Enable IPv6 unicast routing and configure the OSPFv3 with AF for both IPv4 and IPv6 on R3, similar to the configurations for R1 and R2. On R3, set the router ID for both IPv4 AF and IPv6 AF with a single command as shown.

```
R3(config)# ipv6 unicast-routing

R3(config)# router ospfv3 123

R3(config-router)# router-id 3.3.3.1

R3(config-router)# address-family ipv4 unicast
R3(config-router-af)# exit-address-family
R3(config-router)# address-family ipv6 unicast
R3(config-router-af)# exit-address-family
R3(config-router)# exit

R3(config-router)# exit

R3(config)# interface g0/0/0

R3(config-if)# ospfv3 123 ipv4 area 0
R3(config-if)# ospfv3 123 ipv6 area 0
R3(config-if)# exit
R3(config-if)# ospfv3 123 ipv4 area 2
R3(config-if)# ospfv3 123 ipv4 area 2
R3(config-if)# ospfv3 123 ipv6 area 2
```

#### Step 4: Configure OSPFv3 with AF on D2.

a. Enter the following command to enable routing for IPv4. (This may not be required on depending on model and IOS.)

```
D2(config)# ip routing
```

b. Enter the following command to enable routing for IPv6. (This may not be required on depending on model and IOS.)

```
D2(config) # ipv6 unicast-routing
```

**Note**: By default, the 3650 supports IPv6 interface configuration.

c. Configure the OSPFv3 with AF for both IPv4 and IPv6 on D2, similar to the configurations for R1, R2 and R3.

```
D2(config) # router ospfv3 123

D2(config-router) # address-family ipv4 unicast

D2(config-router-af) # router-id 3.3.3.2

D2(config-router-af) # exit-address-family

D2(config-router) # address-family ipv6 unicast

D2(config-router-af) # router-id 3.3.3.2

D2(config-router-af) # exit-address-family

D2(config-router) # exit

D2(config-router) # exit

D2(config-if) # ospfv3 123 ipv4 area 2

D2(config-if) # ospfv3 123 ipv6 area 2

D2(config-if) # exit

D2(config-if) # ospfv3 123 ipv4 area 2

D2(config-if) # ospfv3 123 ipv4 area 2
```

# Part 4: Verify OSPFv3

The commands to verify traditional OSPFv3 and OSPFv3 with AF may differ. This is because OSPFv3 with AF commands include information for both IPv4 and IPv6 address families, whereas traditional OSPFv3 is for IPv6 only.

#### Step 1: Verifying neighbor adjacencies.

a. Use the **show ipv6 ospf neighbor** command on D1 to display OSPFv3 neighbors. This is a command used for routers configured with traditional OSPFv3. The equivalent command for OSPFv2 would be **show ip ospf neighbor**.

```
D1# show ipv6 ospf neighbor
```

```
OSPFv3 Router with ID (1.1.1.2) (Process ID 123)

Neighbor ID Pri State Dead Time Interface ID Interface

1.1.1.1 1 FULL/DR 00:00:39 6 GigabitEthernet1/0/11
```

 This same command on a router running OSPFv3 with AF would generate similar output. For example, on R1 issue the same **show ipv6 ospf neighbor** command. Notice the output is only OSPFv3 for the IPv6 AF

```
R1# show ipv6 ospf neighbor
```

```
OSPFv3 Router with ID (1.1.1.1) (Process ID 123)
Neighbor ID
               Pri
                     State
                                    Dead Time
                                                Interface ID
                                                                Interface
                                                                GigabitEthernet0/0/0
2.2.2.1
                 1 FULL/BDR
                                    00:00:31
                                                5
1.1.1.2
                 1 FULL/BDR
                                    00:00:38
                                                471
                                                                GigabitEthernet0/0/1
```

c. Now, issue the **show ospfv3 neighbor** command on R1. This is a command used for routers configured for OSPFv3 with AF. Notice the output includes neighbors for both IPv4 and IPv6 address families.

#### R1# show ospfv3 neighbor

```
OSPFv3 123 address-family ipv4 (router-id 1.1.1.1)
Neighbor ID
               Pri
                     State
                                     Dead Time
                                                 Interface ID
                                                                Interface
                                                                GigabitEthernet0/0/0
2.2.2.1
                                     00:00:38
                 1
                     FULL/BDR
         OSPFv3 123 address-family ipv6 (router-id 1.1.1.1)
Neighbor ID
               Pri
                     State
                                     Dead Time
                                                 Interface ID
                                                                Interface
2.2.2.1
                 1
                     FULL/BDR
                                     00:00:32
                                                                GigabitEthernet0/0/0
                     FULL/BDR
                                     00:00:30
                                                                GigabitEthernet0/0/1
1.1.1.2
                 1
                                                 471
```

Traditional OSPFv3 commands are similar to those for OSPFv2, except **ipv6** is used as an argument instead of **ip**, for example **show ip ospf neighbor** and **show ipv6 ospf neighbor**. OSPFv3 with AF uses the argument ospfv3 which includes both OSPF for IPv4 and IPv6 AFs. For example, **show ospfv3 neighbor**.

Traditional OSPFv3 commands can be used when a router is configured for OSPFv3 with AF, but the OSPFv3 AF router will only show OSPF for IPv6 AF information. OSPFv3 with AF commands cannot be used on routers configured with traditional OSPFv3.

To summarize the **show** command arguments:

- OSPFv2: Use show ip ospf (IPv4 only)
- Traditional OSPFv3: Use show ipv6 ospf (IPv6 only)
- OSPFv3 with AF: Use show ospfv3 (IPv4 and IPv6 AF) or show ipv6 ospf (IPv6 only)

Why does the show ipv6 ospf neighbor command only display OSPFv3 neighbors in the IPv6 AF?

The show ipv6 ospf neighbor command is used to display OSPFv3 neighbor adjacencies, specifically for IPv6 indicated by the ipv6 keyword in the command. The router ID 1.1.1.6 and 3.3.3.6 are associated with the IPv6 AF.

#### Step 2: Examining the IP routing tables.

a. Use the **show ipv6 route ospf** command on D1 to display OSPFv3 routing entries in the IPv6 routing table.

```
D1# show ipv6 route ospf

IPv6 Routing Table - default - 9 entries

Codes: C - Connected, L - Local, S - Static, U - Per-user Static route

B - BGP, R - RIP, H - NHRP, I1 - ISIS L1

I2 - ISIS L2, IA - ISIS interarea, IS - ISIS summary, D - EIGRP

EX - EIGRP external, ND - ND Default, NDp - ND Prefix, DCE - Destination

NDr - Redirect, RL - RPL, O - OSPF Intra, OI - OSPF Inter

OE1 - OSPF ext 1, OE2 - OSPF ext 2, ON1 - OSPF NSSA ext 1

ON2 - OSPF NSSA ext 2, la - LISP alt, lr - LISP site-registrations

ld - LISP dyn-eid, lA - LISP away, le - LISP extranet-policy
```

OI 2001:DB8:ACAD:2001::/64 [110/4]

```
via FE80::1:1, GigabitEthernet1/0/11
OI 2001:DB8:ACAD:2002::/64 [110/5]
    via FE80::1:1, GigabitEthernet1/0/11
OI 2001:DB8:ACAD:A001::/64 [110/2]
    via FE80::1:1, GigabitEthernet1/0/11
OI 2001:DB8:ACAD:A002::/64 [110/3]
    via FE80::1:1, GigabitEthernet1/0/11
```

Display the routes using the **show ip route ospf**. Why are there no routes displayed using this command?

# D1 is in an IPv6-only area. D1 is only implementing traditional OSPFv3 for IPv6 and has not been configured for OSPFv2 for IPv4.

b. Understanding the difference between commands associated with OSPFv2 and OSPFv3 can seem challenging at times. The **show ip route ospfv3** command is used to view OSPFv3 routes in the IPv4 routing table. The **show ipv6 route ospf** command is used to view OSPFv3 routes in the IPv6 routing table. The **show ipv6 route ospf** command is the same command used with traditional OSPFv3 for IPv6.

```
R1# show ip route ospf
```

```
R1# show ip route ospfv3
```

```
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2
      i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
      ia - IS-IS inter area, * - candidate default, U - per-user static route
      o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
      a - application route
       + - replicated route, % - next hop override, p - overrides from PfR
Gateway of last resort is not set
      10.0.0.0/8 is variably subnetted, 4 subnets, 3 masks
O IA
        10.10.4.0/30 [110/3] via 172.16.0.1, 00:17:34, GigabitEthernet0/0/0
        10.10.5.0/24 [110/4] via 172.16.0.1, 00:17:34, GigabitEthernet0/0/0
O IA
      172.16.0.0/16 is variably subnetted, 3 subnets, 2 masks
        172.16.1.0/30 [110/2] via 172.16.0.1, 00:17:34, GigabitEthernet0/0/0
```

## R1# show ipv6 route ospfv3

% Invalid input detected at '^' marker.

#### R1# show ipv6 route ospf

```
IPv6 Routing Table - default - 9 entries
Codes: C - Connected, L - Local, S - Static, U - Per-user Static route
    B - BGP, R - RIP, H - NHRP, I1 - ISIS L1
    I2 - ISIS L2, IA - ISIS interarea, IS - ISIS summary, D - EIGRP
    EX - EIGRP external, ND - ND Default, NDp - ND Prefix, DCE - Destination
```

```
NDr - Redirect, RL - RPL, O - OSPF Intra, OI - OSPF Inter
OE1 - OSPF ext 1, OE2 - OSPF ext 2, ON1 - OSPF NSSA ext 1
ON2 - OSPF NSSA ext 2, a - Application
0 2001:DB8:ACAD:1002::/64 [110/2]
    via FE80::D1:2, GigabitEthernet0/0/1
OI 2001:DB8:ACAD:2001::/64 [110/3]
    via FE80::2:1, GigabitEthernet0/0/0
OI 2001:DB8:ACAD:2002::/64 [110/4]
    via FE80::2:1, GigabitEthernet0/0/0
0 2001:DB8:ACAD:A002::/64 [110/2]
    via FE80::2:1, GigabitEthernet0/0/0
```

Why doesn't the show ip route ospf command display any routes on R1?

The show ip route ospf command is used to display OSPFv2 routes in the IPv4 routing table. R1 is implementing OSPFv3.

#### Step 3: Examining the OSPF LSDB.

 a. D1 is running traditional OSPFv3. The show ipv6 ospf database command is used to display a summary of the OSPFv3 LSDB.

#### D1# show ipv6 ospf database

```
OSPFv3 Router with ID (1.1.1.2) (Process ID 123)
                Router Link States (Area 1)
ADV Router
                Age
                             Seq#
                                         Fragment ID Link count Bits
1.1.1.1
                1096
                             0x80000009 0
 1.1.1.2
                1110
                             0x80000005 0
                                                                 None
                Net Link States (Area 1)
ADV Router
                                        Link ID
                Age
                             Seq#
                                                   Rtr count
                             0x80000001 6
 1.1.1.1
                1152
                Inter Area Prefix Link States (Area 1)
ADV Router
                Age
                             Seq#
                                        Prefix
                1096
                             0x80000003 2001:DB8:ACAD:A001::/64
 1.1.1.1
1.1.1.1
                1096
                             0x80000003 2001:DB8:ACAD:A002::/64
 1.1.1.1
                 833
                             0x80000005 2001:DB8:ACAD:2001::/64
 1.1.1.1
                1497
                             0x80000002 2001:DB8:ACAD:2002::/64
                Link (Type-8) Link States (Area 1)
ADV Router
                Age
                             Seq#
                                         Link ID Interface
 1.1.1.2
                 1150
                             0x80000001 39
                                                    Gi1/0/23
 1.1.1.1
                 1096
                             0x80000006 6
                                                    Gi1/0/11
```

1.1.1.2	1151	0x80000001	38	Gi1/0/11	
	Intra Area	a Prefix Link S	tates (Area	1)	
ADV Router	Age	Seq#	Link ID	Ref-lstype	Ref-LSID
1.1.1.1	1152	0x8000001	6144	0x2002	6
1.1.1.2	1150	0x80000003	0	0x2001	0
D1 io ruppina O	SDEv2 with AE	The chaw confu	2 databasa s	ommand is us	ad to display a summary

b. R1 is running OSPFv3 with AF. The **show ospfv3 database** command is used to display a summary of the OSPFv3 LSDB for both the IPv4 and IPv6 AFs.

#### R1# show ospfv3 database

C	SPFv3 123 addres	ss-family ipv4	(router-id	1.1.1.1)	
	Router Link	States (Area	0)		
ADV Router	Age	Seq#	Fragment II	D Link coun	t Bits
1.1.1.1	532	0x80000005	0	1	None
2.2.2.1	508	0x80000008	0	2	None
3.3.3.1	507	0x80000006	0	1	В
	Net Link St	cates (Area 0)			
ADV Router	Age	Seq#	Link ID	Rtr count	
2.2.2.1	539	0x8000001	5	2	
3.3.3.1	512	0x80000001	5	2	
	Inter Area	Prefix Link S	tates (Area	0)	
ADV Router	Age	Seq#	Prefix		
3.3.3.1	553	0x8000001	10.10.4.0/	30	
3.3.3.1	513	0x80000001	10.10.5.0/	24	
	Link (Type-	-8) Link State	s (Area 0)		
ADV Router	Age	Seq#	Link ID	Interface	
1.1.1.1	579	0x8000001	5	Gi0/0/0	
2.2.2.1	579	0x80000001	5	Gi0/0/0	
	Intra Area	Prefix Link S	tates (Area	0)	
ADV Router	Age	Seq#	Link ID	Ref-lstype	Ref-LSID
2.2.2.1	539	0x8000001	5120	0x2002	5
3.3.3.1	512	0x80000001	5120	0x2002	5
	Router Link	States (Area	1)		
ADV Router	Age	Seq#	Fragment II	D Link coun	t Bits
1.1.1.1	602	0x80000001	0	0	None

	OSPFv3 123 addres	s-family ipv6	(router-id	1.1.1.1)	
	Router Link	States (Area	0)		
30110		Q		D T' 1	. 5
ADV Router	-	Seq#	-	D Link coun	
1.1.1.1	530	0x80000005	0	1	В
2.2.2.1	508	0x80000009	0	2	None
3.3.3.1	508	0x80000006	0	1	В
	Net Link St	ates (Area 0)			
	1,00 11111 00	(11100 0)			
ADV Router	Age	Seq#	Link ID	Rtr count	
2.2.2.1	539	0x80000001	5	2	
3.3.3.1	511	0x80000001	5	2	
	Inter Area	Prefix Link S	tates (Area	0)	
ADV Router	Age	Seq#	Prefix		
1.1.1.1	579	-	2001:DB8:A0	CAD:1001::/6	4
1.1.1.1	559			CAD:1002::/6	
3.3.3.1	551	0x80000001	2001:DB8:A	CAD:2001::/6	4
3.3.3.1	512	0x80000001	2001:DB8:A	CAD:2002::/6	4
	Link (Type-	8) Link State	s (Area 0)		
ADV Router	Age	Seq#	Link ID	Interface	
1.1.1.1	578	0x80000002	5	Gi0/0/0	
2.2.2.1	578	0x80000002	5	Gi0/0/0	
	Intra Area	Prefix Link S	tates (Area	0)	
ADV Router	: Age	Seq#	Link ID	Ref-lstype	Ref-LSID
2.2.2.1	539	0x80000001	5120	0x2002	5
3.3.3.1	511	0x80000001	5120	0x2002	5
	Dantan Tinh	C+ - + / 7	1.\		
	Router Link	States (Area	1)		
ADV Router	Age	Seq#	Fragment II	D Link coun	t Bits
1.1.1.1	553	0x80000006	0	1	В
1.1.1.2	552	0x80000025	0	1	None
	Net Link St	ates (Area 1)			
		(			
ADV Router	Age	Seq#	Link ID	Rtr count	
1.1.1.2	560	0x80000001	38	2	
	Inter Area	Prefix Link S	tates (Area	1)	
ADV Router	Age	Seq#	Prefix		

1.1.1.1	578	0x80000001	2001:DB8:A	CAD:A001::/6	4
1.1.1.1	538	0x80000001	2001:DB8:A	CAD:A002::/6	4
1.1.1.1	506	0x80000001	2001:DB8:A	CAD:2002::/6	4
1.1.1.1	506	0x80000001	2001:DB8:A	CAD:2001::/6	4
	Link (Type	-8) Link State	s (Area 1)		
ADV Router	Age	Seq#	Link ID	Interface	
1.1.1.1	559	0x8000000C	6	Gi0/0/1	
1.1.1.2	598	0x80000002	38	Gi0/0/1	
	Intra Area	Prefix Link S	tates (Area	1)	
ADV Router	Age	Seq#	Link ID	Ref-lstype	Ref-LSID
1.1.1.2	481	0x80000016	0	0x2001	0
1.1.1.2	560	0x80000001	38912	0x2002	38

What would the show ipv6 route database command display on R1, if anything?

The show ipv6 ospf database command can also be used on R1, but it will only display OSPFv3 IPv6 AF information.

#### Part 5: Tune OSPFv3

#### Step 1: Configuring a passive interface.

a. To configure a passive interface in traditional OSPFv3, use the **passive-interface** command in OSPFv3 router mode.

```
D1(config)# ipv6 router ospf 123
D1(config-rtr)# passive-interface g1/0/23
```

b. To configure a passive interface in OSPFv3 with AF, you can use the **passive-interface** command in OSPFv3 router mode to configure the passive interface for both IPv4 and IPv6 AFs.

```
D2(config) # router ospfv3 123
D2(config-router) # passive-interface g1/0/23
```

c. As an alternative, you can use the **passive-interface** command within AF configuration mode to configure the passive interface for a specific AFs.

```
D2(config-router)# no passive-interface g1/0/23
D2(config-router)# address-family ipv4 unicast
D2(config-router-af)# passive-interface g1/0/23
D2(config-router-af)# exit-address-family
D2(config-router)# address-family ipv6 unicast
D2(config-router-af)# passive-interface g1/0/23
D2(config-router-af)# exit-address-family
```

#### Step 2: Configuring summarization.

a. The **area** area **range** *ipv6-summary-address* command is used to summarize prefixes from one are into another. The *area* is the area from which the prefixes are summarized.

```
R1(config) # router ospfv3 123
R1(config-router) # address-family ipv6 unicast
R1(config-router-af) # area 1 range 2001:db8:acad:1000::/52
R3(config) # router ospfv3 123
R3(config-router) # address-family ipv6 unicast
R3(config-router-af) # area 2 range 2001:db8:acad:2000::/52
```

b. Notice that R2 is now receiving the summarized prefixes.

Why is prefix summarization considered desirable? How does it stabilize routing?

It reduces the number of routes in the routing table and stabilizes routing performance. As long as at least one subnet is still available within the summarized prefix, the aggregated route will continue to be advertised.

## Step 3: Modifying the network type.

a. OSPFv3 supports the same network types as OSPFv2. Notice that the Ethernet interfaces between R2 and R1, and R2 and R3, elect a DR and a BDR. This is because Ethernet is a multiaccess network. However, these are point-to-point links and there is no need for a DR or BDR.

#### R2# show ospfv3 interface brief

Interface	PID	Area	AF	Cost	State	Nbrs	F/C
Gi0/0/1	123	0	ipv4	1	BDR	1/1	
Gi0/0/0	123	0	ipv4	1	DR	1/1	
Gi0/0/1	123	0	<mark>ipv6</mark>	1	BDR	1/1	
Gi0/0/0	123	0	ipv6	1	<mark>DR</mark>	1/1	

b. These connections can be changed to point-to-point using the **ospfv3 network point-to-point** interface command. This command needs to be configured one both sides of the point to point interface.

```
R2(config)# interface g0/0/1
R2(config-if)# ospfv3 network point-to-point
R2(config-if)# exit
R2(config)# interface g0/0/0
R2(config-if)# ospfv3 network point-to-point
R1(config)# interface g0/0/0
R1(config-if)# ospfv3 network point-to-point
R3(config)# interface g0/0/0
R3(config)# interface g0/0/0
R3(config-if)# ospfv3 network point-to-point
```

c. Notice that the links have now change to P2P.

R2#	show	ospfv3	interface	brief				
Inte	rface	PID	Area	AF	Cost	State	Nbrs	F/C
Gi0/	0/1	123	0	ipv4	1	P2P	1/1	
Gi0/	0/0	123	0	ipv4	1	P2P	1/1	
Gi0/	0/1	123	0	ipv6	1	P2P	1/1	
Gi0/	0/0	123	0	<mark>ipv6</mark>	1	P2P	1/1	

What is the effect on the state of the interface when changing a broadcast network to point-to-point?

#### There is no longer a DR or BDR on the multiaccess network.

#### Step 4: Advertising a default route.

a. Similar to OSPFv2, an ASBR in OSPFv3 advertises using the **default-information** command. Configure a static default route for IPv4 and IPv6 on R2.

**Note**: Without a default route in the routing table, OSPF would require the **default-information originate always** command to advertise a default route.

```
R2(config) # ipv6 route ::/0 lo0
R2(config) # ip route 0.0.0.0 0.0.0 lo0

R2(config) # router ospfv3 123
R2(config-router) # address-family ipv6 unicast
R2(config-router-af) # default-information originate
R2(config-router-af) # exit
R2(config-router) # address-family ipv4 unicast
R2(config-router) # default-information originate
R2(config-router) # default-information originate
R2(config-router-af) # default-information originate
```

b. Verify D1 is receiving an IPv6 default route via OSPFv3.

#### D1# show ipv6 route ospf

```
<output omitted>
OE2 ::/0 [110/1], tag 123
      via FE80::1:1, GigabitEthernet1/0/11
OI 2001:DB8:ACAD:2000::/52 [110/5]
      via FE80::1:1, GigabitEthernet1/0/11
OI 2001:DB8:ACAD:A001::/64 [110/2]
      via FE80::1:1, GigabitEthernet1/0/11
OI 2001:DB8:ACAD:A002::/64 [110/3]
      via FE80::1:1, GigabitEthernet1/0/11
```

c. Verify D2 is receiving an IPv4 default route via OSPFv3.

```
D2# show ip route ospfv3
<output omitted>
Gateway of last resort is 10.10.4.1 to network 0.0.0.0

O*E2 0.0.0.0/0 [110/1] via 10.10.4.1, 00:01:13, GigabitEthernet1/0/11
172.16.0.0/30 is subnetted, 2 subnets
```

```
O IA 172.16.0.0 [110/3] via 10.10.4.1, 00:02:55, GigabitEthernet1/0/11 O IA 172.16.1.0 [110/2] via 10.10.4.1, 00:20:22, GigabitEthernet1/0/11
```

## **Router Interface Summary Table**

Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2
1800	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2801	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)
2811	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
4221	Gigabit Ethernet 0/0/0 (G0/0/0)	Gigabit Ethernet 0/0/1 (G0/0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)
4300	Gigabit Ethernet 0/0/0 (G0/0/0)	Gigabit Ethernet 0/0/1 (G0/0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)

**Note**: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.

## **Device Configs - Final**

#### Router R1

```
R1# show run
Building configuration...
```

```
Current configuration: 3836 bytes

!
version 16.9
service timestamps debug datetime msec
service timestamps log datetime msec
platform qfp utilization monitor load 80
no platform punt-keepalive disable-kernel-core
!
hostname R1
!
boot-start-marker
boot-end-marker
```

```
no aaa new-model
no ip domain lookup
login on-success log
subscriber templating
ipv6 unicast-routing
multilink bundle-name authenticated
spanning-tree extend system-id
redundancy
mode none
interface GigabitEthernet0/0/0
ip address 172.16.0.2 255.255.255.252
negotiation auto
ipv6 address FE80::1:2 link-local
ipv6 address 2001:DB8:ACAD:A001::2/64
ospfv3 network point-to-point
ospfv3 123 ipv6 area 0
ospfv3 123 ipv4 area 0
interface GigabitEthernet0/0/1
no ip address
negotiation auto
ipv6 address FE80::1:1 link-local
ipv6 address 2001:DB8:ACAD:1001::1/64
ospfv3 123 ipv6 area 1
ospfv3 123 ipv4 area 1
interface Serial0/1/0
interface Serial0/1/1
router ospfv3 123
address-family ipv4 unicast
 router-id 1.1.1.1
exit-address-family
address-family ipv6 unicast
router-id 1.1.1.1
area 1 range 2001:DB8:ACAD:1000::/52
exit-address-family
ip forward-protocol nd
```

```
ip http server
ip http authentication local
ip http secure-server
!
control-plane
!
line con 0
  exec-timeout 0 0
  logging synchronous
  transport input none
  stopbits 1
line aux 0
  stopbits 1
line vty 0 4
  login
!
end
```

#### Router R2

```
R2# show run
```

Building configuration...

```
Current configuration: 4068 bytes
version 16.9
service timestamps debug datetime msec
service timestamps log datetime msec
platform qfp utilization monitor load 80
no platform punt-keepalive disable-kernel-core
hostname R2
boot-start-marker
boot-end-marker
no aaa new-model
no ip domain lookup
login on-success log
subscriber templating
ipv6 unicast-routing
multilink bundle-name authenticated
spanning-tree extend system-id
```

```
redundancy
mode none
interface Loopback0
ip address 209.165.200.225 255.255.255.224
ipv6 address FE80::2:3 link-local
ipv6 address 2001:DB8:FEED:209::1/64
interface GigabitEthernet0/0/0
ip address 172.16.0.1 255.255.255.252
negotiation auto
ipv6 address FE80::2:1 link-local
ipv6 address 2001:DB8:ACAD:A001::1/64
ospfv3 network point-to-point
ospfv3 123 ipv6 area 0
ospfv3 123 ipv4 area 0
interface GigabitEthernet0/0/1
ip address 172.16.1.1 255.255.255.252
negotiation auto
ipv6 address FE80::2:2 link-local
ipv6 address 2001:DB8:ACAD:A002::1/64
ospfv3 network point-to-point
ospfv3 123 ipv6 area 0
ospfv3 123 ipv4 area 0
router ospfv3 123
address-family ipv4 unicast
 default-information originate
router-id 2.2.2.1
exit-address-family
address-family ipv6 unicast
default-information originate
 router-id 2.2.2.1
exit-address-family
ip forward-protocol nd
no ip http server
ip http secure-server
ip route 0.0.0.0 0.0.0.0 Loopback0
ipv6 route ::/0 Loopback0
control-plane
line con 0
exec-timeout 0 0
logging synchronous
```

```
transport input none
stopbits 1
line aux 0
stopbits 1
line vty 0 4
login
!
end
```

#### Router R3

#### R3# show run

Building configuration...

```
Current configuration: 3859 bytes
version 16.9
service timestamps debug datetime msec
service timestamps log datetime msec
platform qfp utilization monitor load 80
no platform punt-keepalive disable-kernel-core
hostname R3
boot-start-marker
boot-end-marker
no aaa new-model
no ip domain lookup
login on-success log
subscriber templating
ipv6 unicast-routing
multilink bundle-name authenticated
spanning-tree extend system-id
redundancy
mode none
interface GigabitEthernet0/0/0
ip address 172.16.1.2 255.255.255.252
negotiation auto
ipv6 address FE80::3:2 link-local
ipv6 address 2001:DB8:ACAD:A002::2/64
ospfv3 network point-to-point
```

```
ospfv3 123 ipv6 area 0
ospfv3 123 ipv4 area 0
interface GigabitEthernet0/0/1
ip address 10.10.4.1 255.255.255.252
negotiation auto
ipv6 address FE80::3:1 link-local
ipv6 address 2001:DB8:ACAD:2001::1/64
ospfv3 123 ipv6 area 2
ospfv3 123 ipv4 area 2
interface Serial0/1/0
interface Serial0/1/1
router ospfv3 123
router-id 3.3.3.1
address-family ipv4 unicast
exit-address-family
!
address-family ipv6 unicast
area 2 range 2001:DB8:ACAD:2000::/52
exit-address-family
ip forward-protocol nd
ip http server
ip http authentication local
ip http secure-server
control-plane
line con 0
exec-timeout 0 0
logging synchronous
transport input none
stopbits 1
line aux 0
stopbits 1
line vty 0 4
login
!
end
```

## Switch D1

```
D1# show run
Building configuration...
```

Current configuration: 6542 bytes

```
version 16.9
no service pad
service timestamps debug datetime msec
service timestamps log datetime msec
! Call-home is enabled by Smart-Licensing.
service call-home
no platform punt-keepalive disable-kernel-core
hostname D1
vrf definition Mgmt-vrf
- !
address-family ipv4
exit-address-family
address-family ipv6
exit-address-family
no aaa new-model
switch 1 provision ws-c3650-24ps
no ip domain lookup
login on-success log
ipv6 unicast-routing
license boot level ipservicesk9
diagnostic bootup level minimal
spanning-tree mode rapid-pvst
spanning-tree extend system-id
redundancy
mode sso
transceiver type all
monitoring
class-map match-any system-cpp-police-topology-control
 description Topology control
class-map match-any system-cpp-police-sw-forward
 description Sw forwarding, L2 LVX data, LOGGING
class-map match-any system-cpp-default
 description Inter FED, EWLC control, EWLC data
class-map match-any system-cpp-police-sys-data
description Learning cache ovfl, High Rate App, Exception, EGR Exception,
NFLSAMPLED DATA, RPF Failed
class-map match-any system-cpp-police-punt-webauth
```

```
description Punt Webauth
class-map match-any system-cpp-police-121vx-control
  description L2 LVX control packets
class-map match-any system-cpp-police-forus
description Forus Address resolution and Forus traffic
class-map match-any system-cpp-police-multicast-end-station
 description MCAST END STATION
class-map match-any system-cpp-police-multicast
  description Transit Traffic and MCAST Data
class-map match-any system-cpp-police-12-control
 description L2 control
class-map match-any system-cpp-police-dot1x-auth
  description DOT1X Auth
class-map match-any system-cpp-police-data
  description ICMP redirect, ICMP GEN and BROADCAST
class-map match-any system-cpp-police-stackwise-virt-control
  description Stackwise Virtual
class-map match-any non-client-nrt-class
class-map match-any system-cpp-police-routing-control
  description Routing control and Low Latency
class-map match-any system-cpp-police-protocol-snooping
description Protocol snooping
class-map match-any system-cpp-police-dhcp-snooping
  description DHCP snooping
class-map match-any system-cpp-police-system-critical
  description System Critical and Gold Pkt
policy-map system-cpp-policy
interface GigabitEthernet0/0
vrf forwarding Mgmt-vrf
no ip address
negotiation auto
interface GigabitEthernet1/0/1
interface GigabitEthernet1/0/2
interface GigabitEthernet1/0/3
interface GigabitEthernet1/0/4
interface GigabitEthernet1/0/5
interface GigabitEthernet1/0/6
interface GigabitEthernet1/0/7
interface GigabitEthernet1/0/8
!
```

```
interface GigabitEthernet1/0/9
interface GigabitEthernet1/0/10
interface GigabitEthernet1/0/11
no switchport
no ip address
ipv6 address FE80::D1:2 link-local
ipv6 address 2001:DB8:ACAD:1001::2/64
ipv6 ospf 123 area 1
interface GigabitEthernet1/0/12
interface GigabitEthernet1/0/13
interface GigabitEthernet1/0/14
interface GigabitEthernet1/0/15
interface GigabitEthernet1/0/16
interface GigabitEthernet1/0/17
interface GigabitEthernet1/0/18
interface GigabitEthernet1/0/19
interface GigabitEthernet1/0/20
interface GigabitEthernet1/0/21
interface GigabitEthernet1/0/22
interface GigabitEthernet1/0/23
no switchport
no ip address
ipv6 address FE80::D1:1 link-local
ipv6 address 2001:DB8:ACAD:1002::1/64
ipv6 ospf 123 area 1
interface GigabitEthernet1/0/24
interface GigabitEthernet1/1/1
interface GigabitEthernet1/1/2
interface GigabitEthernet1/1/3
interface GigabitEthernet1/1/4
!
```

interface Vlan1

```
no ip address
ip forward-protocol nd
ip http server
ip http secure-server
ipv6 router ospf 123
router-id 1.1.1.2
passive-interface GigabitEthernet1/0/23
control-plane
service-policy input system-cpp-policy
line con 0
exec-timeout 0 0
logging synchronous
stopbits 1
line aux 0
stopbits 1
line vty 0 4
login
line vty 5 15
login
end
Switch D2
D2# show run
Building configuration...
Current configuration: 8968 bytes
version 16.9
no service pad
service timestamps debug datetime msec
service timestamps log datetime msec
service call-home
no platform punt-keepalive disable-kernel-core
hostname D2
!
vrf definition Mgmt-vrf
!
address-family ipv4
exit-address-family
address-family ipv6
```

```
exit-address-family
!
no aaa new-model
switch 1 provision ws-c3650-24ps
ip routing
no ip domain lookup
login on-success log
ipv6 unicast-routing
license boot level ipservicesk9
diagnostic bootup level minimal
spanning-tree mode rapid-pvst
spanning-tree extend system-id
redundancy
mode sso
transceiver type all
monitoring
class-map match-any system-cpp-police-topology-control
 description Topology control
class-map match-any system-cpp-police-sw-forward
  description Sw forwarding, L2 LVX data, LOGGING
class-map match-any system-cpp-default
  description Inter FED, EWLC control, EWLC data
class-map match-any system-cpp-police-sys-data
  description Learning cache ovfl, High Rate App, Exception, EGR Exception,
NFLSAMPLED DATA, RPF Failed
class-map match-any system-cpp-police-punt-webauth
 description Punt Webauth
class-map match-any system-cpp-police-121vx-control
  description L2 LVX control packets
class-map match-any system-cpp-police-forus
 description Forus Address resolution and Forus traffic
class-map match-any system-cpp-police-multicast-end-station
  description MCAST END STATION
class-map match-any system-cpp-police-multicast
  description Transit Traffic and MCAST Data
class-map match-any system-cpp-police-12-control
  description L2 control
class-map match-any system-cpp-police-dot1x-auth
  description DOT1X Auth
class-map match-any system-cpp-police-data
```

```
description ICMP redirect, ICMP GEN and BROADCAST
class-map match-any system-cpp-police-stackwise-virt-control
  description Stackwise Virtual
class-map match-any non-client-nrt-class
class-map match-any system-cpp-police-routing-control
  description Routing control and Low Latency
class-map match-any system-cpp-police-protocol-snooping
  description Protocol snooping
class-map match-any system-cpp-police-dhcp-snooping
 description DHCP snooping
class-map match-any system-cpp-police-system-critical
  description System Critical and Gold Pkt
policy-map system-cpp-policy
interface GigabitEthernet0/0
vrf forwarding Mgmt-vrf
no ip address
negotiation auto
interface GigabitEthernet1/0/1
interface GigabitEthernet1/0/2
interface GigabitEthernet1/0/3
interface GigabitEthernet1/0/4
interface GigabitEthernet1/0/5
interface GigabitEthernet1/0/6
interface GigabitEthernet1/0/7
interface GigabitEthernet1/0/8
interface GigabitEthernet1/0/9
interface GigabitEthernet1/0/10
interface GigabitEthernet1/0/11
no switchport
ip address 10.10.4.2 255.255.255.252
ipv6 address FE80::D2:2 link-local
ipv6 address 2001:DB8:ACAD:2001::2/64
ospfv3 123 ipv4 area 2
ospfv3 123 ipv6 area 2
interface GigabitEthernet1/0/12
!
```

```
interface GigabitEthernet1/0/13
interface GigabitEthernet1/0/14
interface GigabitEthernet1/0/15
interface GigabitEthernet1/0/16
interface GigabitEthernet1/0/17
interface GigabitEthernet1/0/18
interface GigabitEthernet1/0/19
interface GigabitEthernet1/0/20
interface GigabitEthernet1/0/21
interface GigabitEthernet1/0/22
interface GigabitEthernet1/0/23
no switchport
ip address 10.10.5.1 255.255.255.0
ipv6 address FE80::D2:1 link-local
ipv6 address 2001:DB8:ACAD:2002::1/64
ospfv3 123 ipv4 area 2
ospfv3 123 ipv6 area 2
interface GigabitEthernet1/0/24
interface GigabitEthernet1/1/1
interface GigabitEthernet1/1/2
interface GigabitEthernet1/1/3
interface GigabitEthernet1/1/4
interface Vlan1
no ip address
router ospfv3 123
 address-family ipv4 unicast
 passive-interface GigabitEthernet1/0/23
 router-id 3.3.3.2
 exit-address-family
 address-family ipv6 unicast
 passive-interface GigabitEthernet1/0/23
```

```
router-id 3.3.3.2
exit-address-family
ip forward-protocol nd
ip http server
ip http secure-server
control-plane
service-policy input system-cpp-policy
line con 0
exec-timeout 0 0
logging synchronous
stopbits 1
line aux 0
stopbits 1
line vty 0 4
login
line vty 5 15
login
!
end
```