

UltraBook UB

User Guide



About This Document

This document describes the UB user guide.

Copyright Information

Celoxica and the Celoxica logo are trademarks of Celoxica Limited.

All other products or services mentioned herein may be trademarks of their respective owners.

Neither the whole nor any part of the information contained in, or the product described in, this document may be adapted or reproduced in any material form except with the prior written permission of the copyright holder.

The product described in this document is subject to continuous development and improvement. All particulars of the product and its use contained in this document are given by Celoxica Limited in good faith. However, all warranties implied or express, including but not limited to implied warranties of merchantability, or fitness for purpose, are excluded.

This document is intended only to assist the reader in the use of the product. Celoxica Limited shall not be liable for any loss or damage arising from the use of any information in this document, or any incorrect use of the product. The information contained herein is subject to change without notice and is for general guidance only.

Copyright © 1991 - 2013 Celoxica Limited. All rights reserved.

Sales <u>sales@celoxica.com</u>

Customer Support <u>support@celoxica.com</u>

Website http://www.celoxica.com

UK Head Office

Celoxica Limited

34 Porchester Road

London

W2 6ES, UK

Phone: +44 (0) 20 7313 3180

US Head Office

Celoxica Inc.

275 Madison Avenue, Suite 404

New York, NY

10016, USA

Phone: +1 (0) 212 880 2075

US Chicago Office

Celoxica Inc.

141 W Jackson Blvd, Suite 2350

Chicago, IL

60604, USA

Phone: +1 (0) 312 893 1204



Content

1.	Functional Description	7		3.2.6	Market	
1.1	Recommended Reading		3.3	Usage		
1.2	Overview			3.3.1	Instrument Pre-Subscription and Subscription	
	1.2.1 Symbology			3.3.2	View Changes Notifications	
	1.2.2 Instrument Static Information			3.3.3	Market Changes Notifications	
	1.2.3 Levels		3.4	Structur	es	32
	1.2.4 Trades			3.4.1	InstrumentType	32
	1.2.5 Prices			3.4.2	Level	32
	1.2.6 Imbalances			3.4.3	Trade	32
	1.2.7 Trading Status			3.4.4	TradeList	32
	1.2.8 Integrity			3.4.5	Prices	33
1.3	Shared Memory API			3.4.6	Imbalance	33
1.4	Filtering			3.4.7	Status	33
1.5	Recovery			3.4.8	MarketStatus	34
1.5	Necovery	10		3.4.9	UpdateInfo	34
2.	Configuration	12		3.4.10	InternalStatistics	34
2.1	Configuration File Schema			3.4.11	Instrument	35
2.2	Configuration Settings		3.5	Enumer	ations	35
	2.2.1 General Configuration Settings			3.5.1	TradingStatus	35
	2.2.2 Logger Configuration Settings			3.5.2	TradeType	36
	2.2.3 Control Configuration Settings			3.5.3	Integrity	36
	2.2.4 Market Configuration Settings			3.5.4	UpdateFlags	36
	2.2.5 Handler Configuration Settings			3.5.5	QuantityType	37
	3 3.			3.5.6	InstrumentType	37
3.	User API	22		3.5.7	UpdatableKind	38
3.1	Class Diagram	22				
3.2	Class Definitions	23	4.		cal Architecture	
	3.2.1 Session	23	4.1	UB Dae	mon Monitoring	39
	3.2.2 Reader	23	4.2	Shared	Memory Allocation	40
	3.2.3 Instrument	24	4.3	Shared	Memory Usage	43
	3.2.4 Updatable	25		4.3.1	Memory Consumption	43
	3.2.5 View	26		4.3.2	Memory Lock	43



5.	Shipped	Examples44		
6.	Market S	Specifics45		
6.1	ARCAOptions			
	6.1.1	Source45		
	6.1.2	Symbology45		
	6.1.3	Reference Data45		
	6.1.4	Instrument Trading Status45		
	6.1.5	Market Trading Status46		
	6.1.6	Instrument Integrity47		
	6.1.7	Market Integrity47		
	6.1.8	Trade Type47		
	6.1.9	Update Flags47		
	6.1.10	Quantity Type48		
	6.1.11	Raw Exchange Specific Data48		
6.2	CSM	49		
	6.2.1	Source		
	6.2.2	Symbology49		
	6.2.3	Reference Data49		
	6.2.4	Instrument Trading Status49		
	6.2.5	Market Trading Status50		
	6.2.6	Instrument Integrity51		
	6.2.7	Market Integrity51		
	6.2.8	Trade Type51		
	6.2.9	Update Flags51		
	6.2.10	Quantity Type52		
	6.2.11	Raw Exchange Specific Data52		
6.3	OPRA_BI	NARY53		
	6.3.1	Source53		
	6.3.2	Symbology53		
	6.3.3	Instrument Trading Status53		
	6.3.4	Market Trading Status53		
	6.3.5	Trade Type53		
	6.3.6	Update Flags54		

7.	FAQ		. 60
	6.4.11	Raw Exchange Specific Data	59
	6.4.10	Quantity Type	
	6.4.9	Update Flags	
	6.4.8	Trade Type	58
	6.4.7	Market Integrity	
	6.4.6	Instrument Integrity	58
	6.4.5	Market Trading Status	57
	6.4.4	Instrument Trading Status	56
	6.4.3	Reference Data	56
	6.4.2	Symbology	
	6.4.1	Source	56
6.4	PHLXTop	ooV3	56
	6.3.7	Quantity Type	55



Table of Figures

Figure 1 – Multiple user readers	
Figure 2 – Class diagram	2
Figure 3 – View changes notifications	2
Figure 4 – Market changes notifications	3
Figure 5 – UB daemon	3

UltraBook UB 5 User Guide



Revisions

Revision	Date	Description of Changes
R2013-1.0	15 JAN 2013	Release R2013-1.0 - Added details to sections Quantity Type and Raw Exchange Specific Data for ARCAOptions
R2012-8.1	20 DEC 2012	Release R2012-8.1 - UB supports PHLX TOPO - Updated Shared Memory section - Updated the Symbology section - Added details to config.markets.market description
R2012-8.0	28 NOV 2012	Release R2012-8.0 - Added details to the trading status and integrity management - Added Shared Memory Allocation section - Added UpdateInfo.exchangeSequenceNumber - Updated CSM market specifics - Updated ARCAOptions market specifics - Updated View class definition - Updated Instrument class definition
R2012-7.1	31 OCT 2012	Release R2012-7.1 - Added ARCAOPTIONS market specifics - Added Control Configuration Settings section - Updated CSM market specifics - Updated Functional Description section - Updated User API section
R2012-ub-beta	17 SEP 2012	Release R2012-ub-beta - OBv2 is renamed UltraBook UB - Added Market Specifics section - Added Usage sub-section in the User API section - Updated Functional Description section - Updated Technical Architecture section - Updated Configuration section - Updated Structures section in the User API section
R2012-5.ob2-alpha	10 AUG 2012	Initial release

UltraBook UB User Guide



1. Functional Description

1.1 Recommended Reading

This document should be read in conjunction with:

- The Celoxica Manager User Guide
- The PCI Express Card Hardware Installation Guide
- The PCI Express Card Software Installation Guide

1.2 Overview

Celoxica's generic and data-normalized UltraBook UB is an FPGA-based solution providing processed market data stored in a book and high-performance communication with a client software application.

UB normalizes order-driven and book-driven feeds and provides a unified interface for reading orders for different instruments. It supports multiple markets and multiple levels depth.

1.2.1 Symbology

UB provides a flexible symbology, where every instrument can be addressed in multiple ways.

Currently UB needs to determine the mapping between symbol names and indexes from the reference data received directly from the feed. In a future release, a facility for the user to specify a static data referential file will be added.

UB supports several identifier schemes to uniquely identify an instrument. The availability of the schemes per instrument depends on the market.

The list of supported schemes is as follows:

L	_	٠,	,
n	C	y	

Description The UB internal unique identifier.

This scheme is supported for all feeds.
This identifier is provided for all instruments.
This identifier is unique per UB daemon and remains valid during the whole UB daemon lifespan.

Usage key://<keyNumber>

Example key://421048290333

index

Description The hexadecimal form of the instrument index provided by the exchange.

This identifier is unique per <marketName> and remains valid until the market changes it. Usage index://<index>.<marketName> Example index://001e03e4.arca

local		
Description	The instrument name as provided by the exchange.	
	This identifier is unique per <marketname> and remains valid until the market changes it.</marketname>	
Usage	local:// <localname>.<marketname></marketname></localname>	
Example	local://aapl.arca	

UltraBook UB 7 User Guide



osi

Description The OCC Options Symbology Initiative name.

This scheme is supported for options only.

This identifier is unique per instrument and remains valid during the whole

instrument lifespan.

Usage osi://<osiName>.<marketName>

Example osi://aapl 120201P00012340.arca

fsi

Description Celoxica specific naming for Futures.

This scheme is supported for futures only.

This identifier is unique per instrument and remains valid during the whole instrument lifespan.

It consists of the following components:

Future root symbol 6 bytes

Expiry year 2 bytes

Expiry month 2 bytes

Expiry day
 2 bytes

Usage fsi://<fsiName>.<marketName>

Example fsi://aapl 120201.arca

Note:

<marketName> refers to name of the market used when setting config.markets.market.

Other schemes might be supported in future UB releases.

1.2.2 Instrument Static Information

UB provides instrument industry standard static and normalized information:

- The instrument identifiers depending on the available identifier schemes
- The ISO 10962 CFI code
- The instrument type as provided by the exchange

UB also provides raw referential data as provided by the exchange.

UB automatically registers all referential data received from the exchange. The user subscribes to an instrument to get levels, trades, prices and imbalances. UB will only process market data related to a symbol if the user subscribes to that symbol.

1.2.3 Levels

The order book is maintained from level 0 (top of book) to level n where $n \le 4$ and provides the bid and offer quantity per level.

If an exchange provides different quantity types such as customer or all or none quantity type, UB will maintain as many order books as there are quantity types available.

1.2.4 Trades

UB provides the trades received from the exchange when available.

1.2.5 Prices

UB provides the order book OHLC (Open / High / Low / Close) and settlement prices information when available.

UltraBook UB 8 User Guide



1.2.6 Imbalances

UB provides the order book imbalance information when available.

1.2.7 Trading Status

The security and market trading statuses generic forms are provided when available. Note that such statuses often vary significantly between feeds, so it is not always possible to provide a full and generic mapping. UB therefore provides market specific statuses for the user's reference.

UB automatically registers all instrument trading statuses received from the exchange even for non-subscribed instruments; as a consequence, if the user subscribes to an instrument intra-day, he will get the correct instrument trading status.

Note:

For a given instrument, UB registers the trading status only if there was at least one referential message received prior to the trading status message.

1.2.8 Integrity

The instrument and market integrity is also made available to the client application. This integrity status notifies the state of the instrument book and the market:

Clean

There is no error, no data loss.

Best-effort

The instrument book / market information is probably not accurate because of gaps and data loss; a recovery may be in progress to update the order book / market integrity.

Stalled

The instrument book / market information flow has stalled e.g. one of the multicasts on the market has timed out.

This feature is partially supported:

- The instrument integrity is always clean
- The market integrity is set clean at startup, becomes best-effort in case of a sequence gap; however, no recovery process is implemented yet.

1.3 Shared Memory API

UB handles the market data from the exchanges and writes the appropriate market events to shared memory. The shared memory is made accessible to the client application which can therefore read it via a shared memory API.

UB has been designed so that the shared memory order book can be accessed by multiple user readers – multiple threads - as illustrated below.




Figure 1 – Multiple user readers

UltraBook UB 9 User Guide



The client application gets access to:

Order book tables

A complete order book per symbol is made available through shared memory. This API is an easy and quick way for the client application to get access to order books.

The user gets the most recent live information updates by using this API.

• Update queue per reader

The client application defines a set of reader slots from which it is notified if there was a change in the order book. These notifications do not accumulate and are cleared when the user reads the change list.

The change list contains flags about what has changed in the book. Change flags can stack up over time in the notification list however the order of the changes is not maintained.

Several types of changes in the order book are flagged:

- Top of book (level 0) change per quantity type
- Levels other than top of book change per quantity type
- Trades change
- Prices change
- Imbalances change
- Instrument Status change
- Market Status change
- Instrument integrity
- Market integrity

Symbol directory

The client application reads the symbol directory to get static information of instruments.

The client application is able to retrieve the most up-to-date exchange specific referential data as well as standard and normalized instrument characteristics.

Order books for regulatory and consolidated feeds have the same client API presentation as primary feeds i.e. a separate order book per venue.

1.4 Filtering

Software filtering is natively implemented in UB for all feeds as UB automatically filters the symbols based on the subscription.

Note:

UB does not support hardware symbol filtering yet.

1.5 Recovery

Recovery is handled by UB automatically. Books are always initiated with best-effort status, so UB detects this and triggers the snapshot recovery process. During the snapshot process, the user is presented with all updates received from the market even if the book is in best-effort status. Once the snapshot has been processed successfully, the book switches to clean status. If a gap is detected the book switches back to best-effort status and the snapshot process is triggered again.

The following types of recovery are or will be available:

Natural refresh

The order book is built using only live data. This provides a quick and easy way of order book refresh.

This feature is supported.

Snapshot recovery

The picture of the order book is refreshed using market snapshot (when available). This is useful for mid-day starts and for non-liquid instruments.

This feature is not supported yet.

Gap skip recovery

UltraBook UB 10 User Guide



The order book may be crossed when some data are missed. UB is able to cope with such cases by using the uncrossing mechanism: this is a scheme whereby crossing entries are deleted from the book automatically.

This feature is not supported yet.

UltraBook UB 11 User Guide



2. Configuration

This section describes the UB configuration file and all available configuration options.

UB is configured using an XML-style '.cfg' file. When the UB initializes, it loads this configuration file. See section 2.1 for more details.

Example configuration files are shipped with your software. These files were created using reliable, fully tested settings. Celoxica highly recommends creating backup copies of any configuration files before editing.

One configuration file must be defined per UB instance; it allows the user to configure:

- Some general settings; see section 2.2.1 for more details;
- Some logger daemon specific settings; see section 2.2.2 for more details;
- Some UB server process specific settings, see section 2.2.3 for more details;
- Some market specific settings, in particular details for the live multicasts; see section 2.2.4 for more details;
- Market data handlers; see section 2.2.5 for more details.

2.1 Configuration File Schema

The basic structure of an UB configuration file is shown in the following schema. Tags have to be defined in the order as shown. This schema shows tags but not values.

UltraBook UB 12 User Guide



```
<config>
      <ade>
            <cpu>
      <ade>
     <cpu-other>
     <verbosity>
      <daemonize>
     <logger>
           <key>
           <file>
           <size>
     </logger>
      <control>
            <name>
            <cli>ent-timeout>
      </control>
      <markets>
            <market>
                 <sessions>
                        <session>
                              <channels>
                                    <!- Live multicasts ->
                                    <channel>
                              </channels>
                              <references>
                                    <!- Security definitions channel ->
                                    <channel>
                              </references>
                              <recovery>
                                    <!- Recovery channel ->
                                   <channel>
                              </recovery>
```

UltraBook UB 13 User Guide



UltraBook UB 14 User Guide



2.2 Configuration Settings

2.2.1 General Configuration Settings

These configuration settings are general and not market specific.

2.2.1.1 config

Description This tag initiates a body for UB configurations to be made in a file. This tag

is at the top of the file.

Usage <config>

2.2.1.2 config.ade

Description This tag initiates a body for ADE configurations to be made.

Usage <ade>

2.2.1.3 config.ade.cpu

 $\begin{tabular}{ll} \textbf{Description} & \textbf{Sets the CPU number, starting from 0.} \end{tabular}$

Usage <cpu> CPU </cpu>

Parameters CPU Integer

Example <p

2.2.1.4 config.verbosity

Description Sets the verbosity of UB.

Parameters verbosity String.

Possible values are:

error

warning

info

debug

Example <verbosity> error

2.2.1.5 config.cpu-other

Description Specifies the CPU number on which other non-latency-critical Celoxica

threads are allowed to run, as a bitmask. Such threads include the network emulation thread, which enables the accelerator card to exchange nonoffloaded traffic with the OS network stack or the UB snapshot management

thread.

Parameters CPU Integer

Example <p



2.2.1.6 config.daemonize

Description Specifies if UB is daemonized (the process is running on the background) or

not.

When enabled the executable will make the daemon run on the background

and the console will be returned back to the user.

The parameter must be enabled to make the UB daemon be managed by

the Celoxica manager.

Parameters daemon Boolean

Example <daemonize> true </daemonize>

2.2.2 Logger Configuration Settings

The logger configuration allows the setting of parameters for UB to use the logger daemon.

2.2.2.1 config.logger

Description This tag initiates a body for the logger configurations to be made.

Usage <logger>

2.2.2.2 config.logger.key

Description Sets the logger daemon shared memory key.

Usage <key>Key</key>

Parameters Key integer

Example <key>11</key>

2.2.2.3 config.logger.file

Description Sets the default log file if the logger daemon is not present.

Usage <file>File</file>

Parameters File path.

Default is /dev/stderr

Example <file>/tmp/log.log</file>

2.2.2.4 config.logger.size

Description Sets the size of the shared memory if not created.

Parameters Size Log size expressed in bytes

Example <size>5242880</size>

UltraBook UB 16 User Guide



2.2.3 Control Configuration Settings

These configuration settings allow the user to define the UB server process.

2.2.3.1 config.control

Description This tag initiates a body for the UB server process configurations to be

made.

Usage <control>

2.2.3.2 config.control.name

Description Sets the server process name.

Usage <name> name </name>

Parameters name String

Example <name> UB server 1

2.2.3.3 config.control.client-timeout

Description Sets the time in seconds to wait before the server disconnects a silent client.

Parameters timeout Integer.

Default is 10 seconds.

Timeout is deactivated if set to 0.

Example <cli>ent-timeout> 15 </client-timeout>

2.2.4 Market Configuration Settings

These configuration settings are market specific.

2.2.4.1 config.markets

Description This tag initiates a body for market configurations to be made.

Usage <markets>

2.2.4.2 config.markets.market

Description Configures a market with integer id and string name used to identify the

market.

Parameters id Id of the market.

Integer.

marketName Name of the market.

This is the name used in the symbology.

protocol Protocol to be used.

See section 6 for details on the settings to use for each

market.



Example <market> 0 cboe strategy CSM

<market> 1 cboe nonstrategy CSM

Notes

Most of markets ensure the symbol index uniqueness at the market level. However, some markets guarantee the symbol index uniqueness at different layers, for instance per market / source session or per market / instrument type (strategy / non strategy). In such a case, the markets must be configured to ensure the symbol index is unique per market.

Refer to the example configuration files shipped with UB.

2.2.4.3 config.markets.market.sessions

Description This tag initiates a body for session configurations to be made.

Note:

This configuration node is originally intended to separate recovery channels from other channels: this feature is not implemented yet.

A single session per market will therefore have to be configured.

Usage <sessions>

2.2.4.4 config.markets.market.sessions.session

Description Configures a session with integer id and string name used to identify the

session.

Parameters id Id of the session

name Name of the session

Example <session> 0 Test Market Data

2.2.4.5 config.markets.market.sessions.session.channels

Description This tag initiates a body for channels configurations to be made.

Usage <channels>

2.2.4.6 config.markets.market.sessions.session.channels.channel

Description Configures the list of live multicast channels.

Usage <channel> localChanId numQueue srcPlugin interface

srcIP:port:type </channel>

Parameters localChanId The local id for this channel, must be unique for the

market

numQueue The DMA queue number which this channel is delivered,

can be set to 0 only

srcPlugin The source for this channel, set to 11dt when using the

accelerator card

interface The physical interface on the accelerator card where the

channel is received. If required, a particular interface on

a VLAN can be specified.

srcIP:port The multicast IP address and port for this channel

type The type of connection for the channel, t for TCP and u

UltraBook UB User Guide



for UDP

Example <channel> 0 0 11dt ac0 224.0.62.2:30001:u

</channel>

Interface on VLAN 444:

<channel> 0 0 11dt ac0.444 224.0.62.2:30001:u

</channel>

2.2.4.7 config.markets.market.sessions.session.references

Description This tag initiates a body for security definition configurations to be made.

Usage <references>

2.2.4.8 config.markets.market.sessions.session.references.channel

Description Configures the channel from which security definitions are received.

Usage <channel> localChanId numQueue srcPlugin interface

srcIP:port </channel>

Parameters localChanId The local id for this channel, must be unique for the

market

numQueue The DMA queue number which this channel is delivered,

can be set to 0 only

srcPlugin The source for this channel, set to lldt when using the

accelerator card

interface The physical interface on the accelerator card where the

channel is received. If required, a particular interface on

a VLAN can be specified.

srcIP:port The multicast IP address and port for this channel

type The type of connection for the channel, t for TCP and u

for UDP

Example <channel> 0 0 11dt ac0 224.0.62.2:30001:u

</channel>

Interface on VLAN 444:

<channel> 0 0 11dt ac0.444 224.0.62.2:30001:u

</channel>

2.2.4.9 config.markets.market.sessions.session.recovery

Description This tag initiates a body for recovery (dropped packets recovery on

supported markets) configurations to be made.

Gap recovery is not supported yet.

Usage <recovery>

2.2.4.10 config.markets.market.sessions.session.recovery.channel

Description Configures the recovery channel.

Usage <channel> localChanId numQueue srcPlugin interface

srcIP:port </channel>

UltraBook UB 19 User Guide



Parameters	localChanId	The local id for this channel, must be unique for the market	
	numQueue	The DMA queue number which this channel is delivered, can be set to 0 only	
	srcPlugin	The source for this channel, set to ${\tt lldt}$ when using the accelerator card	
	interface	The physical interface on the accelerator card where the channel is received. If required, a particular interface on a VLAN can be specified.	
	srcIP:port	The multicast IP address and port for this channel	
	type	The type of connection for the channel, t for TCP and u for UDP	
Example	<channel> 0 </channel>	0 lldt ac0 224.0.62.2:30001:u	
	Interface on VLAN 444:		
	<channel> 0 </channel>	0 lldt ac0.444 224.0.62.2:30001:u	
2.2.4.11	config.markets	s.market.sessions.session.snapshots	
Description	This tag initiates a body for snapshots configurations to be made.		
	Snapshot recovery is not supported yet.		
Usage	<snapshots></snapshots>		

2.2.4.12	config.markets.market.sessions.session.snapshots.channel		
Description	Configures the snapshot channel.		
Usage	<pre><channel> localChanId numQueue srcPlugin interface srcIP:port </channel></pre>		
Parameters	localChanId	The local id for this channel, must be unique for the market	
	numQueue	The DMA queue number which this channel is delivered, can be set to 0 only	
	srcPlugin	The source for this channel, set to $\ensuremath{\mathtt{lldt}}$ when using the accelerator card	
	interface	The physical interface on the accelerator card where the channel is received. If required, a particular interface on a VLAN can be specified.	
	srcIP:port	The multicast IP address and port for this channel	
	type	The type of connection for the channel, t for TCP and u for UDP	
Example	<pre><channel> 0 </channel></pre>	0 lldt ac0 224.0.62.2:30001:u	
	Interface on	N VLAN 444:	
	<pre>channel> 0 0 11dt ac0.444 224.0.62.2:30001:u </pre>		

2.2.5 Handler Configuration Settings

These configuration settings allow the user to define market data handlers.

UltraBook UB 20 User Guide



2.2.5.1 config.handlers

Description This tag initiates a body for market data handler configurations to be made.

Usage <handlers>

2.2.5.2 config.handlers.handler

Description

Configures a handler with integer id and string name used to identify the handler.

This handler must be specified when the user wants to use the UltraBook User API.

The available market data handlers are:

- "OrderBook" Builds the order books
- "Dump" Prints the UB internal events generated by the market parsers. This handler is intended for troubleshooting/debugging purposes.

Parameters id Id of the handler

name Name of the handler

Example <handler> 0 OrderBook </handler>

<handler> 1 Dump </handler>

UltraBook UB 21 User Guide



3. User API

UB ships as a set of dynamic libraries, which the user code can interface to via the single and simple client API it exposes. A "hello world" example is shipped in the UB package, to illustrate the basic usage of the API. This is described in section *Shipped Examples*.

3.1 Class Diagram




Figure 2 - Class diagram

UltraBook UB 22 User Guide



3.2 Class Definitions

3.2.1 Session

Description

An object of class Session type connects the client application to an order book.

The construction of a Session object in the client application does what is necessary to register the client and open the shared memory segments.

The Session object provides a method to access an instrument index table where all the known instruments and their static information are stored. It also provides a method to retrieve the raw referential data as provided by the market feeds.

An exception is thrown if the server cannot be reached or if an error occurred while communicating with the server.

The session implementation class is allocated on the heap when constructed and freed when the last pointer to it is destroyed.

The Session object can be allocated either on the stack or on the heap.

The copy constructor is enabled.

Copying a Session object only implies a copy of the pointer to the session implementation class.

Class UB::Session

Constructor Session(clientName, serverName)

clientName

client process name

serverName

UB daemon name as defined using configuration node config.control.name.

Exceptions ConnectionFailed

Connection failed with UB daemon.

Operators N/A

Methods instruments()

Returns the most up-to-date list of instruments.

heartbeat()

Returns a Boolean flagging whether the connection with the server is alive or not. The method is time consuming because of the heartbeat exchange between the client and the server; it should therefore not be called in the performance loop.

referentialData(instrument)

Returns the most up-to-date exchange specific data for the given instrument.

See structure *Instrument* for more details.

trySubscribe()

Tries to subscribe to any pre-subscribed instruments and corresponding views. This method has to be called regularly as the list of instruments may change with live referential updates provided by the exchange.

See section 3.3.1 for more details.

3.2.2 Reader

Description

An object of class Reader type manages order book views and is notified of any order book change.

A Reader object is a thin wrapper around what is needed to be able to notify a given client that an order book has been modified. The Reader object provides the user application with the means to get a set of all modified order books and market trading status since the last time it checked for changes.

The construction of a Reader object requires a session, and will negotiate to

UltraBook UB 23 User Guide



get a free notification queue in the shared memory. An exception is raised if the application runs out of free queues.

The reader implementation class is allocated on the heap when constructed and freed when the last pointer to it is destroyed.

The Reader object can be allocated either on the stack or on the heap.

The copy constructor is enabled.

Copying a Reader object only implies a copy of the pointer to the reader implementation class.

Class UB::Reader

Constructor Reader (session, readerName)

session

Session identifier.

readerName

Reader name assigned by the client application.

Exceptions ReaderUnavailable

A free notification queue in the shared memory is not available.

Operators N/A

Methods

updatedElement()

Returns a pointer to the next updated object of class View type or Market

type since the last call.

View::updateInfo() method has to be called on the returned object of class View type to indicate that the last updates on an order book view have been read; otherwise the View object will not be returned

again by Reader::updatedElement() even if additional updates are received.

Market::updateInfo() method has to be called on the returned object of class Market type to indicate that the last updates on a market have been read; otherwise the Market object will not be returned again by Reader::updatedElement() even if additional updates are received.

See sections 3.3.2 and 3.3.3 for more details.

views()

Returns all the views currently associated with this reader.

3.2.3 Instrument

Description

An object of class Instrument type provides static information for an instrument using methods.

An Instrument object is a thin wrapper around one entry in the instrument index table.

The construction of an Instrument object requires a session and an instrument identifier. The instrument identifier must follow a scheme format as described in section Symbology.

The Instrument object provides various methods to get the instrument static information.

The instrument implementation class is allocated on the heap when constructed and freed when the last pointer to it is destroyed.

The Instrument object can be allocated either on the stack or on the heap.

The copy constructor is enabled.

Copying an Instrument object only implies a copy of the pointer to the instrument implementation class.

Class **UB::Instrument**

UltraBook UB 24 User Guide



Constructor Instrument (session, identifier, force)

session

Session identifier.

identifier

Instrument identifier.

force

Optional boolean parameter to force the pre-subscription to an instrument if the instrument is not referenced by UB yet.

A referenced instrument will be subscribed upon its creation whatever the force value.

Default is false.

See section 3.3.1 for more details.

Exceptions

UnsupportedScheme

The scheme is not available for this instrument.

UnknownBook

The instrument is not known from the instrument library.

Operators

!=

For convenient comparisons between Instrument objects.

Methods

SupportedSchemes()

Returns the list of schemes for this instrument.

identifier(scheme)

Returns the instrument identifier using the scheme format for the specified scheme e.g. osi://aapl 120201P00012340.arca if scheme = osi.

The default scheme is 'key'.

marketIdentifier()

Returns the market identifier for this instrument e.g. arcaox (Arca Option) for instrument which identifier is osi://aapl 120201P00012340.arcaox using the scheme osi.

type()

Returns the instrument type.

See structure *InstrumentType* for more details.

isSubscribed()

Returns a boolean to indicate whether the instrument is subscribed (true) or only pre-subscribed (false).

An instrument may only be pre-subscribed if its creation has been forced.

The method Session::trySubscribe() has to be called to try to subscribe to pre-subscribed instruments.

3.2.4 Updatable

Description An object of class Updatable type is an object returned by Reader::updatedElements().

> The actual updatable object is provided using Updatable::kind field (see enumeration UpdatableKind for more details).

Class

UB::Updatable

Constructor Updatable()

Exceptions N/A

UltraBook UB 25 User Guide



Operators N/A

Methods N/A

3.2.5 View

Description

An object of class View type provides the last live information updates on an order book.

A View object is an updatable object of kind UPDATABLE_VIEW (see enumeration *UpdatableKind* for more details).

A View object is a thin wrapper around an order book from a reader point of view. The View object wraps the order book itself and also reader-specific update flags to allow the client application to check what has changed since the last time it has checked the order book on the reader associated with the view.

A View object also provides a set of methods to read the dynamic data from the order book in shared memory. These methods provide the dynamic data that have been changed since the last time the client application checked the order book on the reader associated with the view.

The construction of a View object requires a Reader object to associate to, and an Instrument object to be able to get the corresponding order book.

The view implementation class is allocated on the heap when constructed and freed when the last pointer to it is destroyed.

The View object can be allocated either on the stack or on the heap.

View objects cannot be copied as pointers are returned to the View objects that are associated to a reader: the copy constructor is disabled.

Class UB::View

Constructor View(reader, instrument)

reader

Reader to be associated to the view.

instrument

Instrument to retrieve the order book information.

Exceptions N/A

Operators N/A

Methods level(level, quantityType)

Returns the data of an order book for a given level (both sides) and a given quantity type (QUANTITY_TYPE_NORMAL is the default quantity type).

The function ensures that the data being returned have not been modified while being read in shared memory.

See enumeration *QuantityType* for the possible quantity types.

levels(quantityType)

Returns data of all levels (both sides) of an order book for a given quantity type (QUANTITY_TYPE_NORMAL is the default quantity type).

The function ensures that the data being returned have not been modified while being read in shared memory.

See enumeration *QuantityType* for the possible quantity types.

updateInfo()

Returns the last updates on an order book view. Notifications are cleared when the user reads the change list.

See structure *UpdateInfo* for more details.

trades()



Returns the list of as many unread trades as possible.

The function does not guarantee to return all trades if it is not frequently called: the oldest trades are dropped when the trade queue is full. The most recent trades are therefore always made available.

See structure *TradeList* for more details.

```
lastTrade()
```

Returns the latest received trade.

If no trade has been received, the returned trade has a type TRADE_TYPE_INVALID.

```
instrument()
```

Returns the instrument static data.

```
prices()
```

Returns the order book prices. See structure *Prices* for more details.

```
status()
```

Returns the instrument trading status, market trading status and instrument integrity.

See structure Status for more details.

```
imbalance()
```

Returns the order book imbalance.

See structure Imbalance for more details.

```
internalStatistics()
```

Returns some internal counters. See structure *InternalStatistics* for more details.

```
isSubscribed()
```

Returns a boolean to indicate whether the view is subscribed (true) or only pre-subscribed (false).

The method Session::trySubscribe() has to be called to try to subscribe to pre-subscribed instruments.

3.2.6 Market

Description

An object of class Market type provides the last live information updates on a market.

A Market object is an updatable object of kind UPDATABLE_MARKET (see enumeration *UpdatableKind* for more details).

The Market object is automatically created when a view is associated to a reader.

A Market object also provides a set of methods to read the dynamic data in shared memory. These methods provide the dynamic data that have been changed since the last time the client application checked the market trading status on the reader associated with the market.

The market implementation class is allocated on the heap when constructed and freed when the last pointer to it is destroyed.

The Market object can be allocated either on the stack or on the heap.

The copy constructor is enabled.

Copying a Market object only implies a copy of the pointer to the market implementation class.

Class UB::Market

Constructor Market()

Exceptions N/A

Operators N/A

Methods status()

See structure MarketStatus for more details.

UltraBook UB 27 User Guide



updateInfo()

Returns the last updates on the market. Notifications are cleared when the user reads the change list.

See structure *UpdateInfo* for more details.

marketIdentifier()

Returns the market identifier as configured in the UB server configuration file.

3.3 Usage

UB automatically processes the data coming from the market feeds. It builds order books for instruments for which there is at least one subscription initiated. The use of the API does not affect the UB internal operation.

3.3.1 Instrument Pre-Subscription and Subscription

When an Instrument object is created, the API tries to find it in the instruments already referenced by UB (instruments for which referential data have been received from the exchange) to subscribe to it.

The user has the ability of anticipating an instrument creation by forcing the subscription to that instrument: a forced subscription is a pre-subscription.

The pre-subscription and subscription mechanism works as follows:

- If the instrument is referenced by UB, the subscription will be activated and the user will be able to create views with that instrument.
- 2. If the instrument is not referenced by UB yet and the instrument creation is not forced (force parameter set to false), the instrument creation will throw an exception.
- 3. If the instrument is not referenced by UB yet and the instrument creation is forced (force parameter set to true), the user will pre-subscribe to the instrument. All views created with a pre-subscribed instrument will also be considered as pre-subscribed. As new instruments may be added intra-day, the user is responsible for changing the instruments and views pre-subscriptions into subscriptions by regularly calling Session::trySubscribe().

3.3.2 View Changes Notifications

The API gives the user the ability to access the selected order books. It is possible to iteratively monitor the View objects by using the access methods such as View::level(), View::status(), View::trades() ... The output of these methods is a current snapshot.

Order book changes are flagged using the change flags provided by UB. Changes in the View object are monitored using the change flags on a per View object basis. UB notifies the user when the change flags are first set. The user retrieves the notifications using the Reader::updatedElements() method. This method returns a pointer to a View object (a View object is an Updatable object of kind UPDATABLE_VIEW) which has been changed.

Then the user can obtain the change flags by calling the <code>View::updateInfo()</code> method. This method returns the change flags and then clears them. No further notifications occur until the change flags have been cleared using this method.

UltraBook UB 28 User Guide







Figure 3 – View changes notifications

The processing of market data is asynchronous to the access methods. The access methods provide a snapshot of the current order book. As a result, the user will always see the same order of changes as received from the market feed. There is however no guarantee that the user will see all the changes; for example it can happen that the top of the book has changed twice, but the user only retrieves the top of book resulting from the two changes.


The API usage is illustrated by the following use cases:

First use case



At T0 the user calls Reader::updatedElements(). No pointer to the View object is returned assuming that the first change occurs at T1 only.

2. Second use case




a) At T0 the top of the book is changed. This change is assumed to be the first change. The top of the book change flag is set.

UltraBook UB 29 User Guide



- b) At T1 the user calls Reader::updatedElements(): the method returns a pointer to the View object.
- c) At T2 the user calls <code>View::updateInfo()</code>: the method returns that the only change that occurred is a top of the book change. Then this change flag is automatically reset.
- d) At T3 a trade is received. The trade change flag is set. The View object is therefore considered as updated again.
- e) At T4 the user retrieves the current top of the book by using View::level().


Third use case



- a) At T0 the top of the book is changed. This change is assumed to be the first change. The top of the book change flag is set.
- b) At T1 the user calls Reader::updatedElements(): the method returns a pointer to the View object.
- c) At T2 a trade is received. The trade change flag is set.
- d) At T3 the top of the book is changed again. The top of the book change flag remains set.

- e) At T4 the user calls View::updateInfo(): the method returns that the changes are of type top of the book change and trades. Then these two change flags are automatically reset.
- f) At T5 the top of the book is changed again. The top of the book change flag is set. The View object is therefore considered as updated again.
- g) At T6 the user retrieves the current top of the book by using View::level(): the retrieved top of the book takes into account the top of the book change that happened at T5.

4. Fourth use case



- At T0 a trade is received. This change is assumed to be the first change. The trade change flag is set.
- b) At T1 the user calls Reader::updatedElements(): the method returns a pointer to the View object.
- f) At T2 the user calls View::updateInfo(): the method returns that the change is of type trade. Then this change flag is automatically reset.
- c) At T3 a trade is received. The trade change flag is set.
- d) At T4 the user calls <code>View::trades()</code>: the method returns two trades.

UltraBook UB 30 User Guide



- e) At T5 the user calls Reader::updatedElements(): the method returns a pointer to the View object.
- f) At T6 the user calls View::updateInfo(): the method returns that the change is of type trade. Then this change flag is automatically reset.
- g) At T7 the user calls View::trades(): the method returns no trade as the received trades have already been read.

3.3.3 Market Changes Notifications

The API gives the user the ability to monitor the Market objects by using the access method Market::status(). The output of these methods is a current snapshot.

Market changes are flagged using the change flags provided by UB. Changes in the Market object are monitored using the change flags on a per Market object basis. UB notifies the user when the change flags are first set. The user retrieves the notifications using the Reader::updatedElements() method. This method returns a pointer to a Market object (a Market object is an Updatable object of kind UPDATABLE_MARKET) which has been changed.

Then the user can obtain the change flags by calling the Market::updateInfo() method. This method returns the change flags and then clears them. No further notifications occur until the change flags have been cleared using this method.




Figure 4 – Market changes notifications

The access method provides a snapshot of the current market trading status. As a result, the user will always see the same order of changes as received from the market feed. There is however no guarantee that the user will see all the changes; for example it can happen that the market trading status has changed twice, but the user only retrieves the last market trading status.

UltraBook UB 31 User Guide



3.4 Structures

See the header files for more details.

3.4.1 InstrumentType

Description Provides the instrument type.

Structure InstrumentType

The structure description is as follows:

Field	Description
cfiCode	Instrument ISO 10962 CFI code
exchangeInstrumentType	Raw instrument type as provided by the exchange

3.4.2 Level

Description Provides the quantity and price on both bid and offer level sides.

Structure Level

The structure description is as follows:

Field	Description
askPrice	Price on the offer side
askQuantity	Quantity on the offer side
bidPrice	Price on the bid side
bidQuantity	Quantity on the bid side

3.4.3 Trade

Description Provides the trade data.

Structure Trade

The structure description is as follows:

·		
Field	Description	
type	Type of trade. See enumeration <i>TradeType</i> for the possible values.	
quantity	Optional trade quantity	
price	Optional trade price	
exchangeFlags	Trade flags as provided by the exchange if any	
exchangeTradeld	Trade identifier as provided by the exchange	
exchangeTimestamp	Optional trade timestamp as provided by the exchange	
exchangeSequenceNumber	Optional trade sequence number as provided by the exchange	

3.4.4 TradeList

Description Provides a list of trades

Structure TradeList

The structure description is as follows:

Field Description

UltraBook UB 32 User Guide



Field	Description
totalTradedVolume	Cumulative total traded volume computed by UB
totalTradedCapital	Cumulative total traded capital computed by UB
trades	See structure <i>Trade</i> for more details
exchangeTotalTradedVolume	Exchange total traded volume as provided by the exchange

3.4.5 Prices

Description Provides the order book prices.

Structure Prices

The structure description is as follows:

Field	Description
openPrice	Optional open price
highPrice	Optional high price
IowPrice	Optional low price
closePrice	Optional closing price
settlementPrice	Optional settlement price
exchangeSettlementDate	Optional settlement date as provided by the exchange

3.4.6 Imbalance

Description Provides the order book imbalances.

Structure Imbalance

The structure description is as follows:

Field	Description	
referencePrice	Optional reference price	
pairedQuantity	Optional paired quantity at current reference price	
askimbalance	Optional not paired offer quantity at current reference price	
bidImbalance	Optional not paired bid quantity at current reference price	

3.4.7 **Status**

Description Provides the instrument trading status and the market trading status.

Structure Status

The structure description is as follows:

Field	Description	
marketStatus	Market status. See enumeration <i>TradingStatus</i> for the possible values.	
exchangeMarketStatus	Raw exchange market status as provided by the exchange	
marketIntegrity	Market integrity. See enumeration <i>Integrity</i> for the possible values.	
Instrument trading status. securityStatus See enumeration TradingStatus for the possible values.		
exchangeSecurityStatus Raw exchange instrument status as provided by the exchange		
bookIntegrity	Instrument integrity.	

UltraBook UB 33 User Guide



Field	Description	
	See enumeration <i>Integrity</i> for the possible values.	
recoveryInProgress	Bit flag to indicate that UB is trying to update the order book whose integrity status is INTEGRITY_BEST_EFFORT	

3.4.8 MarketStatus

Description Provides the market trading status.

Structure MarketStatus

The structure description is as follows:

Field	Description
marketStatus	Market status. See enumeration <i>TradingStatus</i> for the possible values.
exchangeMarketStatus	Raw exchange market status as provided by the exchange
marketIntegrity	Market integrity.
	See enumeration <i>Integrity</i> for the possible values.

3.4.9 UpdateInfo

Description Provides the event notifications.

Structure UpdateInfo

The structure description is as follows:

|--|

Field	Description
timestamp	Timestamp of the last event which updated the current view
exchangeTimestamp	Exchange packet timestamp of the last event which updated the current view
exchangeSequenceNumber	Exchange sequence number of the last message which updated the current view
flags	Bit flags to indicate the kind of information that has been updated since the last time the view has been read. Flags are reset each time the user reads. See enumeration <i>UpdateFlags</i> for the possible values.

3.4.10 InternalStatistics

Description Provides counters used to ensure that the data returned to the user have not been modified while being read in shared memory.

Structure InternalStatistics

The structure description is as follows:

Field	Description
readCount	Number of times the levels have been read by the user. This counter is incremented each time methods level() or levels() are called.
readFailedCount	Number of times UB failed to read the shared memory to return consistent data to the user when methods level() or levels() are called: data may indeed be modified while being read before being returned to the user.
reauraneucount	This counter is incremented each time that UB has to read again the shared memory to get consistent data to be returned to the user. The counter is not incremented if the first read achieves to get consistent data.

UltraBook UB 34 User Guide



3.4.11 Instrument

Description Provides the raw exchange specific instrument data.

Structure Instrument

The structure description is as follows:

Field	Description
instrumentType	Protocol used to receive the instrument data. See enumeration <i>InstrumentType</i> for the possible values.
InstrumentData	Exchange specific structure which provides the raw instrument data as provided by the exchange. Refer to the exchange specifications for more details.

3.5 Enumerations

Some descriptions may be market dependent, refer to section *Market Specifics* for more details.

3.5.1 TradingStatus

Description Instrument and market status list.

Enumeration TradingStatus

Values	Description
TRADING_STATUS_OPEN	Open trading status.

Values	Description
	Orders and / or quotes submission is allowed with matching (regular trading) within market hours.
TRADING_STATUS_EXTENDED	Extended hours trading status.
	Orders and / or quotes submission is allowed with matching outside the standard market hours.
TRADING_STATUS_QUOTATION	Quotation-only trading status.
	Orders and / or quotes submission is allowed with no matching.
TRADING_STATUS_HALTED	Suspended or halted trading status.
	Orders and / or quotes submission may be allowed or not with no matching.
TRADING_STATUS_CLOSED	Closed trading status.
	Orders and / or quotes submission is not allowed.
TRADING_STATUS_INITIAL	This status is the initial instrument and / or market trading status.
	It is also the status assigned to an instrument and / or market when a trading status received from the exchange cannot be easily mapped against the supported trading statuses.

The following statuses can be combined with the previous ones:

Values	Description
TRADING_STATUS_SHORT_SELL_RESTRICTION	Short sell restriction trading status.
TRADING_STATUS_GUESSED_FLAG	Flag indicating the status is guessed: the mapping of the trading status provided by the exchange is not straightforward.



3.5.2 TradeType

Description Trade type list.

Enumeration TradeType

Values	Description
TRADE_TYPE_NEW	New trade
TRADE_TYPE_CANCEL	Canceled trade
TRADE_TYPE_UPDATE	Updated trade
TRADE_TYPE_INVALID	Not a valid trade

3.5.3 Integrity

Description Book / market integrity list.

Enumeration Integrity

Values	Description
INTEGRITY_CLEAN	No error, no data loss
INTEGRITY_BEST_EFFORT	The order book information or the market status is probably not accurate because of gaps and data loss
INTEGRITY_STALLED	The order book information or the market status is probably old

3.5.4 UpdateFlags

Description Update flags list.

Enumeration UpdateFlags

Values	Description
UPDATE_FLAGS_TRADE	Trade structure has been updated
UPDATE_FLAGS_TRADING_STATUS	The instrument trading status or the market trading status has been updated
UPDATE_FLAGS_BOOK_PRICES	The instrument prices have been updated
UPDATE_FLAGS_BOOK_IMBALANCE	The instrument imbalance has been updated
UPDATE_FLAGS_INTEGRITY	The instrument integrity or the market integrity has been updated
UPDATE_FLAGS_LEVEL_0_NORMAL	The top of the book for the normal quantity has been updated
UPDATE_FLAGS_LEVEL_1_NORMAL	Level 1 for the normal quantity has been updated
UPDATE_FLAGS_LEVEL_2_NORMAL	Level 2 for the normal quantity has been updated
UPDATE_FLAGS_LEVEL_3_NORMAL	Level 3 for the normal quantity has been updated
UPDATE_FLAGS_LEVEL_4_NORMAL	Level 4 for the normal quantity has been updated
UPDATE_FLAGS_LEVEL_0_IMPLIED	The top of the book for the implied quantity has been updated
UPDATE_FLAGS_LEVEL_1_IMPLIED	Level 1 for the implied quantity has been



Values	Description
	updated
UPDATE_FLAGS_LEVEL_2_IMPLIED	Level 2 for the implied quantity has been updated
UPDATE_FLAGS_LEVEL_3_IMPLIED	Level 3 for the implied quantity has been updated
UPDATE_FLAGS_LEVEL_4_IMPLIED	Level 4 for the implied quantity has been updated
UPDATE_FLAGS_LEVEL_0_CUSTOMER	The top of the book for the customer quantity has been updated
UPDATE_FLAGS_LEVEL_1_CUSTOMER	Level 1 for the customer quantity has been updated
UPDATE_FLAGS_LEVEL_2_CUSTOMER	Level 2 for the customer quantity has been updated
UPDATE_FLAGS_LEVEL_3_CUSTOMER	Level 3 for the customer quantity has been updated
UPDATE_FLAGS_LEVEL_4_CUSTOMER	Level 4 for the customer quantity has been updated
UPDATE_FLAGS_LEVEL_0_ALL_OR_NONE	The top of the book for the all or none quantity has been updated
UPDATE_FLAGS_LEVEL_1_ALL_OR_NONE	Level 1 for the all or none quantity has been updated
UPDATE_FLAGS_LEVEL_2_ALL_OR_NONE	Level 2 for the all or none quantity has been updated
UPDATE_FLAGS_LEVEL_3_ALL_OR_NONE	Level 3 for the all or none quantity has been updated
UPDATE_FLAGS_LEVEL_4_ALL_OR_NONE	Level 4 for the all or none quantity has been updated

3.5.5 QuantityType

Description Quantity type list.

Enumeration QuantityType

Values	Description
QUANTITY_TYPE_NORMAL	Total quantity as provided by the exchange
QUANTITY_TYPE_IMPLIED	Implied quantity as provided by the exchange
QUANTITY_TYPE_CUSTOMER	Customer quantity as provided by the exchange
QUANTITY_TYPE_ALL_OR_NONE	All or none quantity as provided by the exchange

3.5.6 InstrumentType

Description Protocol list.

Enumeration InstrumentType

Values	Description
INSTRUMENT_TYPE_UNKNOWN	Unknown protocol
INSTRUMENT_TYPE_CSM	Instrument received via the CSM protocol
INSTRUMENT_TYPE_ARCA_OPTIONS	Instrument received via the ARCAOPTIONS protocol

UltraBook UB 37 User Guide



3.5.7 UpdatableKind

Description Updated object type list.

Enumeration UpdatableKind

Values	Description
UPDATABLE_UNKNOWN	Unknown object
UPDATABLE_MARKET	The updated object is a Market object
UPDATABLE_VIEW	The updated object is a view objet

UltraBook UB 38 User Guide



4. Technical Architecture

This section should be read in conjunction with the Celoxica Manager User Guide.

4.1 UB Daemon Monitoring

UB is monitored by the Master Daemon: this daemon starts and stops processes, acts as a watchdog and sends alerts in case of issues.

UB uses the Logger Daemon: this daemon reads the log messages written to shared memory by UB, formats them and writes the formatted log messages to files.




Figure 5 – UB daemon

UltraBook UB 39 User Guide



4.2 Shared Memory Allocation

The shared memory is represented as a file in the /dev/shm filesystem. The size of this filesystem naturally determines the maximum size of the shared memory segment(s) that can be allocated for UB.

The shared memory must be allocated before starting the UB daemon using the "ultrabook-manage-memory" tool, otherwise errors will be raised and logged.

It is recommended that the "ultrabook-manage-memory" tool be monitored by the Master Daemon; see the Master Daemon configuration parameter config.init-appli.

As the "ultrabook-manage-memory" tool uses the Logger Daemon, the logs written by the "ultrabook-manage-memory" tool are accessible using the viewlog command.

The "ultrabook-manage-memory" tool has the following options:

Option	Description
-n orname <server-name></server-name>	Allocates shared memory to server named <server-name></server-name>
-m ormarket <market-count></market-count>	Limits the number of markets to <market-count></market-count>
	If not specified, 8 markets will be created by default.
-s orsubscription <subscription-count></subscription-count>	Limits the number of instrument subscriptions to <subscription-count></subscription-count>
-G <gigabytes></gigabytes>	Limits the allocated memory to <gigabytes> GiB</gigabytes>
-M <megabytes></megabytes>	Limits the allocated memory to <megabytes> MiB</megabytes>
dry-run	Does not allocate or create anything, but only prints information about what would be done
remove	Removes the existing shared memory for the given server name

Option	Description
print	Prints the existing shared memory details for the given server name
-h orhelp	Prints the help

The maximum number of readers is automatically set to 32.

UB supports a maximum of 1,000,000 instruments per market.

UltraBook UB 40 User Guide



The maximum number of instrument subscriptions is computed by the "ultrabook-manage-memory" tool as follows:

1. If the memory amount is provided using –M or –G options and the number of subscriptions is not provided using –s option, the maximum number of subscriptions will be rounded up down to the highest power of two which fits in memory.

For example:

```
The user requires 1 GiB shared memory for 2 markets.

you@yourmachine $ ./bin/ultrabook-manage-memory --name ub-server-a -G 1 --market 2
UB: Parsed command-line: { serverName: ub-server-a, marketCount: 2, subscriptionCount: 0, size: 1073741824, dryRun: 0, remove: 0, print: 0 }

Utrabook allocation summary:
- server name: ub-server-a
- menory usage: 718.595 MiB
- maximum # of readers: 32
- maximum # of markets: 2
- maximum # of instruments: 2000000
- maximum # of subscriptions: 16384

In this example, the computed maximum number of subscriptions is 16384.
```

2. If the number of subscriptions is provided using –s option and the memory amount is not provided using either –M or –G options, the maximum number of subscriptions will be rounded up to the lowest power of two greater than the specified maximum and the allocated shared memory will be deduced.

For example:

```
The user requires 10000 subscriptions for 2 markets.

you@yourmachine $ ./bin/ultrabook-manage-memory --name ub-server-a --subscription 10000 --market 2
UB: Parsed command-line: { serverName: ub-server-a, marketCount: 2, subscriptionCount: 10000, size: 0, dryRun: 0, remove: 0, print: 0 }

Utrabook allocation summary:
- server name: ub-server-a
- memory usage: 718.595 MiB
- maximum # of readers: 32
- maximum # of markets: 2
- maximum # of instruments: 2000000
- maximum # of subscriptions: 16384

In this example, the computed maximum number of subscriptions is 16384.
```

3. If both the memory amount and the number of subscriptions are provided, the maximum number of subscriptions will be rounded up to the lowest power of two greater than the specified maximum and the allocated shared memory will be deduced (the specified number of subscriptions prevails over the specified memory amount).

UltraBook UB 41 User Guide



For example:

```
The user requires 2 GiB shared memory and 10000 subscriptions for 2 markets.

you@yourmachine $ ./bin/ultrabook-manage-memory --name ub-server-a -G 2 --subscription 10000 --market 2
UB: Parsed command-line: { serverName: ub-server-a, marketCount: 2, subscriptionCount: 10000, size: 2147483648, dryRun: 0, remove: 0, print: 0 }

Utrabook allocation summary:
    - server name: ub-server-a
    - memory usage: 718.595 MiB
    - maximum # of readers: 32
    - maximum # of arkets: 2
    - maximum # of instruments: 2000000
    - maximum # of subscriptions: 16384

In this example, the computed maximum number of subscriptions is 16384.
```

A single reader can handle the maximum number of subscriptions as computed when allocating the shared memory with the insurance of no notification loss.

UltraBook UB 42 User Guide



4.3 Shared Memory Usage

4.3.1 Memory Consumption

The shared memory is attached only once on the server side. On the client side, the shared memory is attached once for the session object but also each time for each reader object.

As a consequence, when using the "top" tool, the user will get the following memory information:

- The virtual memory (VIRT counter) comprises several times the allocated shared memory
- The actual memory consumption is obtained by summing the SHR counter (shared memory) and the RES counter (resident memory)

4.3.2 Memory Lock

For performance purpose, Celoxica strongly recommends granting rights to the binaries to lock the memory on both the server and the client sides.

Giving permissions to lock the memory can be achieved:

1. Using the "setcap" command when this utility is available

This does not work over the NFS (Network File System).

2. Or by modifying /etc/security/limits.conf to increase the memlock counter.

# <domain></domain>	<type></type>	<item></item>	<value></value>	
*	-	memlock	unlimited	

The documentation is accessible though standard man pages: "man limits.conf".

Once the limits are changed the user must login again.

UltraBook UB 43 User Guide



5. Shipped Examples

UB is shipped with a "hello world" example showcasing most of UB's functional aspects and a "reader" example intending as a coding base for a client trading application using UB.

The two examples are intended to be easy to understand and to illustrate the use of the UB user API; they are therefore written with simplicity rather than speed in mind, and contains detailed comments.

To compile the example:

- 1. cd ~
- celoxica_copy_examples
- cd ~/celoxica-examples/ultrabook/hello_world or cd ~/celoxica-examples/ultrabook/reader
- 4. Is -la

At this stage it is possible to review the files of the example.

5. make

To run the server:

- cd ~/celoxica-examples/ultrabook/hello_world or cd ~/celoxica-examples/ultrabook/reader
- 2. ub -f ub-hello.cfg

It is necessary to configure the UB server correctly. By default the ub-hello.cfg is provided. It connects to the CBOE Streaming Market CSM test environment. Note that on this environment there are very few book updates.

Note that ub is installed in /usr/bin

3. leave your server running (do not terminate it)

To run the example:

- cd ~/celoxica-examples/ultrabook/hello_world or cd ~/celoxica-examples/ultrabook/reader
- ./hello_world or ./reader
 Note that the examples do not need any parameters.
- Observe the output
- 4. Terminate the example

If the example does not terminate properly, the client will therefore be hanging on the server side indefinitely: you will not be able to run the example with the same server again.

UltraBook UB 44 User Guide



6. Market Specifics

This section describes market specifics for the supported protocols.

6.1 ARCAOptions

This section describes the configuration specific settings for the following markets:

Market	Protocol	Description
ARCA OX	ArcaBook for Options	NYSE ARCA Option
AMEX OX	ArcaBook for Options	NYSE AMEX Option

The protocol to be set in *config.markets.market* is **ARCAOptions**.

Note:

Complex options are not supported yet.

6.1.1 Source

Documentation NYSE ArcaBook for options Client Specification

Version 3.15

Date September 27, 2012

6.1.2 Symbology

Valid identifier schemes are as follows:

Values	Support	Examples
key	✓	key://421048290333

Values	Support	Examples
index	\checkmark	index://001e03e4.arcaox
local	✓	local://aapl.arcaox
osi	✓	osi://aapl 120201P00012340.arcaox
fsi	X	-

6.1.3 Reference Data

The raw exchange specific instrument data structures are constructed from the following exchange messages:

Exchange Message	Type
Series Index Mapping	'm'
Underlying Index Mapping	'n'

6.1.4 Instrument Trading Status

TRADING_STATUS_INITIAL is set as follows:

Values	Yes / No
TRADING_STATUS_OPEN	√
TRADING_STATUS_EXTENDED	X
TRADING_STATUS_QUOTATION	X
TRADING_STATUS_HALTED	X
TRADING_STATUS_CLOSED	X
TRADING_STATUS_SHORT_SELL_RESTRICTION	X
TRADING_STATUS_GUESSED_FLAG	√



The instrument trading status is initialized with TRADING_STATUS_INITIAL and is then updated as follows:

upuateu as follows.		
Values	Support	Comments
TRADING_STATUS_OPEN	√	Generated from message System Event 'v' where Event Code equals to:
		 'N' (open indication dark series)
		'O' (open indication series)
		'o' (open indication)'T' (unhalt dark series)
		• 'U' (unhalt series)
		• 'u' (unhalt underlying)
TRADING_STATUS_EXTENDED	X	-
TRADING_STATUS_QUOTATION	X	-
TRADING_STATUS_HALTED	✓	Generated from message System Event 'v' where Event Code equals to:
		• 'S' (halt series)
		• 's' (halt underlying)
TRADING_STATUS_CLOSED	✓	Generated from message System Event 'v' where Event Code equals to:
		'X' (close indication series)
		 'x' (close indication underlying)

Values	Support	Comments
TRADING_STATUS_SHORT_SELL_RESTRICTION	X	-
TRADING_STATUS_GUESSED_FLAG	√	-
TRADING_STATUS_INITIAL	√	Generated from message System Event 'v' where Event Code equals to:
		 'D' (clear underlying ask)
		• 'E' (clear underlying bid)
		• 'F' (clear underlying)
		'L' (light up a dark series)
		'A' Clear series ask
		• 'B' Clear series bid
		• 'C' Clear series
		'G' Clear subscription ask
		'H' Clear subscription bid
		'I' Clear subscription

6.1.5 Market Trading Status

TRADING_STATUS_INITIAL is set as follows:

Values	Yes / No
TRADING_STATUS_OPEN	√

UltraBook UB 46 User Guide



Values	Yes / No
TRADING_STATUS_EXTENDED	X
TRADING_STATUS_QUOTATION	X
TRADING_STATUS_HALTED	X
TRADING_STATUS_CLOSED	X
TRADING_STATUS_SHORT_SELL_RESTRICTION	X
TRADING_STATUS_GUESSED_FLAG	✓

The market trading status remains TRADING_STATUS_INITIAL as no trading status at the market level is published.

6.1.6 Instrument Integrity

The instrument integrity remains INTEGRITY_CLEAN.

6.1.7 Market Integrity

Support	Comments
√	Initial status
√	This status applies as soon as there is sequence gap.
	No recovery process is undertaken (recovery is not implemented yet).
X	-
	√

6.1.8 Trade Type

Values	Support	Comments
TRADE_TYPE_NEW	\checkmark	Generated from message Last Sale 'x'
TRADE_TYPE_CANCEL	√	Generated from message Trade Bust or Correction 'u' where Even Code = 'B' (Trade bust)
TRADE_TYPE_UPDATE	√	Generated from message Trade Bust or Correction 'u' where Even Code = 'C' (Trade correction)

6.1.9 Update Flags

Values	Support	Comments
UPDATE_FLAGS_TRADE	√	-
UPDATE_FLAGS_TRADING_STATUS	√	-
UPDATE_FLAGS_BOOK_PRICES	X	-
UPDATE_FLAGS_BOOK_IMBALANCE	√	Generated from message Auction Imbalance 'i'.
		Only Imbalance.referencePrice and Imbalance.pairedQuantity are provided.
UPDATE_FLAGS_INTEGRITY	√	-
UPDATE_FLAGS_LEVEL_0_NORMAL	✓	-
UPDATE_FLAGS_LEVEL_1_NORMAL	✓	-
UPDATE_FLAGS_LEVEL_2_NORMAL	✓	-
UPDATE_FLAGS_LEVEL_3_NORMAL	✓	-
UPDATE_FLAGS_LEVEL_4_NORMAL	✓	-
UPDATE_FLAGS_LEVEL_0_IMPLIED	X	-

UltraBook UB 47 User Guide



Values	Support	Comments
UPDATE_FLAGS_LEVEL_1_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_2_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_3_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_4_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_0_CUSTOMER	√	-
UPDATE_FLAGS_LEVEL_1_CUSTOMER	√	-
UPDATE_FLAGS_LEVEL_2_CUSTOMER	✓	-
UPDATE_FLAGS_LEVEL_3_CUSTOMER	√	-
UPDATE_FLAGS_LEVEL_4_CUSTOMER	√	-
UPDATE_FLAGS_LEVEL_0_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_1_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_2_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_3_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_4_ALL_OR_NONE	X	-

6.1.10 Quantity Type

Values	Support	Comments
QUANTITY_TYPE_NORMAL	√	Corresponds to the Total Contract / Shares AQ_QUANTITY from message Aggregate Quote 'q'
QUANTITY_TYPE_IMPLIED	X	-

Values	Support	Comments
QUANTITY_TYPE_CUSTOMER	√	Corresponds to the Customer Volume AQ_CUSTOMER_VOLUME from message Aggregate Quote 'q'
QUANTITY_TYPE_ALL_OR_NONE	X	-

6.1.11 Raw Exchange Specific Data

The raw exchange specific data is populated from the following exchange messages:

Field	UB Structure	Correspondence
exchangeInstrumentType	InstrumentType	SecurityType AQ_SECURITY_TYPE from message Underlying Index Mapping 'n'
exchangeTotalTradedVolume	TradeList	Not populated
exchangeSettlementDate	Prices	Not populated
exchangeMarketStatus	Status / MarketStatus	Not populated
exchangeSecurityStatus	Status	EventCode AQ_EVENT_CODE from message System Event 'v'
exchangeFlags	Trade	SaleCondition from message Last Sale 'x'
exchangeTradeId	Trade	TradeReferenceNumber from message Last Sale 'x'

UltraBook UB 48 User Guide



6.2 CSM

This section describes the configuration specific settings for the following markets:

Market	Protocol	Description
CBOE	CBOE Streaming Market	Chicago Board Options Exchange
C2	CBOE Streaming Market	CBOE C2
One Chicago	CBOE Streaming Market	CBOE One Chicago
CFE	CBOE Streaming Market	CBOE Futures Exchange
CBSX	CBOE Streaming Market	CBOE Stock Exchange

The protocol to be set in *config.markets.market* is **CSM**.

6.2.1 Source

Documentation CBOE Streaming Market CSM

Version 1.3.2

Date March 30, 2012

6.2.2 Symbology

Valid identifier schemes are as follows:

Values	Support	Examples
key	\checkmark	key://421048290333
index	√	index://001e03e4.cboe
local	√	local://aapl.cboe
osi	√	osi://aapl 120201P00012340.cboe

Values	Support	Examples			
fsi	\checkmark	fsi://VIX 120201.cfe			

6.2.3 Reference Data

The raw exchange specific instrument data structures are constructed from the following exchange messages:

Exchange Message Type
Security Definition 'd'

6.2.4 Instrument Trading Status

TRADING_STATUS_INITIAL is set as follows:

Values	Support
TRADING_STATUS_OPEN	\checkmark
TRADING_STATUS_EXTENDED	X
TRADING_STATUS_QUOTATION	X
TRADING_STATUS_HALTED	X
TRADING_STATUS_CLOSED	X
TRADING_STATUS_SHORT_SELL_RESTRICTION	X
TRADING_STATUS_GUESSED_FLAG	✓

The instrument trading status is initialized with TRADING_STATUS_INITIAL and is then updated as follows:

Values	Support	Comments
TRADING_STATUS_OPEN	√	Generated from
		messages Current



Values	Support	Comments
		Market Refresh 'W' and Current Market Update 'X' where Security Trading Status equals to:
		• 17 (market open)
		• 23 (fast market)
		 25 (strategy market quotes non-firm)
TRADING_STATUS_EXTENDED	X	-
TRADING_STATUS_QUOTATION	✓	Generated from messages Current Market Refresh 'W' and Current Market Update 'X' where Security Trading Status equals to:
		• 21 (pre-open)
		 22 (market in opening rotation)
		 24 (strategy market in opening rotation)
TRADING_STATUS_HALTED	√	Generated from messages Current Market Refresh 'W' and Current Market Update 'X' where Security Trading Status equals to:
		• 2 (market halted)
		26 (market suspended)

Values	Support	Comments
TRADING_STATUS_CLOSED	√	Generated from messages Current Market Refresh 'W' and Current Market Update 'X' where Security Trading Status equals to:
		 18 (market closed)
TRADING_STATUS_SHORT_SELL_RESTRICTION	X	-
TRADING_STATUS_GUESSED_FLAG	√	-
TRADING_STATUS_INITIAL	√	-

6.2.5 Market Trading Status

TRADING_STATUS_INITIAL is set as follows:

Values	Yes / No
TRADING_STATUS_OPEN	\checkmark
TRADING_STATUS_EXTENDED	X
TRADING_STATUS_QUOTATION	X
TRADING_STATUS_HALTED	X
TRADING_STATUS_CLOSED	X
TRADING_STATUS_SHORT_SELL_RESTRICTION	X
TRADING_STATUS_GUESSED_FLAG	✓

The market trading status remains TRADING_STATUS_INITIAL as no trading status at the market level is published.



6.2.6 Instrument Integrity

The instrument integrity remains INTEGRITY_CLEAN.

6.2.7 Market Integrity

Values	Support	Comments
INTEGRITY_CLEAN	√	Initial status
INTEGRITY_BEST_EFFORT	√	This status applies as soon as there is sequence gap.
		No recovery process is undertaken (recovery is not implemented yet).
INTEGRITY_STALLED	X	-

6.2.8 Trade Type

Values	Support	Comments
TRADE_TYPE_NEW	√	Generated from message Ticker where Trade Condition <> 'CANC' or 'CNCO'
TRADE_TYPE_CANCEL	√	Generated from message Ticker where Trade Condition = 'CANC' or 'CNCO'
TRADE_TYPE_UPDATE	Х	-

6.2.9 Update Flags

Values	Support	Comments
--------	---------	----------

Values	Support	Comments
UPDATE_FLAGS_TRADE	√	-
UPDATE_FLAGS_TRADING_STATUS	√	-
UPDATE_FLAGS_BOOK_PRICES	X	-
UPDATE_FLAGS_BOOK_IMBALANCE	✓	Generated from message EOP.
		Only Imbalance.referencePrice and Imbalance.pairedQuantity are provided.
UPDATE_FLAGS_INTEGRITY	✓	-
UPDATE_FLAGS_LEVEL_0_NORMAL	√	CSM publishes only top of the book
UPDATE_FLAGS_LEVEL_1_NORMAL	X	-
UPDATE_FLAGS_LEVEL_2_NORMAL	X	-
UPDATE_FLAGS_LEVEL_3_NORMAL	X	-
UPDATE_FLAGS_LEVEL_4_NORMAL	X	-
UPDATE_FLAGS_LEVEL_0_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_1_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_2_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_3_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_4_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_0_CUSTOMER	√	CSM publishes only top of the book
UPDATE_FLAGS_LEVEL_1_CUSTOMER	Х	-
UPDATE_FLAGS_LEVEL_2_CUSTOMER	Х	-
UPDATE_FLAGS_LEVEL_3_CUSTOMER	X	-

UltraBook UB 51 User Guide



Values	Support	Comments
UPDATE_FLAGS_LEVEL_4_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_0_ALL_OR_NONE	✓	CSM publishes only top of the book
UPDATE_FLAGS_LEVEL_1_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_2_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_3_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_4_ALL_OR_NONE	X	-

6.2.10 Quantity Type

Values	Support	Comments
QUANTITY_TYPE_NORMAL	√	Corresponds to the Total Limit Volume from messages Current Market Refresh 'W' and Current Market Update 'X'
QUANTITY_TYPE_IMPLIED	X	-
QUANTITY_TYPE_CUSTOMER	√	Corresponds to the Customer Limit Volume from messages Current Market Refresh 'W' and Current Market Update 'X'
QUANTITY_TYPE_ALL_OR_NONE	√	Corresponds to the Total Contingency Volume from messages Current Market Refresh 'W' and Current Market Update 'X'

6.2.11 Raw Exchange Specific Data

The raw exchange specific data is populated from the following exchange messages:

Field	UB Structure	Correspondence
exchangeInstrumentType	InstrumentType	Security Type from message Security Definition 'd'
exchangeTotalTradedVolume	TradeList	Not populated
exchangeSettlementDate	Prices	Not populated
exchangeMarketStatus	Status / MarketStatus	Not populated
exchangeSecurityStatus	Status	Security Trading Status from messages Current Market Refresh 'W' and Current Market Update 'X'
exchangeFlags	Trade	Trade Condition from message Ticker 'X' (exchangeFlags lower bits are populated)
exchangeTradeld	Trade	Not populated

UltraBook UB 52 User Guide



6.3 OPRA_BINARY

This section describes the configuration specific settings for the following markets:

Market	Protocol	Description
OPRA	Binary	OPRA Binary

The protocol to be set in *config.markets.market* is **OPRA_BINARY**.

This protocol is not supported yet.

6.3.1 Source

Documentation OPRA Binary Data Recipient Interface Specification

Version 1.0

Date April 17, 2012

6.3.2 Symbology

Valid identifier schemes are as follows:

Values	Support	Examples
key	√	key://421048290333
index	X	-
local	✓	local://aapl 120201P00012340.opra
osi	√	osi://aapl 120201P00012340.opra
fsi	X	-

6.3.3 Instrument Trading Status

Instrument trading status is not available.

6.3.4 Market Trading Status

Market trading status is mapped as follows:

Values	Support	Comments
TRADING_STATUS_OPEN	√	Generated from message of category 'H' where Type equals to:
		• 'D' (good morning)
TRADING_STATUS_EXTENDED	X	-
TRADING_STATUS_QUOTATION	X	-
TRADING_STATUS_HALTED	X	-
TRADING_STATUS_CLOSED	√	Generated from message of category 'H' where Type equals to:
		'G' (early market close)
		 'H' (end of transaction reporting)
TRADING_STATUS_SHORT_SELL_RESTRICTION	X	-
TRADING_STATUS_GUESSED_FLAG	X	-
TRADING_STATUS_INITIAL	√	-

6.3.5 Trade Type



Values	Support	Comments
TRADE_TYPE_NEW	√	Generated from message of category 'a' where Type equals to:
		• ''(REGULAR)
		• 'B' (OSEQ)
		• 'D' (LATE)
		• 'F' (OPEN)
		• 'H' (OPNL)
		• 'I' (AUTO)
		• 'J' (REOP)
		• 'K' (AJST)
		• 'L' (SPRD)
		• 'M' (STDL)
		• 'N' (STPD)
		• 'P' (BWRT)
		• 'Q' (CMBO)
		• 'R' (SPIM)
		• 'S' (ISOI)
		• 'T' (BNMT)
		• 'X' (XMPT)
TRADE_TYPE_CANCEL	√	Generated from message of category 'a' where Type equals to:
		• 'A' (CANC)
		• 'C' (CNCL)
		• 'E' (CNCO)
		• 'G' (CNOL)

Values	Support	Comments	
		• 'O' (CSTP)	
TRADE_TYPE_UPDATE	Х	-	

6.3.6 Update Flags

Values	Support	Comments
UPDATE_FLAGS_TRADE	√	-
UPDATE_FLAGS_TRADING_STATUS	✓	-
UPDATE_FLAGS_BOOK_PRICES	√	Only open_price, close_price, high_price and low_price are optionally provided.
		Generated from messages of category 'f'.
		Generated from messages of category 'a' where Type equals to:
		• 'H' (OPNL)
		• 'J' (REOP)
UPDATE_FLAGS_BOOK_IMBALANCE	Х	-
UPDATE_FLAGS_INTEGRITY	✓	-
UPDATE_FLAGS_LEVEL_0_NORMAL	✓	-
UPDATE_FLAGS_LEVEL_1_NORMAL	Х	-
UPDATE_FLAGS_LEVEL_2_NORMAL	X	-
UPDATE_FLAGS_LEVEL_3_NORMAL	X	-



Values	Support	Comments
UPDATE_FLAGS_LEVEL_4_NORMAL	X	-
UPDATE_FLAGS_LEVEL_0_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_1_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_2_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_3_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_4_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_0_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_1_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_2_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_3_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_4_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_0_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_1_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_2_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_3_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_4_ALL_OR_NONE	Х	-

Values	Support	Comments
QUANTITY_TYPE_CUSTOMER	X	-
QUANTITY_TYPE_ALL_OR_NONE	X	-

6.3.7 Quantity Type

Values	Support	Comments
QUANTITY_TYPE_NORMAL	√	-
QUANTITY_TYPE_IMPLIED	X	-

UltraBook UB 55 User Guide



6.4 PHLXTopoV3

This section describes the specifics supported by the following markets:

Market	Protocol	Description
PHLX	TOPO	NASDAQ OMX PHLX Top Of PHLX Options
NOM	BONO	NASDAQ OMX NOM Best Of NASDAQ Options
BX Option	Тор	NASDAQ OMX BX Options Top of Market

The protocol to be set in *config.markets.market* is **PHLXTopoV3**.

6.4.1 Source

Documentation NASDAQ OMX PHLX Market Data Feed Top of PHLX Options

 Version
 3.00

 Date
 N/A

6.4.2 Symbology

Valid identifier schemes are as follows:

Values	Support	Examples
key	/	key://421048290333
index	✓	index://001e03e4.phlx
local	\checkmark	local://aapl.phlx
osi	✓	osi://aapl 120201P00012340.phlx
fsi	X	-

6.4.3 Reference Data

The raw exchange specific instrument data structures are constructed from the following exchange messages:

Exchange Message Type
Options Directory 'D'

6.4.4 Instrument Trading Status

TRADING_STATUS_INITIAL is set as follows:

Values	Support
TRADING_STATUS_OPEN	/
TRADING_STATUS_EXTENDED	X
TRADING_STATUS_QUOTATION	X
TRADING_STATUS_HALTED	X
TRADING_STATUS_CLOSED	X
TRADING_STATUS_SHORT_SELL_RESTRICTION	X
TRADING_STATUS_GUESSED_FLAG	√

The instrument trading status is initialized with TRADING_STATUS_INITIAL and is then updated as follows:

Values	Support	Comments
TRADING_STATUS_OPEN	✓	Generated from message Security Open / Closed 'O' where Open State equals to 'Y' (Open for auto execution) if Current Trading State from message Trading Action



Values	Support	Comments
		'H' equals to 'T' (Trading resumed)
TRADING_STATUS_EXTENDED	X	-
TRADING_STATUS_QUOTATION	X	-
TRADING_STATUS_HALTED	√	a) Generated from message Trading Action 'H' where Current Trading State equals to 'H' (Halt in effect)
		b) Generated from message Security Open / Closed 'O' where Open State equals to 'N' (Closed for auto execution) if Current Trading State from message Trading Action 'H' equals to 'T' (Trading resumed)
TRADING_STATUS_CLOSED	X	-
TRADING_STATUS_SHORT_SELL_RESTRICTION	X	-
TRADING_STATUS_GUESSED_FLAG	√	-
TRADING_STATUS_INITIAL	✓	-

6.4.5	Market	Trading	Status
-------	--------	----------------	---------------

TRADING_STATUS_INITIAL is set as follows:

Values	Yes / No
TRADING_STATUS_OPEN	\checkmark
TRADING_STATUS_EXTENDED	X
TRADING_STATUS_QUOTATION	X
TRADING_STATUS_HALTED	X
TRADING_STATUS_CLOSED	X
TRADING_STATUS_SHORT_SELL_RESTRICTION	X
TRADING_STATUS_GUESSED_FLAG	✓

The instrument trading status is initialized with TRADING_STATUS_INITIAL and is then updated as follows:

Values	Support	Comments
TRADING_STATUS_OPEN	√	Generated from message System Event 'S' where Event Code equals to 'Q' (Start of opening process)
TRADING_STATUS_EXTENDED	√	Generated from message System Event 'S' where Event Code equals to 'N' (End of normal hours processing)
TRADING_STATUS_QUOTATION	√	Generated from message System Event 'S' where Event Code equals to 'S' (Start of system hours)
TRADING_STATUS_HALTED	X	-
TRADING_STATUS_CLOSED	√	Generated from message System Event 'S' where



Values	Support	Comments
		Event Code equals to:
		'L' (End of late hours processing)
		 'E' (End of system hours)
TRADING_STATUS_SHORT_SELL_RESTRICTION	X	-
TRADING_STATUS_GUESSED_FLAG	✓	-
TRADING_STATUS_INITIAL	√	-

6.4.6 Instrument Integrity

The instrument integrity remains INTEGRITY_CLEAN.

6.4.7 Market Integrity

Values	Support	Comments
INTEGRITY_CLEAN	√	Initial status
INTEGRITY_BEST_EFFORT	✓	This status applies as soon as there is sequence gap.
		No recovery process is undertaken (recovery is not implemented yet).
INTEGRITY_STALLED	Х	-

6.4.8 Trade Type

Values	Support	Comments
TRADE_TYPE_NEW	/	Generated from message Trade Report 'R'
TRADE_TYPE_CANCEL	✓	Generated from message Broken Trade Report 'X'
TRADE_TYPE_UPDATE	X	-

6.4.9 Update Flags

Values	Support	Comments
UPDATE_FLAGS_TRADE	√	-
UPDATE_FLAGS_TRADING_STATUS	\checkmark	-
UPDATE_FLAGS_BOOK_PRICES	X	-
UPDATE_FLAGS_BOOK_IMBALANCE	X	-
UPDATE_FLAGS_INTEGRITY	✓	-
UPDATE_FLAGS_LEVEL_0_NORMAL	√	PHLX publishes only top of the book
UPDATE_FLAGS_LEVEL_1_NORMAL	X	-
UPDATE_FLAGS_LEVEL_2_NORMAL	X	-
UPDATE_FLAGS_LEVEL_3_NORMAL	X	-
UPDATE_FLAGS_LEVEL_4_NORMAL	X	-
UPDATE_FLAGS_LEVEL_0_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_1_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_2_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_3_IMPLIED	Х	-

UltraBook UB 58 User Guide



Values	Support	Comments
UPDATE_FLAGS_LEVEL_4_IMPLIED	X	-
UPDATE_FLAGS_LEVEL_0_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_1_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_2_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_3_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_4_CUSTOMER	X	-
UPDATE_FLAGS_LEVEL_0_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_1_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_2_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_3_ALL_OR_NONE	X	-
UPDATE_FLAGS_LEVEL_4_ALL_OR_NONE	X	-

6.4.10 Quantity Type

Values	Support	Comments		
QUANTITY_TYPE_NORMAL	√	Corresponds to:		
		Bid Size or Ask Size from messages:		
		 Best Bid AND Ask Update Short Form 'q' 		
		 Best Bid AND Ask Update Long Form 'Q' 		
		Size from messages:		
		 Best Bid OR Ask Update 		

Values	Support	Comments	
			Short Form 'a' / 'b'
		0	Best Bid AND Ask Update Long Form 'A' / 'B'
QUANTITY_TYPE_IMPLIED	X	-	
QUANTITY_TYPE_CUSTOMER	X	-	
QUANTITY_TYPE_ALL_OR_NONE	X	-	

6.4.11 Raw Exchange Specific Data

The raw exchange specific data is populated from the following exchange messages:

Field	UB Structure	Correspondence
exchangeInstrumentType	InstrumentType	Not populated
exchangeTotalTradedVolume	TradeList	Not populated
exchangeSettlementDate	Prices	Not populated
exchangeMarketStatus	Status / MarketStatus	Event Code from message System Event 'S'
exchangeSecurityStatus	Status	Not populated
exchangeFlags	Trade	Trade Condition from message Trade Report 'R'
exchangeTradeId	Trade	Cross ID from message Trade Report 'R'

UltraBook UB 59 User Guide



7. FAQ

1. The client is hanging on the server side indefinitely

Please check the configuration node *config.control.client-timeout* setting.

Note that the "hello world" example does not use the heartbeats: the default UB server configuration file ub.cfg has the timeout monitoring deactivated (=0).

2. Shared memory allocation

Run the following command to allocate 1024 MB shared memory to the UB server named ubserver:

[you@yourmachine]\$ /usr/bin/ultrabook-manage-memory -n ubserver -M 2048

3. Shared memory removal

Either use the "ultrabook-manage-memory" tool and run the following command to remove the existing shared memory for the UB server named ub-server:

[you@yourmachine]\$ /usr/bin/ultrabook-manage-memory -n ubserver --remove

Or run the following command:

rm /dev/shm/ub-server