

ZYVORAI LABS · USER DOCUMENTATION

Zyvor Fabric

Admin Basics

2026-09-10

Operator reference for ports, auth, remote deploy, TLS, and the FluxVM dependency. For the first-hour UI path, see [Getting Started](#).

Ports / access

Port	Service
9095	zyvor-fabricd — API + production web UI (same origin)
7788	FluxVM (node-local VM engine; Fabric proxies it)
5173	Vite UI (dev only)

Web routes: marketing `/`, `/product`, `/platform`, `/security`; sign-in `/sign-in`; console `/app/*`.

Open the UI at `https://<host>:9095` or `http://127.0.0.1:9095` on the host. Never publish lab IPs in docs or tickets — use `<host>`.

Health check:

```
curl -sf http://127.0.0.1:9095/readyz | jq '{ok, store, fluxvm ok: .fluxvm.ok}'
```

Auth and admin password

JWT bearer auth (local admin by default). Optional LDAP/OIDC/PAM for system users.

Sign in at `https://<host>:9095/sign-in` with username `admin` , then open `/app` .

JWT secret and admin password

Both are auto-generated (cryptographically random) on first start if unset, and persisted so they survive restarts:

Env var	Default when unset	Persisted at
<code>ZYVOR_FABRICD_JWT_SECRET</code>	Random, once	<code>/var/lib/zyvor-fabricd/.jwt_secret</code> (mode 0600)
<code>ZYVOR_FABRICD_ADMIN_PASSWORD</code>	Random, once — never defaults to <code>admin</code>	<code>/var/lib/zyvor-fabricd/.admin_password</code>

Retrieve or manage the password with the ctl:

```
/zyvor-fabricd-ctl password --show
sudo cat /var/lib/zyvor-fabricd/.admin_password
/zyvor-fabricd-ctl password --lab-reset [PASSWORD] --rescd-flag-only
```

Set `ZYVOR_FABRICD_ADMIN_PASSWORD` (or `FABRIC_ADMIN_PASSWORD`) **before first start** if you want a known value from day one — once persisted, the file wins even if the env var is later unset.

Deploy (local and remote)

From a Fabric checkout:

Target	Command
Local full deploy	<code>./zyvor-fabricd-ctl deploy</code> (deps → build → install → start)
Bare-metal remote	<code>./scripts/deploy remote USER@HOST</code>
Remote, skip OS deps	<code>./scripts/deploy remote USER@HOST --quick</code>
Kubernetes lab	<code>./scripts/deploy k8s USER@HOST</code>

Remote bare-metal install opens `0.0.0.0:9095` (HTTPS with a self-signed cert by default). Admin password is generated on deploy unless you set `FABRIC_ADMIN_PASSWORD` / `ZYVOR_FABRICD_ADMIN_PASSWORD` , or `FABRIC_LAB_DEFAULTS=1` for a convenient lab default. Force reseed: `FORCE_ADMIN_RESET=1 ./scripts/deploy remote USER@HOST --quick` .

Useful ctl commands after install: `status` , `logs` , `verify` , `doctor` , `restart` .

TLS

```
/zyvor-fabricd-ctl tls -- # generate self-signed server cert (auto-sudo)
```

Enable the paths the ctl prints in `/etc/zyvor-fabricd/zyvor-fabricd.toml` (typically under `/etc/zyvor-fabricd/tls/`). Browsers will warn on self-signed certs in lab — replace with a real cert for production. For local HTTP-only testing, `http://127.0.0.1:9095` is fine when TLS is off.

FluxVM dependency

Fabric does **not** run QEMU itself. It orchestrates VMs through a local [FluxVM](#) instance on `127.0.0.1:7788` (lifecycle, disks, console/VNC, cgroups, per-VM netns, Network Fabric eBPF).

- Dashboard **VM driver** / readiness must show FluxVM reachable (`fluxvm.ok` on `/readyz`).
- VM Dataplane (schema v4) and Edge Maglev Services (Service Fabric v6) require FluxVM dataplane features enabled — see [VM Dataplane](#) and [Edge Dataplane](#).
- If FluxVM auth is enabled, set `driver.fluxvm_token` in `zyvor-fabricd.toml` .

Sibling checkouts of FluxVM (and GuestKit for image tooling) are expected for full image builds; see the product [README](#).

Install sketch

1. Deploy locally or `./scripts/deploy remote USER@HOST` .
2. Confirm `./zyvor-fabricd-ctl status` and `/readyz` .
3. Retrieve admin password → open `https://<host>:9095/sign-in` → `/app` .
4. Follow [Getting Started](#).

More detail: [Installation](#) · [Web UI](#) · [Production](#).

Related

- [Getting Started](#)
- [Using the Dashboard](#)
- [Common workflows](#)
- [Complete page index](#)