

TUT-1071

Simplifying HA
Cluster bootstrap
and shutdown with
SLE-HA 15 SP4

#### Roger Zhou

Sr. Engineering Manager

zzhou@suse.com



## Agenda:

- 1. SLE-HA 15 SP4 highlights to improve UI/UX
- 2. Example scenario to setup a cluster
- 3. Things behind the scene

Preventing LVM2 autoactivation during OS boot Cluster predefined configuration Cluster with the disk-based SBD in VM Cluster with the disk-less SBD Cluster stack graceful shutdown

4. Future TODO list





## SLE-HA 15 SP4 highlights to improve UI/UX

The continous effort over years ...


- Easier initial setup with crmsh predefined bootstrap profiles
- Cluster graceful shutdown using crmsh "--all" option
   It improves diskless sbd cluster and the dlm cluster
- ocfs2 'nocluster' mount option as the local mount without the cluster stack running
- pacemaker supports ocfl.1
- corosync adds resilience to cope with the Public Cloud packet inspection hiccup

### Example scenario to setup a cluster filesystem


Now, only need two commands, for example:

```
ssh -t 15sp4-1 crm cluster init -y \
-s /dev/disk/by-partlabel/sbd-154 \
-o /dev/disk/by-partlabel/ocfs2 \
-m /srv/ocfs2 -C
```

ssh -t 15sp4-2 crm cluster join -yc 15sp4-1



- NOTE
  - -C option indicates to use the lymlockd based Cluster LVM for ocfs2.
  - -u option is no longer needed now. By default crmsh bootstraps corosync with udpu.





# Behind the Scene during bootstraping



To use LVM2 in the cluster, we need prevent LVM2 autoactivation during os boot

- For the shared VG, it can not be activated without the cluster stack in the very early stage during the os boot.
- For the specified 'systemid' volumes, to prevent them getting activated during the os boot, LVM-Activate Resouce Agent levarages a new --setautoactivation lvm2 option. It defers lvm activation operations to the pacemaker stack.
- crmsh sets "no-quorum-policy=freeze" as the general advice for a dlm cluster. This avoids the "stop failure" to cause the node reset.

crmsh has the predefined cluster configuration in /etc/crm/profile.yml

- For example, the typical cluster in "microsoft-azure"

corosync.totem.token 30000

sbd.watchdog\_timeout 60





Cluster with the disk-based SBD use case

- crmsh checks watchdog, and will configure and modprobe the softdog driver during the os boot, if need.
- to set pcmk\_delay\_max 30s if the cluster is 2-node without qdevice.
- to ensure the determinate state of the stonith operationstonith-timeout > pcmk\_delay\_max + msgwait
- to prevent the fence failure to trigger double fencing
   stonith-timeout > token + consensus

Cluster with the disk-based SBD in VM environment (eg. kvm/xen, vmware, hyper-v)

 to avoid a node returns to the cluster too quickly and print the critical message "We were alleged just fenced by ..."

SBD\_DELAY\_START > token + consensus + pcmk\_delay\_max + msgwait

to avoid systemd giveup starting sbd servicecrmsh bootstrap adjusts TimeoutStartSec > SBD\_DELAY\_START



Cluster with the disk-less sbd use case

— stonith-timeout > stonith-watchdog-timeout


stonith-watchdog-timeout = 2\*SBD\_WATCHDOG\_TIMEOUT

- For the VM environment

SBD\_DELAY\_START > token + consensus + 2\*SBD\_WATCHDOG\_TIMEOUT



## Behind the Scene cluster graceful shutdown



### Behind the scene: graceful shutdown of the whole cluster

- `crm cluster stop --all` stops pacemaker at all nodes first,
   then stops corosync afterwards at all nodes.
- This intends to solve two issues of the cluster shutdown in the node-by-node approach. In that case, once the node loses quorum:
  1. the diskless sbd cluster will trigger self reset
  2. the dlm will hang and it prevents shutdown
- Furthermore, dlm\_tool implements a brand new `set\_config` option.
   crmsh leverages it to shutdown the hanging dlm above.



#### **Future TODO**

The continous effort to improve UI/UX ...

- bootstrap the priority fence delay feature for the 2-node cluster
- gradually start the large cluster, eg. tens of nodes
- speedup time by isolating csync2 for the normal bootstraping
- **—** ...
- Looking forward to your feedback. They count!







## Thank you



For more information, contact SUSE at: +1 800 796 3700 (U.S./Canada) +49 (0)911-740 53-0 (Worldwide) Maxfeldstrasse 5
90409 Nuremberg
www.suse.com

E

© SUSE LLC. All Rights Reserved. SUSE and the SUSE logo are registered trademarks of SUSE LLC in the United States and other countries. All third-party trademarks are the property of their respective owners.

General Disclaimer: This document is not to be construed as a promise by any participating company to develop, deliver, or market a product. It is not a commitment to deliver any material, code, or functionality, and should not be relied upon in making purchasing decisions. SUSE makes no representations or warranties with respect to the contents of this document, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. The development, release, and timing of features or functionality described for SUSE products remains at the sole discretion of SUSE. Further, SUSE reserves the right to revise this document and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

All SUSE marks referenced in this presentation are trademarks or registered trademarks of SUSE, LLC, Inc. in the United States and other countries. All third-party trademarks are the property of their respective owners.

