# ABTO VoIP SIP SDK for iOS

#### Short manual

1. How create phone instance and subscribe for events:

```
[AbtoPhoneInterface new] or [[AbtoPhoneInterface alloc] init]
```

2. How to initialize phone instance:

```
[phone initialize:self]
```

where self is object, that implements AbtoPhoneInterfaceObserver delegate

3. How to change settings for phone instance:

Get config interface, modify required fields, and invoke 'finalizeConfiguration'

e.g. to specify user, domain and password:

```
phone.config.regUser
phone.config.regDomain
phone.config.regPassword
```

4. How to set codecs order:

[phone.config setCodecPriority:codecIdx priority:value]

e.g. set unsigned one byte value to prioritize codecs(0 to disable all other values to enable, recommend to start from 128):

```
[phone.config setCodecPriority:PhoneAudioVideoCodecG729ab priority:129] [phone.config setCodecPriority:PhoneAudioVideoCodecPcmu priority:128] [phone.config setCodecPriority:PhoneAudioVideoCodecSpeex priority:0]
```

- 5. How to register/unregister:
- first register or reregister after unregister can be triggered by:

```
[phone finalizeConfiguration]
```

- unregister simply by:

[phone unregister]

6. How handle registration status:

correct registration is handled in delegate's method

- (void)onRegistered:(NSInteger)accId

registration issue is handled in delegate's method

- (void)onRegistrationFailed:(NSInteger)accId statusCode:(int)statusCode statusText:(NSString\*)statusText unregistration is handled in delegate's method
- (void)onUnRegistered:(NSInteger)accId
- 7. How to make audio call:

```
[phone startCall:@"11111" withVideo:NO];
```

8. How to make video call:

```
[phone setRemoteView:viewRemoteVideo];
[phone setLocalView:viewLocalVideo];
[phone startCall:@"22222" withVideo:YES];
```

9. How to receive/reject incoming calls:

```
    answer call in audio mode with code (use SIP code for accepting call):
    [phone answerCall:callId status:200 withVideo:NO];
```

- answer call in video mode with code (use SIP code for accepting call):

[phone setRemoteView:viewRemoteVideo]; [phone setLocalView:viewLocalVideo]; [phone answerCall:callId status:200 withVideo:YES];

- decline call with code(use SIP codec for rejecting call)

[phone hangUpCall:callId status:486];

# 10. How to play ringtones

- for incoming calls(ring tone):

phone.config.ringToneUrl — string URI phone.config.enableRingTone - bool enable/disable

- for outgoing calls(ring back tone):

phone.config.ringBackToneUrl – string URI phone.config.enableRingBackTone - bool enable/disable

## 11. How to enable speaker, mute microphone in conversation mode

- to enable/disable speaker:

[phone setSpeakerphoneOn:callId status:YES];

- to mute/unmute microphone:

[phone muteMicrophone:callId on:YES];

## 12. How to send dial tone (DTMF)

[phone sendTone:callId tone:'8'];